

NAG Toolbox for MATLAB

x04cd

1 Purpose

x04cd prints a double triangular matrix stored in a packed one-dimensional array.

2 Syntax

```
[ifail] = x04cd(uplo, diag, n, a, form, title, labrow, rlabs, labcol,
               clabs, ncols, indent)
```

3 Description

x04cd prints a double triangular matrix stored in packed form, using a format specifier supplied by you. The matrix must be packed by column. The matrix is output to the unit defined by x04ab.

4 References

None.

5 Parameters

5.1 Compulsory Input Parameters

1: **uplo** – string

Indicates the type of the matrix to be printed

uplo = 'L' (Lower)

The matrix is lower triangular. In this case, the packed array **a** holds the matrix elements in the following order: (1, 1), (2, 1), ..., (**n**, 1), (2, 2), (3, 2), ..., (**n**, 2), .

uplo = 'U' (Upper)

The matrix is upper triangular. In this case, the packed array **a** holds the matrix elements in the following order: (1, 1), (1, 2), (2, 2), (1, 3), (2, 3), (3, 3), (1, 4), .

Constraint: **uplo** = 'L' or 'U'.

2: **diag** – string

Indicates whether the diagonal elements of the matrix are to be printed.

diag = 'B' (Blank)

The diagonal elements of the matrix are not referenced and not printed.

diag = 'U' (Unit diagonal)

The diagonal elements of the matrix are not referenced, but are assumed all to be unity, and are printed as such.

diag = 'N' (Non-unit diagonal)

The diagonal elements of the matrix are referenced and printed.

Constraint: **diag** = 'B', 'U' or 'N'.

3: **n** – int32 scalar

The order of the matrix to be printed.

If **n** is less than 1, x04cd will exit immediately after printing **title**; no row or column labels are printed.

4: **a(*) – double array**

Note: the dimension of the array **a** must be at least $\max(1, n \times (n + 1)/2)$.

The matrix to be printed. Note that **a** must have space for the diagonal elements of the matrix, even if these are not stored.

5: **form – string**

A valid Fortran format code. This may be any format code allowed on the system, whether it is standard Fortran or not. **form** is used to print elements of the matrix *A*. It may or may not be enclosed in brackets. Examples of valid values for **form** are 'F11.4', '1PE13.5', 'G14.5'.

In addition, there are two special codes which force x04cd to choose its own format code:

form = ' '

x04cd will choose a format code such that numbers will be printed with either an F8.4, an F11.4 or a 1PE13.4 format. The F8.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 1.0. The F11.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 9999.9999. Otherwise the 1PE13.4 code is chosen.

form = *

x04cd will choose a format code such that numbers will be printed to as many significant digits as are necessary to distinguish between neighbouring machine numbers. Thus any two numbers that are stored with different internal representations should look different on output. Whether they do in fact look different will depend on the run-time library of the Fortran compiler in use.

Constraint: the character length of **form** must be ≤ 80 .

6: **title – string**

A title to be printed above the matrix.

If **title** = ' ', no title (and no blank line) will be printed.

If **title** contains more than **ncols** characters, the contents of **title** will be wrapped onto more than one line, with the break after **ncols** characters.

Any trailing blank characters in **title** are ignored.

7: **labrow – string**

Indicates the type of labelling to be applied to the rows of the matrix.

labrow = 'N'

Prints no row labels.

labrow = 'I'

Prints integer row labels.

labrow = 'C'

Prints character labels, which must be supplied in array **rlabs**.

Constraint: **labrow** = 'N', 'I' or 'C'.

8: **rlabs(*) – string array**

Note: the dimension of the array **rlabs** must be at least **n** if **labrow** = 'C', and at least 1 otherwise.

If **labrow** = 'C', must contain labels for the rows of the matrix.

Labels are right-justified when output, in a field which is as wide as necessary to hold the longest row label. Note that this field width is subtracted from the number of usable columns, **ncols**.

9: **labcol – string**

Indicates the type of labelling to be applied to the columns of the matrix.

labcol = 'N'

Prints no column labels.

labcol = 'I'

Prints integer column labels.

labcol = 'C'

Prints character labels, which must be supplied in array **clabs**.

Constraint: **labcol** = 'N', 'I' or 'C'.

10: **clabs(*) – string array**

Note: the dimension of the array **clabs** must be at least **n** if **labcol** = 'C', and at least 1 otherwise.

If **labcol** = 'C', must contain labels for the columns of the matrix.

Labels are right-justified when output. Any label that is too long for the column width, which is determined by **form**, is truncated.

11: **ncols – int32 scalar**

The maximum output record length. If the number of columns of the matrix is too large to be accommodated in **ncols** characters, the matrix will be printed in parts, containing the largest possible number of matrix columns, and each part separated by a blank line.

ncols must be large enough to hold at least one column of the matrix using the format specifier in **form**. If a value less than 0 or greater than 132 is supplied for **ncols**, then the value 80 is used instead.

12: **indent – int32 scalar**

The number of columns by which the matrix (and any title and labels) should be indented. The effective value of **ncols** is reduced by **indent** columns. If a value less than 0 or greater than **ncols** is supplied for **indent**, the value 0 is used instead.

5.2 Optional Input Parameters

None.

5.3 Input Parameters Omitted from the MATLAB Interface

None.

5.4 Output Parameters

1: **ifail – int32 scalar**

0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

ifail = 1

On entry, **uplo** $\neq$ 'L' or 'U'.

ifail = 2

On entry, **diag** $\neq$ 'N', 'U' or 'B'.

ifail = 3

On entry, variable **form** is more than 80 characters long.

ifail = 4

The code supplied in **form** cannot be used to output a number. **form** probably has too wide a field width or contains an illegal edit descriptor.

ifail = 5

On entry, either **labrow** or **labcol** $\neq$ 'N', 'I' or 'C'.

ifail = 6

The quantity **ncols** – **indent** – *labwid* (where *labwid* is the width needed for the row labels) is not large enough to hold at least one column of the matrix.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

```

uplo = 'Lower';
diag = 'Non-unit';
n = int32(4);
a = [1;
      2;
      3;
      4;
      5;
      6;
      7;
      8;
      9;
      10];
format = ' ';
title = 'Example 1: ';
labrow = 'Integer';
rlabs = {'Uno '};
labcol = 'Integer';
clabs = {'Un '};
ncols = int32(80);
indent = int32(0);
[ifail] = ...
    x04cd(uplo, diag, n, a, format, title, labrow, rlabs, labcol, clabs,

```

ncols, indent)				
Example 1:				
	1	2	3	4
1	1.0000			
2	2.0000	5.0000		
3	3.0000	6.0000	8.0000	
4	4.0000	7.0000	9.0000	10.0000
ifail =	0			
