



## Installation and Configuration Guide

### **Sybase® IQ**

12.7

[ SUN SOLARIS ]

DOCUMENT ID: DC30066-01-1270-03

LAST REVISED: March 2007

Copyright © 1991-2007 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names used herein may be trademarks or registered trademarks of their respective companies.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# Contents

<b>About This Book .....</b>	<b>v</b>
<b>CHAPTER 1                      Preparing for Installation.....</b>	<b>1</b>
Sybase IQ editions .....	1
Sybase IQ components .....	2
System requirements .....	2
Configuration recommendations .....	2
Disk space .....	4
Swap space .....	4
RAM .....	5
Adjusting the operating system configuration.....	6
Managing shared memory.....	6
Setting file descriptor limits.....	7
Setting up raw devices for multiplex access.....	7
Verifying network functionality.....	7
Choosing file locations .....	8
Before you install Sybase IQ Server .....	9
<b>CHAPTER 2                      Installing Sybase IQ .....</b>	<b>15</b>
Installation overview .....	15
Installing Sybase IQ Extended Enterprise Edition.....	19
Installing Sybase IQ Enterprise Edition.....	26
Installing Sybase IQ Developer's Kit .....	26
Checking for product updates .....	26
Testing installed products .....	27
Running Sybase IQ ETL Server .....	27
Running Sybase IQ Server.....	27
<b>CHAPTER 3                      Installing Sybase IQ Client Components .....</b>	<b>33</b>
Installing client components on Linux .....	33
Installing client components on Windows.....	37
Before you install Sybase IQ client components .....	38
Installing Sybase IQ Extended Enterprise Client.....	39

	Installing Sybase IQ Network Client .....	43
	Installing without user interaction .....	43
<b>CHAPTER 4</b>	<b>Migrating Data .....</b>	<b>47</b>
	Upgrading non-multiplex databases .....	48
	Shutting down servers .....	48
	Installing IQ .....	48
	Starting the server .....	49
	Upgrading databases .....	49
	Enforcing referential integrity .....	50
	Starting the Sybase IQ Agent .....	51
	Verifying databases after upgrade .....	51
	Backing up databases after upgrade .....	51
	After you upgrade .....	52
	Running a mixed-version multiplex .....	52
	Upgrading 12.5 multiplex databases to 12.7 .....	53
	Upgrading 12.6 multiplex databases to 12.7 .....	57
	Migrating databases to a 64-bit system .....	60
	Restoring to your previous version after upgrade .....	61
	Upgrading Sybase IQ ETL .....	61
	Upgrading Sybase IQ ETL Server version only .....	62
	Upgrading Sybase IQ ETL Development .....	63
	Migrating across hardware platforms .....	64
<b>CHAPTER 5</b>	<b>Configuring Sybase IQ .....</b>	<b>67</b>
	Configuring the Sybase IQ Server .....	67
	Configuring client connectivity .....	69
	Connecting using JDBC .....	70
	Connecting using ODBC .....	71
	Connecting using OLE DB .....	78
	Connecting using Open Client .....	78
	Running client and server on the same system .....	79
	Network issues for IQ servers .....	80
	<b>Index .....</b>	<b>83</b>

# About This Book

## Subject

This book, *Sybase IQ Installation and Configuration Guide for Sun Solaris*, provides instructions for:

- Installing Sybase® IQ and Sybase IQ ETL Server
- Installing Sybase IQ Network Client and Sybase IQ ETL Development
- Migrating Sybase IQ data
- Configuring Sybase IQ and your operating system

## Audience

This guide is for system administrators, managers, or anyone who will be involved in setting up Sybase IQ.

## How to use this book

**Table 1: Guide to using this book**

To do this...	See...
Perform preinstallation tasks	Chapter 1, “Preparing for Installation”
Install Sybase IQ Server	Chapter 2, “Installing Sybase IQ”
Install Sybase IQ ETL Server	Chapter 2, “Installing Sybase IQ”
Install Sybase IQ Network Client	Chapter 3, “Installing Sybase IQ Client Components”
Install Sybase IQ ETL Development (Windows only)	Chapter 3, “Installing Sybase IQ Client Components”
Migrate data to a new Sybase IQ version, from 32-bit to 64-bit systems, and across hardware platforms	Chapter 4, “Migrating Data”
Configure Sybase IQ after installation	Chapter 5, “Configuring Sybase IQ”

## Related documents

The Sybase IQ documentation set includes the following documents:

- *Encrypted Columns in Sybase IQ*

Covers the use of user encrypted columns within the Sybase IQ data repository. You need a separate license to install this product option.

- 
- *Introduction to Sybase IQ*  
Includes hands-on exercises for those unfamiliar with Sybase IQ or with the Sybase Central™ database management tool.
  - *Large Objects Management in Sybase IQ*  
Explains storage and retrieval of Binary Large Objects (BLOBs) and Character Large Objects (CLOBs) within the Sybase IQ data repository. You need a separate license to install this product option.
  - *New Features in Sybase IQ 12.7*  
Lists new features and behavior changes.
  - *Sybase IQ Error Messages*  
Lists Sybase IQ error messages (referenced by SQLCode, SQLState and message text) and SQL preprocessor errors and warnings.
  - *ETL User's Guide for Sybase IQ*  
Describes how to transform data from data providers to data targets. Located on the Getting Started Sybase IQ 12.7 Extended Enterprise Edition CD.
  - *Sybase IQ Performance and Tuning Guide*  
Explains query optimization, design, and tuning issues for very large databases.
  - *Sybase IQ Reference Manual*  
Provides a full description of the SQL language, stored procedures, data types, and system tables supported by Sybase IQ.
  - *Sybase IQ Release Bulletin*  
Provides an overview of new features and last minute changes to the product and documentation. Read for help if you encounter a problem.
  - *Sybase IQ System Administration Guide*  
Covers administration issues such as database creation and load operations, data security and integrity, server start-up and connection, and multiplex operations.
  - *Sybase IQ Troubleshooting and Recovery Guide*  
Explains how to solve problems, perform system recovery, and repair databases.

- *Sybase IQ Utility Guide*

Provides Sybase IQ utility program reference material, such as available syntax, parameters, and options.

---

**Sybase IQ and Adaptive Server Anywhere**

Because Sybase IQ is an extension of Adaptive Server® Anywhere, a component of SQL Anywhere® Studio, IQ supports many of the same features as Adaptive Server Anywhere. The IQ documentation set refers you to SQL Anywhere Studio documentation where appropriate.

---

Documentation for Adaptive Server Anywhere:

- *Adaptive Server Anywhere Programming Guide*

Intended for application developers writing programs that directly access the ODBC, Embedded SQL™, or Open Client™ interfaces, this book describes how to develop applications for Adaptive Server Anywhere.

- *Adaptive Server Anywhere Database Administration Guide*

Intended for all users, this book covers material related to running, managing, and configuring databases and database servers.

- *Adaptive Server Anywhere SQL Reference Manual*

Intended for all users, this book provides a complete reference for the SQL language used by Adaptive Server Anywhere. It also describes the Adaptive Server Anywhere system tables and procedures.

You can also refer to the Adaptive Server Anywhere documentation in the SQL Anywhere Studio 9.0.2 collection on the Sybase Product Manuals Web site. To access this site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

**Other sources of information**

Use the Sybase Getting Started CD, the SyBooks CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.

- 
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

- The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

- Infocenter is an online version of SyBooks that you can view using a standard Web browser. To access the Infocenter Web site, go to Sybooks Online Help at <http://infocenter.sybase.com/help/index.jsp>.

## **Sybase certifications on the Web**

Technical documentation at the Sybase Web site is updated frequently.

### **❖ Finding the latest information on product certifications**

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click Certification Report.
- 3 In the Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Certification Report title to display the report.

### **❖ Finding the latest information on component certifications**

- 1 Point your Web browser to Availability and Certification Reports at <http://certification.sybase.com/>.
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
- 3 Select Search to display the availability and certification report for the selection.



❖ **Creating a personalized view of the Sybase Web site (including support pages)**

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click MySybase and create a MySybase profile.

**Sybase EBFs and software maintenance**

❖ **Finding the latest information on EBFs and software maintenance**

- 1 Point your Web browser to the Sybase Support Page at <http://www.sybase.com/support>.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.
- 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the “Technical Support Contact” role to your MySybase profile.

- 5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

**Typographic conventions**

Table 2 lists the typographic conventions used in this documentation.

---

**Table 2: Typographic conventions**

Item	Description
Code	SQL and program code is displayed in a mono-spaced (fixed-width) font.
User entry	Text entered by the user is shown in bold serif type.
<i>emphasis</i>	Emphasized words are shown in italic.
<i>file names</i>	File names are shown in italic.
database objects	Names of database objects, such as tables and procedures, are shown in bold, san-serif type in print, and in italic online.

## The sample database

Sybase IQ includes a sample database used by many of the examples in the IQ documentation.

The sample database represents a small company. It contains internal information about the company (employees, departments, and financial data) as well as product information (products), sales information (sales orders, customers, and contacts), and financial information (fin\_code, fin\_data).

The sample database is held in a file named *asiqdemo.db*, located in the directory *\$ASDIR/demo* on UNIX systems and *%ASDIR%\demo* on Windows systems.

## Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Sybase IQ 12.7 HTML documentation has been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

For information about accessibility support in the Sybase IQ plug-in for Sybase Central, see “Using accessibility features” in the *Introduction to Sybase IQ*. The online help for this product, which you can navigate using a screen reader, also describes accessibility features, including Sybase Central keyboard shortcuts.

---

**Configuring your accessibility tool**

You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool and see “Using screen readers” in *Introduction to Sybase IQ*.

---

For information about how Sybase supports accessibility, see Sybase Accessibility at <http://www.sybase.com/accessibility>. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

For a Section 508 compliance statement for Sybase IQ, go to Sybase Accessibility at <http://www.sybase.com/products/accessibility>.

**If you need help**

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.



# Preparing for Installation

About this chapter

This chapter describes preinstallation requirements and considerations.

Contents

Topic	Page
Sybase IQ editions	1
Sybase IQ components	2
System requirements	2
Setting up raw devices for multiplex access	7
Verifying network functionality	7
Choosing file locations	8
Before you install Sybase IQ Server	9

## Sybase IQ editions

Sybase IQ is available in the following editions:

**Table 1-1: Sybase IQ editions**

Name	Features	Installation instructions
Extended Enterprise Edition	Includes Sybase IQ plus ETL (extract, transform and load) capability	“Installing Sybase IQ Extended Enterprise Edition” on page 19
Enterprise Edition	Sybase IQ	“Installing Sybase IQ Enterprise Edition” on page 26
Developer’s Kit	Contains all features of Enterprise Edition but is licensed for internal development and testing purposes only. Limited for use on 1 CPU by a maximum of 5 seats.	“Installing Sybase IQ Developer’s Kit” on page 26

## Sybase IQ components

Each Sybase IQ edition includes two sets of products:

- To install components required for *operation as* a network server, install the Sybase IQ *Server Components*. See Chapter 2, “Installing Sybase IQ.”
- To install components required for *connection to* a network server, see Chapter 3, “Installing Sybase IQ Client Components.”

## System requirements

You must install the correct operating system patches required to run Sybase IQ. Sybase recommends that you update your operating system with the latest maintenance release and the patch level recommended by the manufacturer.

Sybase IQ is tested with the latest patches available at build time. For *minimum* operating system and patch level requirements, see the *Sybase IQ Release Bulletin*.

## Configuration recommendations

Before installing, check that your system has enough disk space and RAM. If you plan to use multiplex capability, you must also set up raw device access.

---

**Note** This table lists minimum requirements. Add more resources for larger numbers of active users.

---

To install and run Sybase IQ 12.7 on Solaris, you need:

**Table 1-2: Configuration recommendations**

<b>System Requirement</b>	<b>Recommendation</b>
Disk space to install and run Sybase IQ Server	308MB
Disk space to install Sybase IQ ETL Server	124MB
Disk space to install Open Client Developer's Kit 15.0	402MB
Disk space to install Sybase Central Java Edition 4.3	4MB
Disk space to install jConnect 5.5	17MB
Disk space to install jConnect 6.0	16MB
Disk space to install Java Runtime Environment 1.4.2	60MB
Disk space for databases	Site dependent
RAM	At least 1GB dedicated to Sybase IQ

Sybase Central Java Edition is a graphical administration tool for managing certain Sybase products, including IQ databases. When you install Sybase IQ, you also install the Sybase IQ plug-in, which enables Sybase Central to manage IQ databases.

To install and run the Sybase IQ plug-in and Sybase Central Java Edition as a UNIX or Linux client, you need:

**Table 1-3: Configuration recommendations for Sybase Central**

<b>System requirement</b>	<b>Recommendation</b>
Disk space for Sybase Central Java Edition	2MB free disk space
RAM for Sybase Central Java Edition	48MB
Resolution	800x600x256

**Note** The tables list minimum requirements. For larger numbers of active users, you will need more resources.

To install and run the Sybase IQ plug-in and Sybase Central Java Edition as a Windows client, you need:

**Table 1-4: Configuration recommendations for Sybase Central on Windows**

System Requirement	Recommendation
Processor	Pentium 400Mhz or greater
Disk space for Sybase Central Java Edition	3MB free disk space
RAM for Sybase Central Java Edition	48MB
Resolution	800x600x256

## Disk space

Use the `df -k` (disk free) command to see space available on your current device in kilobytes:

```
df -k
```

Compare the available disk space information from your machine to the required disk space requirements.

Here is sample output from a `df -k` command on a UNIX System V machine:

Filesystem	kbytes	used	avail	capacity	Mounted on
/dev/dsk/c0t3d0s0	61615	11890	43565	21%	/
/dev/dsk/c0t3d0s6	561630	231018	274452	46%	/usr
/proc	0	0	0	0%	/proc
fd	0	0	0	0%	/dev/fd
/dev/dsk/c0t3d0s5	61615	46426	9029	84%	/var
swap	1377464	120	1377344	0%	/tmp
/dev/dsk/c0t3d0s7	30807	10639	17088	38%	/opt
/dev/md/dsk/d10	23634496	17400102	5052674	77%	/tech1

The “*avail*” column shows the amount of disk space available on each file system.

## Swap space

Certain operations may cause the memory used by Sybase IQ to grow dynamically. Changing the way Sybase IQ uses buffers can dramatically change the way it uses memory. See the chapter “Managing System Resources” in the *Sybase IQ Performance and Tuning Guide* for more information about buffers.



Depending upon the load on the system where the Sybase IQ executable is running, swap requirements may exceed space allotted. Insufficient swap space may result in the system supporting fewer users, and large processes that cannot acquire sufficient swap space may be prematurely killed by the operating system.

See your operating system documentation for information about extending swap space.

## RAM

The recommended minimum RAM is 1GB.

To check the random access memory (RAM) available, use the following command (the first flag is a lowercase L):

```
% lsattr -l sys0 -E
```

keylock	normal	State of system keylock at boot time	False
maxbuf	20	Maximum number of pages in block I/O BUFFER CACHE	True
maxmbuf	2048	Maximum Kbytes of real memory allowed for MBUFS	True
maxuproc	200	Maximum number of PROCESSES allowed per user	True
autorestart	false	Automatically REBOOT system after a crash	True
iostat	true	Continuously maintain DISK I/O history	True
realmem	524288	Amount of usable physical memory in Kbytes	False
conslogin	enable	System Console Login	False
maxpout	0	HIGH water mark for pending write I/Os per file	True
minpout	0	LOW water mark for pending write I/Os per file	True
fullcore	false	Enable full CORE dump	

The realmem line gives the RAM available. (This example shows 524288KB, which is 524.288MB of RAM.) Sybase currently recommends at least 256MB of RAM for Sybase IQ.

To determine RAM available on a Sun system, type:

```
/etc/prtconf | head

System Configuration:  Sun Microsystems  sun4u
Memory size: 4096 Megabytes
System Peripherals (Software Nodes):
SUNW,Ultra-80
    packages (driver not attached)
    terminal-emulator (driver not attached)
    deblocker (driver not attached)
    obp-tftp (driver not attached)
    disk-label (driver not attached)
```

## Adjusting the operating system configuration

To configure the operating system correctly, you must:

- Install any required operating system patches
- Adjust system-wide parameters (such as shared memory parameters)

Installing kernel patches

See the *Sybase IQ Release Bulletin* for a list of any patches required to run Sybase IQ.

## Managing shared memory

Sybase IQ uses shared memory for two purposes:

- When the client and Sybase IQ are on the same system, shared memory is the default communication mechanism, not TCP/IP.
- When you specify the server command-line option `-iqwmem`, shared memory is used to provide wired memory.

You need to increase the default settings in `/etc/system` only if the `-iqwmem` option is used.

To increase the size of shared memory segments, follow these steps:

- 1 Log in as the superuser, usually “root”. All operating system tasks must be performed as “root”.
- 2 Adjust the maximum shared memory segment size parameter in the operating system kernel configuration file `/etc/system`.

The required amount for your buffer caches depends on how much memory your system has, the number of users, and the size of your databases. However, Sybase recommends that you specify a configuration for the largest amount of wired memory you expect your system to support. For example, you could create a shared segment to support a maximum physical memory of 3350MB for your system by adding the following line to the `/etc/system` file:

```
set shmsys:shminfo_shmmax=0xffffffff
```

Never set `shmmax` to a value greater than 7/8 of physical memory.

For more information about your kernel, see your operating system documentation.

- 3 Reboot your operating system.

## Setting file descriptor limits

Although the Solaris thread limit is not a problem, developers and Sybase field personnel should be aware that using the Solaris debugger on IQ requires a file descriptor for each thread in addition to the file descriptors for each dbspace. You need to adjust the number of file descriptors by means of the C shell limit command and by including `set rlim_fd_max=4096` in `/etc/system`.

## Setting up raw devices for multiplex access

This section applies only to users of multiplex capability. The Main IQ Store of a multiplex database should occupy raw disks on a shared disk subsystem, typically a fiber channel disk array. Make sure that raw disks are available with enough space to store all persistent data in the IQ database.

---

**Note** Be sure to configure your shared disk subsystem so that all systems where multiplex servers will reside can access the same physical disks as local drives. This access must not use remote drive mapping.

---

### Raw device setup on UNIX

On UNIX systems, system administrators should use the `chmod` command to give each user who runs the IQ server read/write access to the raw devices.

If your configuration includes Windows systems, see the *Sybase IQ Installation and Configuration Guide for Windows* for raw device setup instructions for those systems.

## Verifying network functionality

Sybase IQ uses networking software whenever the client and server components are installed on different systems.

- 1 Verify that the network is configured properly by using this command:

```
% telnet host
```

where *host* is the computer you are currently using. For example, if the host is called “tahoe”, enter:

```
% telnet tahoe
```

This should give you a login prompt for the same machine you are currently using, for example:

```
tahoe>
```

---

**Note** If telnet does not allow you to log in, there is a problem with your network. Ask your vendor technical support organization for assistance.

---

- 2 Check that you can log in over the network, then log out.
- 3 Use either rsh to open a remote shell or ping the system from another machine. For example, to check the system “tahoe”:

```
% rsh tahoe
% ping tahoe
```

## Choosing file locations

Before you install Sybase IQ, consider where to put your data.

Subsequent sections introduce file placement. For performance implications, see the chapter titled “Managing System Resources” in the *Sybase IQ Performance and Tuning Guide*.

Several types of files can be associated with each database:

- Database files
- Transaction log files
- Message log files

### Database files

For each database you create, Sybase IQ creates four files:

- A file for permanent IQ data, called the IQ Store (*filename.iq* by default)
- A file for temporary IQ data, for sorting and other internal uses (*filename.iqtmp*)
- A file for system information and your database schema, called the Catalog Store (*filename.db*)
- A message log file, (*filename.iqmsg*)

Each database file is called a **dbspace**. You may need to create additional dbspaces for your IQ data. Depending on your query needs, you may need more dbspaces for temporary data as well.

Make sure that you have enough disk space for your dbspaces. *Chapter 3, “Working with Database Objects”* in the *Sybase IQ System Administration Guide* includes a procedure for estimating the disk space you need for your IQ data. For the best performance, especially with larger databases, you should spread the dbspaces for your IQ data across multiple disks.

Consider carefully where you want to place your database files. To move a database file, you must do a full backup and restore of that database.

#### Placing databases in raw partitions

You can put a database file—that is, a dbspace—in either a file system file or a raw partition.

File systems simplify device management, but for multiplex databases, the Main IQ Store should be on a shared raw disk.

A raw partition can hold only one dbspace. The size of the dbspace is the size of the raw partition. However, you can add up to 2047 dbspaces, as long as each is stored on a different raw partition. You cannot store anything besides a main or temporary dbspace on the raw partition.

#### Transaction log

Sybase IQ records information it needs to recover from a system failure in the transaction log. The default file name extension for this file is *.LOG*. For the best security and performance, store the transaction log on a separate device from the database. A transaction log mirror on a separate device is also recommended for IQ databases.

#### Message log

The default file name extension for this file is *.iqmsg*. For a minor performance boost, store the IQ message log separately from the data files. The message log cannot be on a raw partition.

## Before you install Sybase IQ Server

You must uninstall previous versions of Sybase IQ, jConnect, Sybase Central, and Open Client before you install Sybase IQ Server. Please read this section carefully before installing or uninstalling. This section does not apply to Sybase IQ ETL Server or Sybase IQ ETL Development.

Plug-in requirements Sybase Central is installed on Solaris with the Sybase IQ Server and is also available as a Windows or Linux client for use with the Solaris server. For full Sybase Central functionality, this version of Sybase IQ Server requires a new version of the IQ plug-in, the IQ Agent (formerly ASIQ Agent), the Sybase Central Toolkit, and the Java Runtime Environment.

Check the following table before you install:

Table 1-5: Plug-in compatibility with Sybase IQ installed products

<b>IQ Plug-in</b>	<b>Sybase IQ</b>	<b>Sybase Central Toolkit</b>	<b>Agent</b>	<b>JRE</b>
12.7	12.5 and higher fully supported. Earlier IQ versions minimally supported.	4.3 or later required	12.7 Agent required	1.4.2 required
12.6	12.6 or 12.5 fully supported. Earlier IQ versions minimally supported.	4.3 or later required	12.6 Agent required	1.4.2 required
12.5	12.5 or earlier	3.2 required	12.5 Agent required	1.2.2 required (1.3.1 on Linux)

Running multiple IQ Agents In general, you cannot install Sybase IQ 12.6 or higher server components on a Sybase IQ 12.5 server without first uninstalling Sybase IQ 12.5. The exception is that you *can* install a standalone 12.6 or higher IQ Agent on a 12.5 server to manage a multiplex containing both 12.5 and higher-version servers (mixed-version multiplex). See “Running a mixed-version multiplex” on page 52 for more information.

To install a standalone IQ Agent on a 12.5 Sybase IQ server, use the sybinstall parameter -add\_agent. See “Upgrading 12.5 multiplex databases to 12.7” on page 53.

If desired, you can run a 12.5 IQ Agent and a higher version IQ Agent on the same machine, *as long as the agent version matches that of the connected server, and each has its own port number.*

To convert multiplex databases to Sybase IQ 12.7, you first must convert each query server to 12.7. After all query servers are converted, you must install the IQ Agent on the write server and convert the write server to 12.7. For details, see “Upgrading 12.6 multiplex databases to 12.7” on page 57.

Upgrading LONG BINARY columns Sybase IQ 12.6 and higher versions *do not support* existing LONG BINARY columns created using any release prior to Sybase IQ 12.5 ESD8. You must explicitly drop LONG BINARY columns before installing 12.7, and recreate them after installing. For details, see the appendix “Upgrading existing LONG BINARY columns” in the manual *Large Objects Management in Sybase IQ*.

**Preserving check constraints before database upgrade**

Sybase IQ 12.6 and higher versions enforce previously unenforced column and table CHECK constraints on updates, inserts, and loads of new data. Existing data in databases created with previous versions of Sybase IQ may contain unsupported constraints that now generate errors. (Databases created with previous versions of Sybase IQ are not deleted when you uninstall Sybase IQ and install a new version, but you need to upgrade each database to use the features of each new version.)

To find existing table data that violates a given constraint, create a query. For example, to find data that violates the constraint `C1 < 15`, run the following query:

```
SELECT COUNT(*) FROM TABLE x WHERE NOT (C1 < 15)
```

Sybase provides two special stored procedures to help you remove and recreate constraints. These stored procedures are located in the *scripts* subdirectory of %ASDIR%:

- The `sp_iqprintconstraints` procedure creates a script that you can run to recreate constraints. Commands are written to the server log, in the file *servername.nnn.SRVLOG* (where *nnn* is the number of times the server has been started) in the directory specified by \$ASLOGDIR).
- The `sp_iqdropconstraints` procedure drops all constraints on all IQ tables in database.

The steps that follow describe how to use these procedures.

---

**Note** You need only remove and recreate constraints once per upgrade to 12.6 or higher. You need not repeat this procedure for ESD releases and subsequent upgrades.

---

To avoid errors, follow these steps:

- 1 Install Sybase IQ 12.7. (Installing the product does not overwrite existing databases, which you must upgrade separately.)
- 2 Query the database to identify potential constraint violations.
- 3 Generate commands to recreate constraints in existing tables.
- 4 Run ALTER DATABASE UPGRADE as instructed in Chapter 4, “Migrating Data”.
- 5 Recreate constraints in the upgraded database.

After you run ALTER DATABASE UPGRADE on each database, run the command script(s) to recreate constraints.

For example, the following commands create the table rental, with a check constraint to validate that the date\_returned is later than the date borrowed.

```
CREATE TABLE rental (
    date_borrowed DATE NOT NULL,
    date_returned DATE,
    title CHAR(20)
    REFERENCES titles (id_num),
    CHECK( date_returned >= date_borrowed )
)
```

The sp\_iqprintconstraints procedure returns the following:

```
ALTER TABLE rental ADD CHECK date_returned >=
date_borrowed
```

#### Interoperability with installed products

If your system already has a version of one of the products to be installed, the installation proceeds as follows:

- If the product already installed has a newer date or version than the product installed with IQ, the installation does not install any older files.
- If the product already installed is older than the one included with IQ, the installation only installs newer files.
- When an older product exists, the IQ installation assumes that it is in use and omits it from the uninstall list. This prevents changing existing applications if you uninstall IQ.

#### Updating SDK

The Sybase IQ installation CD contains the Sybase Software Developer's Kit (SDK), which includes Open Client.

Sybase IQ recommends Open Client 15.0, EBF 13563. If your system already has this version installed as part of Adaptive Server Enterprise, Replication Server, or other Sybase products, you can skip installing the Open Client supplied with IQ 12.7.

Sybase recommends that you install Sybase IQ 12.7 in a clean directory for easier version management. Environmental variables are local to the shell and the subdirectories are specific to the versions.

The start\_asiq utility controls the version of the SDK used by Sybase IQ, and always sets it to the version installed by Sybase IQ.



The SYBASE\_OCS environment variable controls the version of the SDK used by other Sybase products. On UNIX platforms the behavior of setup files has changed regarding this variable.

In previous versions of Sybase IQ, running the setup procedure set the SYBASE\_OCS variable. If another installed Sybase product had already set the variable, the value was changed.

In Sybase IQ 12.7, running the setup procedure (*ASIQ-12\_7.csh* or *ASIQ-12\_7.sh*) only sets the variable if it is not already set. *If the value of SYBASE\_OCS has been set by another Sybase product, that value remains in effect unless you unset SYBASE\_OCS, and then run the source file.* See “Setting environment variables” on page 23 for details.

You can update the Sybase SDK (Open Client) as future versions become available, provided that you set the INSTALL\_ALL\_PATCH environment variable before installing the update.

To set the variable using the csh or C shell:

```
setenv INSTALL_ALL_PATCH "Y"
```

To set the variable using bash or Korn shell (ksh):

```
INSTALL_ALL_PATCH="Y"  
export INSTALL_ALL_PATCH
```



# Installing Sybase IQ

About this chapter

This chapter describes how to install the Sybase IQ server components.

Contents

Topic	Page
Installation overview	15
Installing Sybase IQ Extended Enterprise Edition	19
Installing Sybase IQ Enterprise Edition	26
Installing Sybase IQ Developer's Kit	26
Checking for product updates	26
Testing installed products	27

There are two ways to install Sybase IQ:

- For *operation as a network server*, install the Sybase IQ *Server Components* on your Sun Solaris system. See “Installing Sybase IQ Extended Enterprise Edition” on page 19.
- For *connection to a network server*, see Chapter 3, “Installing Sybase IQ Client Components.”

## Installation overview

For supported platform and operating system configurations and required patches, see the *Sybase IQ Release Bulletin*.

To install Sybase IQ Server Components, run the installation program on the product CD. For UNIX systems, the program is called sybinstall.

The installation program installs:

- Sybase IQ Server 12.7
- Sybase IQ ETL Server 4.2.1. You may optionally install this if you have the Sybase IQ Extended Enterprise Edition.

- Sybase Central Java Edition viewer 4.3 (the graphical administration tool) and the latest plug-in for Sybase IQ. For details about using Sybase Central, see its online help.
- Software Developer's Kit (SDK) which provides Open Client connections for ASE servers.
- The Sybase jConnect JDBC Driver, version 5.5. The installation includes a recent EBF. If you install the jConnect driver, Java classes installed into a database can make JDBC calls to access and modify data. You need TCP/IP to use the jConnect driver.

The Sybase jConnect JDBC Driver version 6.0 is optionally available, but Sybase IQ requires jConnect 5.5 in order to work with Sybase Central and other java components. If you install jConnect 6.0 without installing 5.5, Sybase IQ functionality will be incomplete.

- Java Runtime Environment 1.4.2.

You may deselect unneeded components before installing, except for SDK (Open Client), which is required.

---

**Warning!** If you have an existing version of Open Client on your system, installing Open Client will add missing Open Client files and overwrite older files.

---

If you have a previous 12.x version of Sybase IQ, you need to upgrade your databases as part of installation. See "Upgrading non-multiplex databases" on page 48 for important steps you must complete before installing.

To install the Server Components, you must:

- 1 Mount the CD and set up the sybase account.
- 2 Prepare the installation directory.
- 3 Run the sybinstall utility from the Sybase IQ product CD (Extended Enterprise Edition, Developer's Edition, or Enterprise Edition).
- 4 Set environment variables. (Sybase IQ Server installation only.)
- 5 Unmount the CD.

The sections that follow describe each of these tasks.

**❖ Mounting the product CD and setting up the sybase account**

- 1 If your CD has been set up for auto-mount, you must get the absolute pathname for this device from the System Administrator. In this case, change directory to this specified directory and skip to the procedure titled “To prepare the installation directory” on the following page. Otherwise follow all the steps to load the Sybase IQ software from a CD.
- 2 Log on as the user “root”.
- 3 Place the CD into the CD drive.
- 4 Create a subdirectory of the root directory where you will mount the CD, if one does not already exist. For example:

```
% cd /  
% mkdir /cdrom
```

- 5 If your system does not auto-mount, mount the CD with a command like the following:

```
% mount -o -ro -F hsfs device_name /cdrom
```

where *device\_name* is the name of the CD drive and */cdrom* is the name of the directory where the CD will be mounted.

- 6 If there is no “sybase” account on your system, set one up to perform all unloading tasks. (Setting up this account requires “root” privileges.)

It is important to maintain consistent ownership and privileges for all files and directories. A single user with read, write, and execute permissions should perform all Sybase IQ unload, installation, upgrade, and setup tasks.

The “sybase” user must have permission privileges from the top (or root) of the disk partition or operating system directory down to the specific physical device or operating system file.

- 7 Log out as “root” and type “exit”.

**❖ Preparing the installation directory**

- 1 Log on as the “sybase” user. This command logs into system *storm*:

```
% rlogin -l sybase storm
```

- 2 Identify or create a directory location for the Sybase installation directory, where you install the Sybase IQ product. The “sybase” user should be the owner of the directory. If you have other Sybase products installed, Sybase recommends that you install Sybase IQ in its own separate directory, not the \$SYBASE directory used by another product. To create a directory, use a command like the following:

```
% mkdir cd-install;chmod 777 cd-install
```

- 3 Run the “disk free” command to verify that the directory location for the Sybase installation directory is in a UNIX file system with enough space to accommodate the software.

```
df -k .
```

Check the amount of free space against Table 1-2 on page 3.

- 4 Set the SYBASE environment variable to the path of the installation directory you have chosen for Sybase IQ, using the following formats. In these examples, the SYBASE installation directory is */work/server*

- For the C shell (csh), add this line to the *.cshrc* file:

```
setenv SYBASE /work/server
```

- For the Korn (ksh) or Bourne (sh) shell, add this line to the *.profile* file:

```
SYBASE=/work/server;  
export SYBASE
```

- 5 Use the `ls -la` command to verify that you have permission to read, write and execute in the Sybase installation directory.

#### ❖ Running the *sybinstall* utility

- 1 Change directory to the installation directory:

```
% cd $SYBASE
```

- 2 Start the install utility, *sybinstall*:

```
% /cdrom/sybinstall
```

- 3 Follow the instructions at “Installing Sybase IQ ETL Server” on page 19 or “Installing Sybase IQ Server” on page 20

# Installing Sybase IQ Extended Enterprise Edition

The Sybase IQ Extended Enterprise Edition CD contains two products:

- Sybase IQ ETL
- Sybase IQ Server

If you do not require ETL capability, skip to “Installing Sybase IQ Server” on page 20.

## ❖ Installing Sybase IQ ETL Server

Sybase IQ ETL Server provides Extract/Transform/Load capability for Sybase IQ.

- 1 Run sybinstall as described in “Running the sybinstall utility” on page 18.
- 2 Type the number 1 on the Welcome screen and press Return.

A message similar to the following displays:

```
Sybase IQ ETL Server 4.21 Build 2327
```

- 3 The procedure displays a list of countries or regions. Type the number that appears beside your country or region. The license agreement displays in your language.
- 4 Press the spacebar or Return to scroll through the agreement until you reach the end where a Y/N prompt displays.

Type “Y” to accept the license terms and continue the installation. If you disagree with the terms of the license, type “N” and press Return, which exits the installation procedure.

- 5 After a message about verifying the archive integrity displays, you can specify the installation directory.

The procedure displays the default directory, for example:

```
Installation directory  
[/disk1/SYBASE/SybaseIQETLServer]
```

You must have write permission in the installation directory. Accept the default or type the target directory you prefer and press Return. Sybase recommends that installation paths contain only alphanumeric characters.

- 6 Type “Y” to create the directory if it does not exist or to overwrite an existing target directory. Type “N” to exit the installation.
- 7 If you typed “Y”, the procedure begins and lists the amount of space required. For example:

Space needed for installation: 127490 KB

- 8 After installation, you must configure the package. Type “Y” to configure the package immediately. Type “N” to exit. You can configure the package later by running `./configure.sh` in `$SYBASE/SybaseIQETLServer`.

The following message indicates a successful installation.

Installation complete

To begin using Sybase IQ ETL, see *ETL User’s Guide for Sybase IQ* (DC00608-01-0421-01). This document is available online and on the Getting Started Sybase IQ 12.7 Extended Enterprise Edition CD.

- 9 Press Return to return to the main menu.
- 10 Enter “Q” to quit the install or “2” to install Sybase IQ Server. See the next procedure to install Sybase IQ Server.

#### ❖ Installing Sybase IQ Server

- 1 Run `sybinstall` as described in “Running the sybinstall utility” on page 18.

---

**Note** You can optionally use parameters on the `sybinstall` command line to simplify Sybase IQ Server installation. See “Bypassing sybinstall menus” on page 24.

---

- 2 On the Welcome screen:
  - If installing Sybase IQ Enterprise Edition, press Return to continue.
  - If installing Sybase IQ Extended Enterprise Edition, enter “2” and press Return, then press Return again at the second Welcome screen.
- 3 If you have previously installed Sybase IQ, the script first displays information about servers currently running. This screen ends with the message:

The above IQ servers have been found running on this system. Please check that all IQ servers running in \$SYBASE directory have been shut down before continuing. Do you want to continue <Y/N>?

- 4 If any of the listed servers are running in the `$SYBASE` directory, enter “N” to exit the install and make sure the server(s) are shut down before you continue. If the servers are not running in the `$SYBASE` directory, enter “Y.”
- 5 Type the number that corresponds to the location where you are installing.



If the country where you are located is not listed, select the most appropriate area ('Americas (Mid/So.)', 'Asia Pacific', 'Europe, Middle East, Africa', or 'Other Locations').

If you don't find a license agreement that matches your location, or if the license agreement is unreadable on your system, you can read all available license agreements at the Sybase website at <http://www.sybase.com>, and rerun *sybinstall* passing it the parameter `-l_accept_sybase_license`. For example:

```
%/cdrom/sybinstall -l_accept_sybase_license
```

- 6 The first screen of the License Agreement for your location displays. As you read, hold down the Return key to scroll until you reach the end of the agreement.

When you have read the complete agreement, you will see a prompt. To accept the license terms and continue the installation, enter "Y." If you disagree with the terms of the license, enter "N," which exits the installation procedure.

- 7 The script next lists the amount of space available in your \$SYBASE directory and the amount of space required to install Sybase IQ and all of its associated products.
- 8 To accept the default, enter "S."

*By default, all six products are installed. You must install SDK (Open Client) 15.0 (or have it already installed) in order to start Sybase IQ.*

- 9 To deselect or change any of the installed products, type the option number at the prompt. For example, to deselect Sybase Central Java Edition, enter "3." Deselected product(s) will not be installed.

If Adaptive Server Enterprise is on the same system as Sybase IQ, you must maintain the environment for each product separately and correctly.

You can only deselect one product per screen. The screen displays again with the words "Not Selected" under the Install directory for each deselected product.

Numbers 1 through 6 are toggle options. If you change your mind, type the number of a deselected product to reselect it.

- 10 Check the Install Directory listed *for each product to be installed*. If the installation does not default to the desired directory, enter "C" and type the target directory you prefer at the Enter new target directory prompt.

- 11 After selecting products, enter “S” to start the installation.
- 12 Before installing files, sybinstall displays the Setup Utility Database screen. The utility database (*utility\_db*) never holds data. It is used in special cases when the server needs a connected database but either no database exists or none should be running, for example, when restoring a database. Connecting to *utility\_db* allows you only a narrow range of specialized file manipulation statements: CREATE DATABASE, DROP DATABASE, and RESTORE DATABASE. For more information, see “Utility database server security” in *Sybase IQ System Administration Guide*.

The ascii file that holds the login and password for this database is *\$ASIQ\_DIR/bin/util\_db.ini*. By default, the login is “DBA” and the password is “SQL”. You can change the login and password by responding to the prompt:

```
Do you want to change the current user and password
<Y/N>?
```

To change the login and password, type “Y”. The installation procedure prompts you for a new login, then a password. If you do not wish to change the default login or password, type “N.”

- 13 The procedure begins copying files. As the procedure installs each product selected, it displays a list of the files installed. This may take a few minutes. When finished, the following message displays:

```
Product install completed.
Press <Return> to continue:
```

Press Return.

- 14 After installing the required components, the install procedure prompts for optional components and keys.

```
Enter Component :
```

If you have no optional components, press Return and type “N” when prompted to enter another component.

To install optional components, type the component (for example, LOB for Large Object or ENC for Column Encryption). The procedure then prompts for the key.

```
Enter Key :
```

Now type the installation key exactly as it appears on your installation key document. Entering the key returns the message <Component> enabled!.

When the installation completes, a message lists environment setup files created.

- 15 If installing Sybase IQ Extended Enterprise Edition, press Return to return to the main menu. Type “Q” to exit the installation program.

#### ❖ **Completing the installation**

- 1 Print and read the appropriate Readme file.

For Sybase IQ ETL, the Readme file displays when you install IQ ETL Development. (See “Installing Sybase IQ ETL Development” on page 40.)

For Sybase IQ Server, see *\$ASDIR/readme.txt*.

- 2 Log on as the “root” user and unmount the CD (if you had to mount to begin the installation):

```
% umount /cdrom
```

- 3 Remove the CD from the drive.
- 4 If you installed Sybase Central, see the *Sybase IQ System Administration Guide* for instructions on configuring and running the IQ Agent. You must configure and run the IQ Agent in order to manage multiplexes with Sybase Central.
- 5 Set the environment variables as described in “Setting environment variables” on page 23
- 6 Log out.

---

**Note** After installing the software, Sybase strongly recommends that you check the online support Web site for software updates. If a software update (EBF) has been released, it contains bug fixes made after this product shipped.

---

#### ❖ **Setting environment variables**

You must set certain environment variables to run the Open Client Developer’s Kit and Sybase IQ Server. Sybase IQ installs environment files that you can run to set variables.

- 1 If you plan to run Open Client and Sybase IQ on the same system, skip to Step 2.

To run Open Client Developer's Kit on a standalone system, perform this step.

bash or Korn (ksh) shell users should enter:

```
% . $SYBASE/SYBASE.sh
```

tcsh or C (csh) shell users should enter:

```
%source $SYBASE/SYBASE.csh
```

- 2 The environment files that set Sybase IQ variables also set the variables needed by Open Client.

bash or Korn (ksh) shell users should enter:

```
%source $SYBASE/ASIQ-12_7/ASIQ-12_7.sh
```

tcsh or C (csh) shell users should enter this command:

```
%source $SYBASE/ASIQ-12_7/ASIQ-12_7.csh
```

These procedures set the ASDIR environment variable used to start and test Sybase IQ. To test Sybase IQ, see "Running Sybase IQ Server" on page 27.

#### ❖ **Bypassing sybinstall menus**

When installing Sybase IQ Server, you can run the sybinstall utility as a series of menus with prompts or bypass menus using the *sybinstall* command line parameters. These optional parameters do not apply to the Sybase IQ ETL Server installation.

- 1 Choose one or more of the parameters in Table 2-1.

**Table 2-1: Optional sybinstall parameters for Sybase IQ Server installation**

Parameter	Function
-add_agent	Install standalone IQ Agent. Use only on systems where IQ is already installed. Do not combine with any other parameters.
-add_license	Install options ordered and licensed separately.
-autoinstall	Install all defaults.
-dst <source/CD-directory>	Install in specified directory
-help	Display all parameters and usage.
-l_accept_sybase_license	Bypass license agreement prompt.
-info version	Display information about this product.
-products	Specify product(s) to install. Products not listed are ignored. If a parameter is omitted, all products are installed or selected by user menu selection. Products are: <ul style="list-style-type: none"> <li>• IQ — Sybase IQ</li> <li>• OC — Open Client</li> <li>• SC — Sybase Central</li> <li>• JC5 — jConnect 5.5</li> <li>• JC6 — jConnect 6.0</li> <li>• JRE — Java Runtime Environment</li> </ul>
-src <source/CD-directory>	Specify directory from which to install.
-y	Assume “yes” to all questions, warnings, and errors.

## 2 Specify the parameters on the command line.

The following command runs sybinstall with all menus and prompts, so that you can choose the components installed.

```
% /cdrom/sybinstall
```

The following command runs sybinstall so that it updates Sybase Central and Sybase IQ:

```
% /cdrom/sybinstall -autoinstall -update -products
"IQ SC" -y
```

The installation procedure log is created in \$SYBASE/sybinstall.log. If the file cannot be created in the \$SYBASE directory, it defaults to /tmp/sybinstall.log.

## Installing Sybase IQ Enterprise Edition

The Sybase IQ Enterprise Edition CD contains only Sybase IQ Server and supporting product components. To install Sybase IQ Enterprise Edition, follow the steps in “Installation overview” on page 15 and “Installing Sybase IQ Server” on page 20.

## Installing Sybase IQ Developer’s Kit

The Sybase IQ Developer’s Kit CD contains only Sybase IQ Server and supporting product components. To install Sybase IQ Developer’s Kit, follow the steps in “Installation overview” on page 15 and “Installing Sybase IQ Server” on page 20.

## Checking for product updates

After you install the software, Sybase strongly recommends that you check the online support Web site for software updates. If a software update (EBF) has been released, it contains bug fixes made after this product shipped.

### ❖ Finding the latest information on EBFs and software updates

- 1 Point your Web browser to the Sybase Support Page at <http://www.sybase.com/support>.
- 2 Select EBFs/Maintenance. Enter user name and password information, if prompted (for existing Web accounts) or create a new account (a free service).
- 3 Select a product.
- 4 Specify a time frame and click Go.
- 5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

## Testing installed products

Now you are ready to test your Sybase IQ installation. This section tells how to start Sybase IQ ETL Server and Sybase IQ Server.

### Running Sybase IQ ETL Server

To start Sybase IQ ETL Server, change to the Sybase IQ ETL installation directory (default *opt/SYBASE/SybaseIQETLServer*) and run the following command:

```
% GridNode.sh
```

This command starts the server with the default port 5124. To change the port, use the `-port` parameter, for example, to change the port to 1234:

```
% GridNode.sh -port 1234
```

For a complete overview, see the *ETL User's Guide for Sybase IQ* on the Getting Started CD.

### Running Sybase IQ Server

This section tells how to start and stop Sybase IQ Server with the sample database.

Starting the sample database

To start Sybase IQ Server, change to a directory where you have write privileges and run the `start_asiq` utility, using the following command format:

```
start_asiq @configuration_filename.cfg dbname.db
```

This command starts the database and sets parameters named in the (optional) configuration (*.cfg*) file.

---

**Note** If Adaptive Server Anywhere is installed on the same subnet as Sybase IQ, you must change the default port number for IQ; both products use the default port of 2638. First, set a new port number in the `$ASDIR\scripts\default.cfg` file. Then update each IQ database configuration file (for example, `$ASDIR\demo\asiqdemo.cfg`) by changing the port number in the following line:

```
-x tcpip{port=2638}
```

Change to an unused number, for example, 4444:

```
-x tcpip{port=4444}
```

---

You can use a configuration file to specify options that you want to set whenever you start your server. A configuration file for the sample database is installed in the *\$ASDIR/demo* directory as an example. For details about configuration files, see “Configuring the Sybase IQ Server” on page 67.

---

**Note** The directory where the server is started becomes the default directory for all server files created by Sybase IQ.

---

For example, to start the sample database installed with the product, you could use these commands:

```
% cd $ASDIR/demo
% start_asiq @asiqdemo.cfg asiqdemo.db
```

---

**Note** The server name may not start with a number.

---

#### Startup parameters

Startup information, which includes the version of Open Client in use, is saved in the *stderr* log. Output from *start\_asiq* ends with this line:

```
Server started successfully
```

For more information, see the *Sybase IQ System Administration Guide*.

---

**Note** If you run the *start\_asiq* utility from *\$ASDIR/bin*, the script changes directory to “*./.*” to avoid creating database files in the */bin* directory.

---

Using defaults in *\$ASDIR/scripts/default.cfg*, the *start\_asiq* utility sets any required environment variables that have not been set and sets parameters that govern Sybase IQ to the recommended defaults. (You may use a configuration file to override these defaults.) *If you start your server using any command other than start\_asiq, or if your configuration file is encrypted, you must specify the following parameters:*



**Table 2-2: Parameters set by start\_asiq**

Parameter	Value	Description
-c	48MB	Catalog store cache size
-gc	20	Checkpoint interval
-gd	all	Allows all users to start the database by connecting
-gl	all	Allows all users to load or unload tables
-gm	10	Default number of connections
-gp	4096	Catalog store page size
-ti	4400	Client time-out set to 72 hours. Prevents users with long queries from being logged off over a long weekend.

---

**Note** On the start\_asiq command line, the last option specified takes precedence, so if you want to override your configuration file, list any options you want to change *after* the configuration file name. For example:

```
start_asiq @asiqdemo.cfg -x 'tcpip{port=1870}'  
asiqdemo.db
```

The -x parameter here overrides connection information in the *asiqdemo.cfg* file.

---

For a complete list and description of startup parameters, see “The database server” in Chapter 2 of *Sybase IQ Reference Manual*.

---

**Note** Do not discard this document after installing Sybase IQ. You may need these required parameters later.

---

If you have Sybase Central, you may use the Start Database Server wizard, as documented in *Introduction to Sybase IQ*, instead of start\_asiq.

---

**Note** On UNIX systems, always run Sybase Central Java and dbisql using the default colors of the Common Desktop Environment. Running these products under Open Windows or changing the default colors may cause display problems.

---

The server process runs in the background. It sends output to a server log file, *\$ASLOGDIR/servername.NNN.srvlog* where *NNN* is the number of times the server has been started. For example, *\$ASLOGDIR/fiona.123.srvlog*.

---

## Creating databases

The sample database, *asiqdemo*, is installed in the *\$ASDIR/demo* directory.

To create your own databases, start and connect to the utility database, as described in Chapter 3. See *Sybase IQ System Administration Guide* for complete instructions.

## Running queries

Follow the “Quick start” directions in the *readme.txt* file to run Interactive SQL queries in the sample database.

## Stopping the server

To stop a server, run the `stop_asiq` command, for example:

```
stop_asiq
```

```
Checking system for IQ 12 Servers ...
```

```
The following 2 server(s) are owned by 'kthayer'
```

```
##      Owner      PID   Started   CPU_Time
--  -----  -
1:    kthayer    4378  10:34:42      0:04
start_asiq -gn 25 @asiqdemo.cfg asiqdemo.db -o /c
--

2:    kthayer    4726  10:41:09      0:04

start_asiq -gn 25 @jd_banking.cfg jd_banking.db -o /c
--
```

Please note that 'stop\_asiq' will shutdown a server completely without regard for users, connections or load process status. For a finer level of detail the utility 'dbstop' has the options to control whether a server is stopped based on active connections.

```
Enter the server to shutdown ('1'...'2') or 'Q' to Quit:
```

```
2
```

```
Shutting down server ...
```

Checkpointing server .....

Server shutdown.

Managing processes

The `stop_asiq -agent` command lets you stop the IQ Agent on your Unix or Linux system. This is compatible with Sybase IQ 12.5 if you have ESD8 or above installed.

Stopping servers in  
cron or at jobs

To use `stop_asiq` in a cron or at job, specify the utility with the appropriate `-stop` option:

```
stop_asiq -stop one
```

Setting `-stop one` shuts down a single server, when exactly one running server was started by the user ID that starts the cron or at job. This prevents accidentally shutting down the wrong server if several are running.

```
stop_asiq -stop all
```

You can specify both options on the same command, for example:

```
stop_asiq -agent -stop all
```

Setting `-stop all` shuts down all servers that were started by the user ID that starts the cron or at job.

---

**Note** You must specify the full pathname to the `stop_asiq` executable in the cron statement.

---

For complete `stop_asiq` syntax, see the *Sybase IQ Utility Guide*.

Other ways to stop  
servers

There are other ways to stop an IQ database server:

- Run the Interactive SQL (DBISQL) STOP ENGINE command
- Select the server name and choose Stop from the dropdown in Sybase Central. For details, see the *Introduction to Sybase IQ*.
- Run the Stop utility, documented in the *Sybase IQ Utility Guide*.



# Installing Sybase IQ Client Components

About this chapter

This chapter explains how to install Sybase IQ client components, available on two platforms.

Contents

Topic	Page
Installing client components on Linux	33
Installing client components on Windows	37

## Installing client components on Linux

---

**Note** Sybase IQ ETL Development client is currently available only on Windows systems. Sybase IQ Network Client is available on both Linux and Windows.

---

Sybase IQ Network Client for Linux contains the components required for *connection* to a network server. The 32-bit client is compatible with IQ servers on all supported server platforms; there is no 64-bit client.

Sybase IQ Network Client for Linux is certified to run on:

- Red Hat Enterprise Linux 3.0 i86 or AMD64, Advanced Server or Workstation Edition:
  - kernel 2.4.21-27.0.2.ELsmp #1 SMP and glibc 2.3.2-95.30 on 32-bit systems
  - kernel 2.4.21-27.0.2.ELhugemem #1 SMP and glibc 2.3.2-95.30 on 64-bit systems
- Red Hat Enterprise Linux 2.1 x86, Advanced Server or Workstation, with kernel 2.4.9-e.40smp and glibc 2.2.4-32.8.
- SuSE Linux Enterprise Server (SLES) 8.0, kernel 2.4.9-e.57smp #1 SMP and glibc 2.2.4.-32.18

- SuSE Linux Enterprise Server (SLES) 9.0 for 32-bit systems, kernel 2.6.5-7.97-smp #1 SMP and glibc 2.3.3-98.28

Sybase IQ Network Client is also compatible with Red Flag Linux DB Server release 4.0, kernel 2.4.21-AS.2 smp on i686 and glibc 2.2.93.

---

**Note** Sybase IQ Network Client does not run on IBM Linux on POWER.

---

Table 3-1 demonstrates that you can run different versions of Sybase IQ on the same system.

**Table 3-1: Linux client/server downward compatibility**

Product and version to install	Product and version already installed	Compatibility
12.7 Server	12.5 Server	Standalone IQ Agent only
	12.5 Network Client	Allowed, provided that environment for each is set up for the appropriate version
	12.6 Network Client	Allowed as an upgrade
12.7 Network Client	12.5 Server	Allowed, provided that environment for each is set up for the appropriate version
	12.5 Network Client	Allowed. If one is uninstalled, user must repair remaining one.
	12.6 Server	Prohibited

Table 3-2 lists disk space required to install Sybase IQ Network Client for Linux.

**Table 3-2: Sybase IQ Network Client disk space requirements on Linux**

Product	Disk space
Sybase IQ 12.7 Network Client	275MB
Sybase Central Java Edition 4.3	4MB
jConnect 5.5	17MB
jConnect 6.0	6MB
Java Runtime Environment 1.4.2	60MB

The following procedure describes how to install the Sybase IQ Network Client for Linux. To install Sybase IQ Network Client for Windows or Sybase IQ ETL Development, see “Installing client components on Windows”. To install the Sybase IQ Server Components, see Chapter 2, “Installing Sybase IQ.”

#### ❖ Running the *sybinstall* utility

If this is the first Sybase product you have installed, see “Mounting the product CD and setting up the sybase account” on page 17 and “Preparing the installation directory” on page 17.

- 1 Change directory to the installation directory:

```
% cd $SYBASE
```

- 2 Start the install utility, *sybinstall*. You can run this utility as a series of menus with prompts, or bypass menus using the *sybinstall* command line parameters.

**Table 3-3: Command parameters for *sybinstall* utility**

Parameter	Function
-add_agent	Install standalone 12.7 IQ Agent only
-autoinstall	Install all defaults
-help	Display all parameters and usage
-l_accept_sybase_license	Bypass license agreement prompt when using -autoinstall
-info version	Display information about this product
-y	Assume “yes” to all questions, warnings, and errors

The following command runs *sybinstall* with all menus and prompts, so that you can choose the components installed:

```
% /cdrom/sybininstall
```

The following command runs sybininstall so that it installs the default products:

```
% /cdrom/sybininstall -autoinstall  
-I_accept_sybase_license
```

The installation procedure log is created in \$SYBASE/sybininstall.log. If the file cannot be created in the \$SYBASE directory, it defaults to /tmp/sybininstall.log.

Avoid installing Sybase IQ Network Client in the same directory as an IQ server. If you attempt to do this, an error like the following displays:

```
WARNING
```

```
The directory '/olddev1/users/sybase_scr/ASIQ-12_7'  
contains files for the ASIQ server. This install  
contains only the network client files and should  
never be installed in the same directory as an  
existing server.  
Please make sure that /remote/ase/linux is set to the  
correct directory
```

```
Do you want to continue <Y/N>?
```

The following steps show the menus that *sybininstall* displays by default.

To enter a response, type the desired letter or number, then press Return.

- 3 On the Welcome screen, press Return to continue.
- 4 Type the number that corresponds to the location where you are installing.

If you find no license agreement that matches your location, or if the license agreement is unreadable on your system, you can read all available license agreements at the Sybase Web site at <http://www.sybase.com>, and rerun *sybininstall*, passing it the parameter `-I_accept_sybase_license`. For example:

```
% /cdrom/sybininstall -I_accept_sybase_license
```

The first screen of the Software Test and Evaluation License Agreement displays.

- 5 As you read, hold down the Return key until you reach the end of the agreement.

At the end of the agreement, a prompt appears.



- 6 Type “Y” to accept the license terms and continue the installation. If you disagree with the terms of the license, type “N.”

The script next lists the amount of space available in your \$SYBASE directory, and the amount of space required for the three components it installs.

- 7 To install all four products, type “S.” To deselect or change any of the installed products, type the option number at the prompt. For example, to deselect Sybase Central Java Edition, type “2.”

Deselected products are not installed. You can deselect only one product per screen. When you deselect a product, the screen displays again with the words “Not Selected” under the Install directory for that product.

---

**Note** Numbers 1 through 4 are toggle options. If you change your mind, type the number of a deselected product to reselect it.

---

- 8 After selecting products, type “S” to start the installation.

As the procedure installs each product selected, it displays a list of the files installed. This may take a few minutes. When the installation completes, a message lists environment setup files created.

❖ **Setting environment variables**

You must set certain environment variables to run Sybase IQ. Sybase IQ installs environment files that you can run to set variables.

- 1 bash or Korn (ksh) shell users should type:

```
% source $SYBASE/ASIQ-12_7/ASIQ-12_7.sh
```

- 2 tcsh or C (csh) shell users should type:

```
% source $SYBASE/ASIQ-12_7/ASIQ-12_7.csh
```

## Installing client components on Windows

Client components are those required for *connection* to a network server. You can install:

- Sybase IQ Network Client – see “Installing Sybase IQ Network Client” on page 43.

- Sybase IQ ETL Development (Sybase IQ Extended Enterprise Edition only) – see “Installing Sybase IQ Extended Enterprise Client” on page 39.

## Before you install Sybase IQ client components

Sybase IQ 12.7 ETL Development is certified to run on:

- Microsoft Windows 2003 (Service Pack 1)
- Microsoft Windows 2000 (Service Pack 4)
- Microsoft Windows XP Professional (Service Pack 2)

Sybase IQ 12.7 Network Client is certified to run on:

- Microsoft Windows 2003 (Service Pack 1)
- Microsoft Windows 2000 (Service Pack 4)
- Microsoft Windows 98 SE
- Microsoft Windows ME
- Microsoft Windows XP Professional (Service Pack 2)

**Table 3-4: Windows client/server downward compatibility**

Product and version to install	Product and version already installed	Compatibility
12.7 Server	12.5 Server	Standalone IQ Agent only
	12.5 Network Client	Prohibited
	12.6 Network Client	Prohibited
12.7 Network Client	12.5 Server	Prohibited
	12.5 Network Client	Prohibited
	12.6 Server	Prohibited

See Table 3-5 for disk space required to install and run Sybase IQ client components for Windows.

**Table 3-5: Client configuration recommendations for Windows**

<b>System requirement</b>	<b>Recommendation</b>
Disk space to install and run Sybase IQ 12.7 Network Client	83MB
Disk space to install Sybase IQ ETL Development	163MB
Disk space to install Sybase Central Java Edition 4.3	30MB
Disk space to install jConnect 5.5	17MB
Disk space to install jConnect 6.0	6MB

## Installing Sybase IQ Extended Enterprise Client

The Sybase IQ Extended Enterprise Client CD contains two products:

- Sybase IQ ETL Development
- Sybase IQ Network Client

The following sections describe installation for each product.

### Installing Sybase IQ ETL Development

The Sybase IQ Extended Enterprise Client CD can install both Sybase IQ ETL Development and Sybase IQ Network Client. If you plan to install both, install Sybase IQ ETL Development first. Otherwise, skip to “Installing Sybase IQ Network Client for Windows” on page 41.

#### ❖ Running the installation program

- 1 Log in to the Windows machine using an account with Administrator privileges.
- 2 Exit any Windows programs running on your machine.
- 3 Place the CD in the CD drive.

If your system is equipped with autorun, the installation starts immediately and you can skip the next step.

- 4 Select Start > Run.

Use Browse to select your CD drive letter, and, in the File Name box, type:

`setup.exe`

❖ **Installing Sybase IQ ETL Development**

Sybase IQ ETL Development provides client components for Extract/Transform/Load capability, including the GridNode application. (For details, see the *ETL User's Guide for Sybase IQ* on the Getting Started CD.) If you do not require ETL capability, choose Sybase IQ Network Client and skip to “Installing Sybase IQ Network Client for Windows” on page 41. If you plan to install both products, install Sybase IQ ETL Development first.

- 1 Follow the steps in “Running the installation program” on page 39.
- 2 When prompted to select the component to install, choose Sybase IQ ETL Development and click Next.
- 3 Select a setup language and click OK to continue.
- 4 Read the welcome screen and click Next.
- 5 Read the license agreement. To accept it and continue the install, select “I accept the agreement,” and click Next. To stop the procedure without installing Sybase IQ, click Cancel.
- 6 The default location for Sybase IQ ETL Development is *C:\Program Files\SYBASE\IQETLDevelop421*. To install in the default location, click Next. Otherwise, click Browse to specify a new location. Sybase recommends that installation paths contain only alphanumeric characters.
- 7 The default location for the program shortcut is the Start Menu folder *Sybase\*. To install in the default location, click Next. Otherwise, click Browse to specify a new location.
- 8 If you run the installation using an Administrator account, you need to activate the “Install for all users” option. This allows you to launch the application on user accounts with restricted access rights.

---

**Note** When started the first time on a user account, all files requiring write privileges are copied to the user directory, typically *C:\Documents and Settings\<username>\Application Data\SYBASE\Sybase IQ ETL Development\421*

---

---

**Note** Depending on the “Install for all users” option, log files are located in the *\log* subdirectory of either the user or the installation directory.

---

Select check boxes for any additional setup tasks desired. Click Next.

**Sybase IQ ETL  
Development  
Configuration settings**

- 9 The installation procedure displays specified installation destinations, Start Menu folder selected, and additional tasks specified. Click Install to continue or Back to change the locations or tasks.
- 10 View the Readme file and click Next to continue.
- 11 The Launch Sybase IQ ETL Development box is selected by default. To avoid automatically launching Sybase IQ ETL Development, clear the box. Click Finish to exit Setup for Sybase IQ ETL Development.

Sybase IQ ETL Development uses the Windows registry to store configuration settings.

HKEY\_CURRENT\_USER\Software\JavaSoft\Prefs\sybase\iqetl stores the preferences. See “Customizing preferences” in Chapter 2 in the *ETL User’s Guide for Sybase IQ* for details.

HKEY\_CURRENT\_USER\Software\JavaSoft\Prefs\sybase\iqetl\connection stores Repository connection details. See “Administering the repository” in Chapter 2 in the *ETL User’s Guide for Sybase IQ* for details)

---

**Note** To allow reusing the settings after upgrading to a new version of Sybase IQ ETL Development these registry keys are not removed when uninstalling the product. If required you need to remove them manually.

---

To install Sybase IQ Network Client for Windows, perform the following procedure.

❖ **Installing Sybase IQ Network Client for Windows**

Sybase IQ Network Client provides components required for *operation as a network client*.

---

**Note** You can install the Sybase IQ Network Client on many end-user machines, remotely, without displaying dialog boxes or requiring interactive responses. For directions, see “Performing a silent installation” on page 44.

---

- 1 Follow the steps in “Running the installation program” on page 39.
- 2 If installing from the Sybase IQ Extended Enterprise Client CD, choose Sybase IQ Network Client from the products listed and click Next, then click Next after reading the Welcome window.

If installing from the Sybase IQ Network Client CD, read the Welcome window and click Next.

- 3 Select the location where you are installing the software and click Next.
- 4 Read the License Agreement. To accept, select the I Accept the Terms of this Agreement check box and click Next. To return to a previous screen, click Back. To stop the procedure without installing, click Cancel.
- 5 Type your name and your company name in the text boxes on the Customer Information screen and click Next.
- 6 Choose Complete or Custom install. The Complete install is recommended for most users. The Custom install lets you select components of products to install.
- 7 Products are installed in separate folders under the folder you specify. You can accept the default (*C:\Program Files\Sybase*), or use the Browse button to select another folder.

Click Next.

- 8 For a Complete install, skip to step 10.

For a Custom install, choose products to install. The Products Selection screen lists names and descriptions of products. Required products are automatically selected. Click any checked product to deselect it. Required products vary depending on selections. Products are:

- Sybase IQ
- Sybase Central Java Edition
- Java Runtime Environment
- Sybase jConnect JDBC Driver

For Sybase IQ and Sybase Central, a Customize Product screen lets you select desired components. Click Browse to specify a new destination folder. Click Disk Space to calculate available space on other drives and to change the destination drive for installed products.

- 9 Click Next when satisfied with selected products.
- 10 Before copying the program files, the setup procedure lists the products selected and the target directories where they will be installed. Click Back to make changes or Next to install.

The installation procedure displays a gauge to show the percentage and names of files installed.

---

**Note** It is best to reboot after any program installation, to ensure that registry and environment settings are correct.

---

- 11 When the installation procedure completes, it prompts you to reboot your system. To reboot your system now, remove the Sybase IQ Extended Enterprise Client CD from the CD drive and click Finish. To reboot at a later time, click “No, I will restart my computer later,” then click Finish.

After installing

If you installed Sybase Central, see the *Sybase IQ System Administration Guide* for instructions on configuring and running the IQ Agent. You must run the IQ Agent to use Sybase Central.

## Installing Sybase IQ Network Client

---

**Note** You can install the Sybase IQ Network Client on many end-user machines, remotely, without displaying dialog boxes or requiring interactive responses. For directions, see “Performing a silent installation” on page 44.

---

Follow the steps in “Installing Sybase IQ Network Client for Windows” on page 41.

## Installing without user interaction

You can use the silent installation feature to ensure a uniform Sybase IQ Network Client installation on Windows for a large number of end-user machines. By eliminating end-user input, the silent installation may reduce installation errors.

The silent installation uses a response file as input. The client CD includes a default response file, which automatically accepts all installation defaults. You can create a specialized version of the response file, for example, if you need to install in a nonstandard location, or do not want to reboot the client machine immediately after installing.

This procedure requires that you have a network machine that is visible to all client machines. This can be either the machine where you install IQ, or a separate machine.

❖ **Creating a response file**

Follow these steps only for nondefault silent installations on Windows.

- 1 Copy the installation CD contents onto a Windows machine in your network.
- 2 Log in to the machine where you will install IQ Client, using an account with Administrator privileges.
- 3 Exit any Windows programs running on your machine.
- 4 Change directory to the location of the *setup.exe* file.
- 5 Type the following command, which will record all of your responses to installation prompts as you make them:

```
setup -r
```

- 6 Install Sybase IQ Network Client.

---

**Warning!** When creating a response file, do not answer Yes to the dialog box question, “Would you like to restart your computer now?”

---

When the installation completes, it creates the response file  
*C:\WINDOWS\setup.iss*.

- 7 Copy the *C:\WINDOWS\setup.iss* file to the same location as the *setup.exe* file on each machine where you want to perform a silent install based on this response file.

❖ **Performing a silent installation**

Follow these steps to install using the default response file, or a specialized response file you have placed in the client’s *setup.exe* directory.

- 1 Copy the installation CD contents onto the network machine if you have not already done so.

Perform the remaining steps on each machine where you will install IQ silently.

- 2 Log in to the machine where you will install IQ Client, using an account with Administrator privileges.
- 3 Exit any Windows programs running on the machine.
- 4 Open an MS-DOS window and change the drive and directory to the location of the *setup.exe* file on the network machine.
- 5 Type the following to run the silent installation:



```
setup -s -accept_sybase_license
```

All errors are written to the file `%temp%\Sybase_IQ.install.log`. The TEMP variable defaults to `C:\WINDOWS\Temp`.

#### Next steps

The next chapter, Chapter 4, “Migrating Data,” describes how to move your data from one version to the next, from a 32-bit to a 64-bit version, and from one hardware platform to another.

If you anticipate a need to restore data to its previous version after you upgrade, read “Restoring to your previous version after upgrade” on page 61 before you begin the upgrade process.



# Migrating Data

## About this chapter

This chapter explains how to migrate data from one Sybase IQ version to the next, from 32-bit to 64-bit systems, and across hardware platforms.

---

**Note** For information about migrating data between Sybase IQ and other databases, see the *ETL User's Guide for Sybase IQ* (DC00608-01-0421-01). This manual is on the Getting Started Sybase IQ 12.7 Extended Enterprise Edition CD.

---

## Contents

Topic	Page
Upgrading non-multiplex databases	48
Running a mixed-version multiplex	52
Upgrading 12.5 multiplex databases to 12.7	53
Upgrading 12.6 multiplex databases to 12.7	57
Migrating databases to a 64-bit system	60
Restoring to your previous version after upgrade	61
Upgrading Sybase IQ ETL	61
Migrating across hardware platforms	64

If you have a Sybase IQ version prior to 12.5, you must first upgrade to version 12.5. Refer to the 12.5 *Sybase IQ Installation and Configuration Guide*.

If you are running a 64-bit version of Sybase IQ for the first time, and you have existing databases created using a 32-bit version, no special migration steps are necessary. For general procedures, see “Migrating databases to a 64-bit system” on page 60. As always, Sybase recommends that you have a stable backup for databases before making significant changes in the environment.

---

**Note** Before you install Sybase IQ 12.7, you must upgrade LONG BINARY columns. For instructions, see the appendix, “Upgrading existing LONG BINARY columns” in the manual *Large Objects Management in Sybase IQ*.

---

## Upgrading non-multiplex databases

Table 4-1 lists steps for upgrading non-multiplex servers and databases to Sybase IQ 12.7. Details follow the table.

**Table 4-1: Upgrading non-multiplex databases**

To do this ...	See ...
1. Shut down servers	“Shutting down servers” on page 48
2. Install IQ	“Installing IQ” on page 48
3. Start the server	“Starting the server” on page 49
4. Upgrade databases	“Upgrading databases” on page 49
5. Enforce referential integrity	“Enforcing referential integrity” on page 50
6. Verify after upgrade	“Verifying databases after upgrade” on page 51
7. Back up databases again (recommended)	“Backing up databases after upgrade” on page 51

### Before you upgrade

You must have a recent backup before you upgrade to a major release of Sybase IQ.

If you anticipate a need to restore data to its previous version after you upgrade, read “Restoring to your previous version after upgrade” on page 61 before you begin the upgrade process.

If you have multiplex servers, instead of following the steps in this section follow those in “Upgrading 12.5 multiplex databases to 12.7” on page 53 or “Upgrading 12.6 multiplex databases to 12.7” on page 57.

## Shutting down servers

Before installing Sybase IQ, you must shut down each server. At the command prompt, issue a `stop_asiq` command. You can also stop a server by using the `STOP ENGINE` command from DBISQL or any front-end client.

## Installing IQ

Install Sybase IQ, following the instructions in Chapter 2, “Installing Sybase IQ.” If you find a software update on the online support Web site, install it before completing the remaining upgrade steps.

## Starting the server

To start the server, change to a directory where you have write privileges. Run the `start_asiq` utility, using the following command format:

```
start_asiq @configuration_filename.cfg -gm 1 -gd dbname.db
```

The *dbname* is the name of the database to upgrade. (You can also start the server using any of the start-up methods described in *Sybase IQ System Administration Guide*.)

Run `start_asiq` only from a session where you have previously set the environment variables. For information about setting the variables, see “Setting environment variables” on page 23.

---

**Note** If you run the utility from a directory that does not contain the database and configuration files, be sure to provide the full path name for the file or files.

---

## Upgrading databases

Upgrading from 12.5  
or higher

Run the `ALTER DATABASE UPGRADE` command against every existing Sybase IQ database to upgrade it to IQ 12.7. This makes the databases compatible with the new version of Sybase IQ.

Upgrading a database adds and modifies system tables, system procedures, and options to enable 12.7 options. It does *not* change the file format used to store and access data on a disk. It also does not remove preexisting options that have been eliminated in version 12.7.

### ❖ Upgrading databases to version 12.7

Performance optimizations in Version 12.7 depend on structural changes and option settings made by the `ALTER DATABASE UPGRADE` command. The format of the database files is the same as in Sybase IQ Version 12.6, but some system tables, stored procedures, and database options have changed.

To upgrade, follow these steps:

- 1 Make sure that you have performed the preceding steps in this chapter and installed any available EBFs. For details, see “Finding the latest information on EBFs and software maintenance” on page ix.
- 2 Disconnect from the database and reconnect to your database (again using an account with DBA privileges).

Be sure to start the server in a way that restricts user connections. Never allow other users to connect when ALTER DATABASE UPGRADE is running. Sybase recommends using two server start-up options:

- Use -gd DBA so that only users with DBA authority can start and stop databases.
- Use -gm 1 to allow a single connection plus one DBA connection above the limit so that a DBA can connect and drop others in an emergency.

An alternate way to restrict connections is to specify

```
sa_server_option('disable_connections', 'ON')
```

just after you start the connection where you are performing the upgrade and

```
sa_server_option('disable_connections', 'OFF')
```

on the same connection after upgrading. *The disadvantage is that this method precludes emergency access from another DBA connection.*

- 3 Start DBISQLC or DBISQL and execute the ALTER DATABASE UPGRADE statement. For example:

```
ALTER DATABASE UPGRADE
```

If the database you are upgrading was created with the Java options set off, append the keywords JAVA OFF JCONNECT OFF to the preceding command.

---

**Note** The defaults for MAIN\_RESERVED\_DBSPACE\_MB and TEMP\_RESERVED\_DBSPACE\_MB were increased in version 12.5 for newly created databases. If these options are set to less than the 200MB in your database, set the options to 200MB or 50% of the size of the last dbspace before or immediately after upgrading your database.

---

## Enforcing referential integrity

ALTER DATABASE UPGRADE does not upgrade any unenforced foreign keys defined prior to Sybase IQ version 12.5. See *Sybase IQ System Administration Guide* for details on how to identify existing unenforced foreign keys and enforce referential integrity with them.

## Starting the Sybase IQ Agent

If you have installed Sybase Central, you now need to start the Sybase IQ agent.

## Verifying databases after upgrade

Run `sp_iqcheckdb` to verify the consistency of the upgraded databases.

---

**Note** In this step, you run the IQ 12.7 version of `sp_iqcheckdb`, which uses input parameters, rather than database options, to specify the type of database consistency checking.

---

### ❖ Running `sp_iqcheckdb`

- 1 Issue a CHECKPOINT command.
- 2 Run `sp_iqcheckdb` in detailed check mode.

```
sp_iqcheckdb 'check database'
```

If you run the procedure from Interactive SQL, redirect output to a file by typing the following:

```
sp_iqcheckdb 'check database' >& filename
```

- 3 Issue a COMMIT statement.

Examine the `sp_iqcheckdb` report for errors. For information on interpreting the `sp_iqcheckdb` results and corrective action, refer to Chapter 2, “System Recovery and Database Repair,” in *Sybase IQ Troubleshooting and Recovery Guide*. If you need to contact Sybase Technical Support, you must provide the output from `sp_iqcheckdb`.

## Backing up databases after upgrade

Sybase recommends that you back up your databases again with the BACKUP statement. For complete syntax, see the *Sybase IQ System Administration Guide*.

This backup after the upgrade is recommended but not required. If you use the IQ BACKUP statement instead of a system-level backup, you can run backups and queries concurrently.

## After you upgrade

### Updating configuration files

Be sure to compare your existing *params.cfg* files with the new *default.cfg* file created by the installation. The installation does not update or overwrite existing *params.cfg* files. In each *params.cfg* file, update parameter defaults that differ from those in the *default.cfg* file, while maintaining any customized parameter settings appropriate for your system. Be sure that you add any new start-up parameters in *default.cfg* to your *params.cfg* file. The `-gl` parameter, for example, is required for server start-up in version 12.5 and above.

### Checking new option settings

ALTER DATABASE UPGRADE changes many database option settings, including all performance options, to the new default. Some other settings retain their previous value. To see the effect of ALTER DATABASE UPGRADE on your database option settings, you can do any of the following:

- To list current settings for all database options, query the SYSOPTIONS system view:

```
SELECT *  
FROM SYSOPTIONS
```

For other ways to list all option settings, see the chapter “Database Options” in the *Sybase IQ Reference Manual*.

- Run `sp_iqcheckoptions`. This stored procedure displays a list of database options that have been changed from the default value together with the current value of the option and the default value for the connected user. It also displays nondefault server start-up options. For more information, see `sp_iqcheckoptions` in the chapter “System Procedures” in the *Sybase IQ Reference Manual*.

Note that the `Query_Plan` option is ON by default, which can lead to a large IQ message file size.

## Running a mixed-version multiplex

You can deploy new releases on one server of an existing multiplex without interrupting other servers, as long as the servers being upgraded are version 12.5 or higher. *Always upgrade the write server last.*

Any multiplex where all servers are not at the same version is **mixed-version multiplex**.



New features are completely available only after all databases are upgraded using ALTER DATABASE UPGRADE. If you upgrade databases on a query server, but leave the write server at 12.6, synchronization returns database versions on the query server to version 12.6, and you must repeat the ALTER DATABASE UPGRADE. Databases take their version from the write server.

Synchronizing affects database version, *not the installed software version* on a server. For example, if you install 12.7 software on the query server, that software continues to be at version 12.7 after any synchronizations. Multiple database versions can exist on servers with installed software version 12.7, as shown in Table 1-5 on page 10. However, you must connect to each server using an IQ agent of the same version, and the appropriate agent port.

Be sure to back up the write server before an upgrade. Once you create an IQ Local Store on a query server, you must back up that query server as part of future upgrades.

If you have a mixed-version multiplex with a 12.5 write server, be aware that creating a local store succeeds on a 12.6 or 12.7 query server but is not recognized by the 12.5 write server, and is lost at the next synchronization. (Version 12.5 did not support local stores.)

## Upgrading 12.5 multiplex databases to 12.7

Upgrade all multiplex databases to version 12.5 before following the instructions in this section.

Before upgrading  
multiplex databases

---

**Note** Sybase Central uses default settings for server start-up switches from the *params.cfg* file. The default values of some start-up options, such as those that control cache sizes, may be insufficient for migrating large multiplex servers. For best results, create a configuration file with higher values for switches such as -c, -cl and -ch. Specify this file explicitly when starting the multiplex server for database upgrade. For details about configuration files, see “Configuring the Sybase IQ Server” on page 67.

---

To upgrade multiplex databases from 12.5 to 12.7, perform the steps in that follow on each server in the multiplex.

To upgrade 12.6 databases, see “Upgrading 12.6 multiplex databases to 12.7” on page 57.

Wherever backup is recommended, you should back up the write server and any query servers where you created an IQ Local Store.

❖ **Upgrading 12.5 multiplex databases**

---

**Note** On UNIX systems, you may optionally install 12.7 Sybase IQ software on all the servers in a separate directory from the previously installed version before starting the upgrade process. Once the separate directories are ready, follow the steps below.

---

- 1 Shut down all the servers.
- 2 Install Sybase IQ 12.7 on the write server's system. (See Chapter 1.) On UNIX, you can do this before shutting down the servers. On Windows, installation forces a system reboot.
- 3 If you plan to run only 12.7 servers, skip to Step 4. To run 12.5 servers in the same multiplex as 12.7, install a 12.7 agent on the write server. The 12.7 IQ plug-in is compatible with 12.5 servers, but you must start 12.5 servers with a 12.5 agent and 12.7 servers with a 12.7 agent.

To install the standalone agent, use the following command on UNIX or Linux systems:

```
sybinstall -add_agent
```

After this install, you have two IQ agents:

- The agent for your existing version, which runs on the default port. The 12.5 agent is S99SybaseIQAgent.
  - The 12.7 agent, which requires its own port. The 12.7 agent is S99SybaseIQAgent12.
- 4 Stop the IQ agent on the write server's system and restart it using the 12.7 installation environment.

First, use the `ps` command to locate the java process for the IQ agent:

```
ps -ef | grep jre
fionat 5795 5705 0 17:46:49 pts/8 0:00 grep jre
fionat 5781 5755 0 17:46:49 pts/8 0:00
/wrk/sybcentral/java/jre2/bin/./bin/sparc/native_threads/java -ms8m -m
```

To determine if the process is the IQ agent or the client process for the Sybase Central viewer, repeat the command with the parent process's ID:

```
ps -fp 5755
UID      PID      PPID  C  STIME      TTY      TIME  CMD
```

```
fionat 5755 1 0 17:45:09 pts/8 0:00 /bin/ksh /work ASIQ-
12_5/bin/scjview -mainclass sybase.scf.ro.SCAgent -1
```

At the end of the line, *sybase.scf.ro.SCAgent* indicates the IQ agent. (If the parent process ends with *scjview*, it is the client process for the Sybase Central viewer, not the agent.)

To stop the agent in the preceding example, enter:

```
kill -HUP 5781
```

- 5 Remove any `-n <servername>` switch in a *params.cfg* file used to start a multiplex database.
- 6 (Mixed-version multiplex only) Edit the *params.cfg* file in the database directory on each query server to set the following switch(es):

- Set `-iqnomain 1`
- If the query server has local stores, set `-iqnolocalreplay 1`

*You must set these switches before you run ALTER DATABASE UPGRADE and they must still be set when you synchronize query servers.*

- 7 Start the write server in single node mode using the `-iqmpx_sn 1` switch. *If you use a server name different from the write server name, you must also use the override switch, `-iqmpx_ov 1`.*

Use a unique server name that you have not previously used, as follows:

```
start_asiq @params.cfg -n <upgrade_server>
-iqmpx_sn 1 -x 'tcpip{port=<writer_port>}' <dbfile>
```

You may use the write server's normal TCPIP port.

- 8 Disconnect Sybase Central and SQL Remote from the database.
- 
- 9 **Note** Sybase IQ 12.6 and higher releases enforce column and table CHECK constraints that were previously unenforced, but only on inserts, updates, and loads of new data. Before you upgrade the database, Sybase suggests that you follow the procedure in “Preserving check constraints before database upgrade” on page 11 to record and recreate constraints.
- 

Connect to the server to be upgraded with `dbisqlc` or `dbisql` as DBA. *Make sure that no other users connect during the upgrade process.* See “Upgrading databases” on page 49 for recommended syntax to restrict users.

- 10 Make sure that you have performed the preceding steps in this chapter and installed any available EBFs. For details, see “Finding the latest information on EBFs and software maintenance” on page ix.
- 11 Upgrade the database by issuing the following command:

```
ALTER DATABASE UPGRADE
```

If the database you are upgrading was created with the Java options set off, append the keywords `JAVA OFF JCONNECT OFF` to the preceding command. For more about the `ALTER DATABASE UPGRADE` statement, see the *Sybase IQ Reference Manual*.

---

**Note** The defaults for `MAIN_RESERVED_DBSPACE_MB` and `TEMP_RESERVED_DBSPACE_MB` were increased in version 12.5 for newly created databases. If these options are set to less than the 200MB in your database, set the options to 200MB or 50% of the size of the last dbspace before or immediately after upgrading your database.

---

- 12 *If your multiplex has a write server with no query servers*, issue the following statement to convert to a non-multiplex database.

```
call sp_iqendmpx();
```

After you run `sp_iqendmpx`, you have a non-multiplex database. Skip the remaining steps in this procedure, see “Enforcing referential integrity” on page 50, and complete the remaining tasks in “Upgrading non-multiplex databases” instead.

- 13 Reset the SQL Remote configuration by issuing the SQL statements:

```
call sp_iqmpxdroppublication()  
call sp_iqmpxcreatepublication()
```

You can check the multiplex configuration by issuing:

```
call sp_iqmpxvalidate()
```

It should indicate that `dbremote` is not running for this server, but there should be no other errors.

- 14 Install Sybase IQ 12.7 on each query server system, if not done in advance.
- 15 Stop and restart the IQ agent in the 12.7 environment on each query server.
- 16 Start Sybase Central, connect, and run Synchronize from the write server.
- 17 (Mixed-version multiplex only) Edit the *params.cfg* file in the database directory on the upgraded query server as follows:

- Remove the -iqnomain 1 switch
- If the query server has local stores, remove the -iqnolocalreplay 1 switch

Restart the query server that you just upgraded.

- 18 Perform the ALTER DATABASE UPGRADE and subsequent steps on each query server in the multiplex.

All upgraded servers in the multiplex environment are now running version 12.7.

After upgrading  
multiplex databases

Because the shared top-level directory is not a good location for database files, you should move these files to directories local to each server in the multiplex environment. For instructions, see the section “Migration” in Chapter 14, “Data Backup, Recovery, and Archiving” in the *Sybase IQ System Administration Guide*. After you move all database files, you can remove the shared top-level directory from the server systems if desired.

See also “After you upgrade” on page 52 for other items you may want to check after upgrading.

## Upgrading 12.6 multiplex databases to 12.7

To upgrade multiplex databases from 12.6 to 12.7, perform the following steps.

---

**Note** Sybase IQ 12.6 and higher releases enforce column and table CHECK constraints that were previously unenforced, but only on inserts, updates, and loads of new data. Before you upgrade the database, Sybase suggests that you follow the procedure in “Preserving check constraints before database upgrade” on page 11 to record and recreate constraints.

---

### ❖ Upgrading 12.6 multiplex databases

You may optionally install 12.7 Sybase IQ software on all the servers in a separate directory from the previously installed version before starting the upgrade process. Once the separate directories are ready, follow the steps below.

- 1 Shut down all the servers.

- 2 Install Sybase IQ 12.7 on the write server's system. (See Chapter 1.) You can do this before shutting down the servers.
- 3 If you plan to run only 12.7 servers, skip to Step 4. To run 12.6 servers in the same multiplex as 12.7, install a 12.7 agent on the write server. The 12.7 IQ plug-in is compatible with 12.6 servers, but you must start 12.6 servers with a 12.6 agent and 12.7 servers with a 12.7 agent.

To install the standalone agent, use the following command on UNIX or Linux systems:

```
sybinstall -add_agent
```

After this install, you have two IQ agents:

- The agent for your existing version, which runs on the default port. The 12.6 agent is S99SybaseIQAgent1260.
  - The 12.7 agent, which requires its own port. The 12.7 agent is S99SybaseIQAgent12.
- 4 Stop the IQ agent on the write server's system and restart it using the 12.7 installation environment. (On Windows, this is not needed because the IQ agent starts automatically during reboot.)

First, use the `ps` command to locate the java process for the IQ agent:

```
ps -ef | grep jre
fionat 5795 5705 0 17:46:49 pts/8 0:00 grep jre
fionat 5781 5755 0 17:46:49 pts/8 0:00
/wrk/sybcentral/java/jre2/bin/./bin/sparc/native_threads/java -ms8m -m
```

To determine if the process is the IQ agent or the client process for the Sybase Central viewer, repeat the command with the parent process's ID:

```
ps -fp 5755
UID    PID    PPID  C  STIME     TTY     TIME CMD
fionat 5755    1    0 17:45:09 pts/8 0:00 /bin/ksh /work ASIQ-
12_5/bin/scjview -mainclass sybase.scf.ro.SCAgent -1
```

At the end of the line, *sybase.scf.ro.SCAgent* indicates the IQ agent. (If the parent process ends with *scjview*, it is the client process for the Sybase Central viewer, not the agent.)

To stop the agent in the preceding example, enter:

```
kill -HUP 5781
```

- 5 Remove any `-n <servername>` switch in a *params.cfg* file used to start a multiplex database.

- 6 (Mixed-version multiplex only) Edit the *params.cfg* file in the database directory on each query server to set the following switch(es):

- Set `-iqnomain 1`
- If the query server has local stores, set `-iqnolocalreplay 1`

*You must set these switches before you run ALTER DATABASE UPGRADE and they must still be set when you synchronize query servers.*

- 7 Disconnect Sybase Central and SQL Remote from the database.
- 8 Start the write server in single node mode using the `-iqmpx_sn 1` switch. *If you use a server name different from the write server name, you must also use the override switch, `-iqmpx_ov 1`.*

Use a unique server name that you have not previously used, as follows:

```
start_asiq @params.cfg -n <upgrade_server>
-iqmpx_sn 1 -x 'tcpip{port=<writer_port>}' <dbfile>
```

You may use the write server's normal TCPIP port.

- 9 Connect to the server to be upgraded with `dbisqlc` or `dbisql` as DBA. *Make sure that no other users connect during the upgrade process.* For suggested syntax, see “Upgrading databases” on page 49.
- 10 Make sure that you have performed the preceding steps in this chapter and installed any available EBFs. For details, see “Finding the latest information on EBFs and software maintenance” on page ix.
- 11 Upgrade the database by issuing the following command:

```
ALTER DATABASE UPGRADE
```

If the database you are upgrading was created with the Java options set off, append the keywords `JAVA OFF JCONNECT OFF` to the preceding command. For more about the `ALTER DATABASE UPGRADE` statement, see the *Sybase IQ Reference Manual*.

- 12 Reset the SQL Remote configuration by issuing the SQL statements:

```
call sp_iqmpxdroppublication()
call sp_iqmpxcreatepublication()
```

To check the multiplex configuration, issue this statement:

```
call sp_iqmpxvalidate()
```

It should indicate that `dbremote` is not running for this server, but there should be no other errors.

- 13 Install Sybase IQ 12.7 on each query server system, if not done in advance.
- 14 Stop and restart the IQ agent in the 12.7 environment on each query server.
- 15 Start Sybase Central, connect, and run Synchronize from the write server.
- 16 (Mixed-version multiplex only) Edit the *params.cfg* file in the database directory on each query server as follows:
  - Remove the -iqnomain 1 switch
  - If the query server has local stores, remove the -iqnocalreplay 1 switch

Restart the query server that you just upgraded.

- 17 Perform the ALTER DATABASE UPGRADE and subsequent steps on each query server in the multiplex.

All upgraded servers in the multiplex environment are now running version 12.7.

## Migrating databases to a 64-bit system

This section describes how to migrate your database from a 32-bit to a 64-bit hardware platform.

### Prerequisite

The procedures assume your database is already upgraded to Sybase IQ 12.7.

### ❖ Migrating databases to a 64-bit machine

- 1 Back up the database.
- 2 Shut down the server.
- 3 Install the Sybase IQ 64-bit software and any required ESDs.
- 4 If the current version of Sybase IQ is higher than the version on which you were previously running, start Interactive SQL and issue the database upgrade statement:

ALTER DATABASE UPGRADE

If the database was created with the Java options off, append the keywords JAVA OFF JCONNECT OFF to the preceding command.

- 5 Start the server.



Sybase recommends that you perform regular backups.

## Restoring to your previous version after upgrade

If you anticipate a need to restore data to its previous version after you upgrade, follow the guidelines in this section to ensure that IQ files are saved *before* you upgrade.

---

**Note** Sybase recommends that you install Sybase IQ 12.7 to a separate location from the directory where you installed previous Sybase IQ software.

---

### ❖ Preparing for upgrade

Before you upgrade, follow these steps to ensure that you can restore your data to its previous version.

- 1 Perform an IQ backup, as described in Chapter 13, “Backup and Data Recovery” in *Sybase IQ System Administration Guide*.
- 2 When you install Sybase IQ, install it in another directory, and follow the upgrade steps.

### ❖ Restoring data to the previous Sybase IQ version

If you find that you need to go back to the previous version, follow these steps.

- 1 Change the environment variables to point at the older installation directories.
- 2 Start the utility database and restore the backup that you performed before the upgrade.
- 3 Stop the utility database and start the database that you restored.

## Upgrading Sybase IQ ETL

To upgrade Sybase IQ ETL, follow the instructions in this section.

## Upgrading Sybase IQ ETL Server version only

To upgrade Sybase IQ ETL Server to a higher version, you must install the new version in a different directory or uninstall the older version and install the new version.

If you decide to remove the older server directory, take care not to remove the ODBC or native connectivity files. This includes the *.odbc.ini* file or any ODBC or native drivers.

UNIX and Linux  
installation

On UNIX or Linux systems, follow these steps:

### ❖ Upgrading Sybase IQ ETL Server on Linux or UNIX

- 1 Install the new ETL server/grid engine in a different directory
- 2 Shut down the old GridNode, by entering the following at the command prompt:  

```
./GridNode.sh -shutdown
```
- 3 Check that shutdown succeeded:  

```
ps -e | grep GridNode
```
- 4 If GridNode is still running, kill the process.
- 5 Copy the files in the *licenses* directory from the old to the new installation.
- 6 Copy the *.ini* files in the *etc* directory from the old to the new installation.
- 7 Start the new ETL server/grid engine.

To start it directly, use

```
GridNode.sh
```

To start the ETL server as a service, use:

```
GridNode.sh -install
```

- 8 Check that startup succeeded:  

```
ps -e | grep GridNode
```
- 9 If GridNode is running, you may delete the older ETL server by removing its install directory.

Be that sure the *.odbc.ini* file containing all defined data sources is not in the directory with the older ETL Server. If it is and you plan to delete the older server directory, move the *.odbc.ini* to a different directory.

**Windows installation**

**Warning!** The following steps do not apply to the ETL Server/grid engine installed with Sybase IQ ETL Development client. See “Upgrading Sybase IQ ETL Development” on page 63 for information about upgrading the ETL Server/grid engine installed with the ETL development client.

---

On Windows systems, you may leave the older version of the ETL server/grid engine and install the newer one in a different directory. You must shut down GridNode if it is running as a system service. To end a GridNode process running as a service, open the Windows Task Manager and display the Processes tab. Select the GridNode.exe process or processes, if more than one is running, and click End Process. (Do not use Control Panel > Administrative Tools > Services.) Make sure that no GridNode is running when you install a new version.

You may uninstall the older ETL server/grid engine using the Control Panel | Add/Remove Programs option and then install the new ETL server/grid engine.

## Upgrading Sybase IQ ETL Development

Follow the procedures in this section to upgrade Sybase IQ ETL Development.

❖ **Preparing to upgrade Sybase IQ ETL Development**

- 1 Check for the process *GridNode.exe* in the Task Manager.
- 2 Make sure that the Show Processes From All Users box is selected.
- 3 If you find the GridNode.exe process, end this task.
- 4 If using MS Access repositories located in the application directories, copy the database files and make the ODBC Data Source point to the new location.

❖ **Upgrading Sybase IQ ETL Development**

- 1 Install the new version in a different directory.
- 2 Copy the .ini files (except for *components\_\*.ini*) in the *etc* directory from the old to the new installation.
- 3 Start the new Sybase IQ ETL Development version.
- 4 Connect to an existing repository.
- 5 Check whether the GridNode is running. (See “Preparing to upgrade Sybase IQ ETL Development”.)

After successful installation:

- Delete and recreate job schedules (if any). (For details, see *ETL User's Guide for Sybase IQ*.)
- You may uninstall the older ETL Development version

## Migrating across hardware platforms

Sybase IQ supports migrating your database from one platform to another, as long as both have the same endian structure.

Platforms with big-endian structure are:

- AIX64
- HP-UX64 PA-RISC
- HP-UX64 Itanium
- IBM Linux on POWER
- SunOS64

Platforms with little-endian structure are:

- Linux32\*\*
- Linux64
- Windows 32
- WinAMD64
- SunAMD64

Sybase IQ 12.6 ESD #2 and higher releases support migration between Windows and Linux.

---

### **IMPORTANT!**

\*\* If you created your Sybase IQ database on a Linux 32-bit version prior to Sybase IQ 12.6 ESD #2, you must first install IQ 12.6 ESD #2 for Linux 32-bit and create a new data backup before migrating to another platform.

---

#### ❖ **Migrating a database from one platform to another**

- 1 Back up the database.

- 2 Shut down the Sybase IQ server.
- 3 Install the Sybase IQ server on the new platform. Your migration can take place on the same or a different machine.
- 4 Start the Sybase IQ server on the new hardware platform.
- 5 Connect to the utility database, *utility\_db*.
- 6 Restore the database from the backup you created in Step 1.
- 7 Shut down the server and restart it against the restored database. If the current version of Sybase IQ is higher than the version on which you were previously running, you need to upgrade databases, and therefore restart the server in a way that restricts user connections. Sybase recommends using two server start-up options:
  - Use -gd DBA so that only users with DBA authority can start and stop databases.
  - Use -gm 1 to allow a single connection plus one DBA connection above the limit so that a DBA can connect and drop others in an emergency.

An alternate way to restrict connections is to specify

```
sa_server_option 'disable_connections', 'ON'
```

on the connection where you intend to perform the upgrade and

```
sa_server_option 'disable_connections', 'OFF'
```

on the same connection after upgrading. *The disadvantage is that this method precludes emergency access from another DBA connection.*

- 8 Start Interactive SQL and issue the database upgrade statement. For example:

```
ALTER DATABASE UPGRADE
```

If the database was created with the Java options off, append the keywords `JAVA OFF JCONNECT OFF` to the preceding command.

For more information, see “Upgrading non-multiplex databases” on page 48.



About this chapter

This chapter tells how to configure Sybase IQ.

Contents

Topic	Page
Configuring the Sybase IQ Server	67
Configuring client connectivity	69

## Configuring the Sybase IQ Server

A configuration file lists switches that you want to set whenever you start your server. See Chapter 1 of the *Sybase IQ Utility Guide* for a complete list of switches.

Installing Sybase IQ creates a configuration file called *asiqdemo.cfg* for the sample database. You can start the sample database using this configuration file as follows:

```
% cd $ASDIR/demo
% start_asiq @asiqdemo.cfg asiqdemo.db
```

For example, for an *asiqdemo* database on a system named *arches* on a 64-bit system, the *asiqdemo.cfg* file might look like this:

```
-n arches_asiqdemo
-c 48MB
-gc 20
-gd all
-gl all
-gm 10
-gp 4096
-ti 4400
-x tcpip(port=5555)
```

The *asiqdemo.cfg* file sets parameters that govern Sybase IQ to the following recommended defaults:

**Table 5-1: Parameters set by *asiqdemo.cfg***

Parameter	Value	Description
-n	<HOSTNAME>_asiqdemo	Name of system followed by “_asiqdemo”
-c	32MB on 32-bit systems 48MB on 64-bit systems	Catalog store cache size in MB
-gd	all	Users permitted to start a database
-gl	all	Users permitted to load a table
-gm	10	Default number of connections
-gp	4096	Catalog store page size
-ti	4400	Client timeout
-x	tcpip{port=xxxx}	Network connection protocol where xxxx=port number. Sybase strongly recommends that you change the default port number from 2638 to another number.

You can use the *asiqdemo.cfg* file as a template to create configuration files for all of your databases if you:

- Change the *asiqdemo.cfg* file name
- Replace the -n value with a unique server name
- Replace the -x port number with a unique port number for that server

If you use the same parameters to start all your databases, you could create a generic configuration file. Simply delete the -n and -x lines and supply these parameters on the command line at startup.

---

**Note** On the start\_asiq command line, the last switch specified takes precedence, so if you want to override your configuration file, list any switches you want to change *after* the configuration file name. For example:

```
start_asiq @asiqdemo.cfg -n myserver
-x 'tcpip{port=1870}' asiqdemo
```

The -x parameter here overrides connection information in the *asiqdemo.cfg* file.

---

When specifying network connections, you need a different *server name:port#* combination for each database server. When you connect to the server, you need to specify the same combination used to start the server.



You can add comments to configuration files by preceding each comment line with the #symbol. For example:

```
#Here are parameters:
-gl all
#This is a test for -gm change
-gm 40
-gp 4096
```

Begin each comment on a new line.

#### Default configuration file

The *asiqdemo.cfg* file gets default parameter values from *\$ASDIR/scripts/default/default.cfg*. This file is also the source for the *params.cfg* file used in *start\_asiq*, by Sybase Central, and in multiplex configurations. You can maintain consistency by editing parameters in *default.cfg*, although you should keep a copy and avoid changing recommended default values.

#### Security and configuration files

To protect password information, you can encrypt your configuration files using the *dbfhide* (File Hiding) utility. For details see *Adaptive Server Anywhere Database Administration Guide*. If you specify log file parameters (*-o logfile*) in encrypted files, the log is not available to the IQ Agent or *start\_asiq*, which will be unable to display server log information back to the database administrator. Sybase recommends that you put log file parameters and others that do not require encryption on the command line or in a separate configuration file. For example:

```
start_asiq @encrypt_params @other_params
```

or

```
start_asiq @encrypt_params -n myserv -c 400
-o $ASDIR/logfile/myserv.log
```

## Configuring client connectivity

Sybase IQ supports ODBC and JDBC applications. It uses Adaptive Server Anywhere (ASA) as the server for storing catalog information.

Sybase IQ versions prior to 12.0 used Adaptive Server Enterprise as catalog server. ODBC applications used as client front-end tools with older versions of Sybase IQ will continue to run in IQ version 12.x, but third-party and customer-written Open Client™ DB-Library and Client-Library applications are unlikely to perform as expected.

*When developing Open Client applications to run with Sybase IQ 12.x, avoid using catalog tables or system stored procedures supported by Adaptive Server Enterprise but not Sybase IQ. See Appendix A, “Compatibility with Other Sybase Databases,” in the Sybase IQ Reference Manual.*

Sybase IQ is compatible with clients (like Open Client-Library and DB-Library) that use TDS. Open Client version 11.1.1 supports TDS 5.x and applications would therefore work with Sybase IQ, but only if these applications use the system tables, views and procedures that are found in Sybase IQ. System procedures, catalog tables, and views available in Sybase IQ are listed in the *Sybase IQ Reference Manual*. There are no restrictions accessing data in the IQ Store through any supported interface.

## Connecting using JDBC

JDBC provides a SQL interface for Java applications. Sybase Central and DBISQL can use either JDBC or ODBC. This section describes how to configure a JDBC connection for Sybase IQ. For an overview of using JDBC, see “Data Access Using JDBC,” in the *Sybase IQ System Administration Guide*.

In order for Sybase IQ to access a server on your network using JDBC, you must supply the host name, port number, and database name when you connect.

For example, in Sybase Central, type F11 or choose Connect from the Tools menu, and supply connection information. IQ supplies the host machine, port number, and database name from the last successful connection. If that is correct, you need only supply User ID and Password on the Identification tab. On this tab, Alt-U activates the User ID text box and Alt-P activates the Password text box.

In the DBISQL Connect dialog, you can choose the iAnywhere JDBC Driver via a radio button on the Advanced tab.

The IQ Agent can only use jConnect with JDBC to connect to a multiplex server. The jConnect JDBC drivers have been certified with multiplex and non-multiplex servers.

## Connecting using ODBC

Open Database Connectivity (ODBC) is a standard application programming interface (API) developed by Microsoft. It allows a single application to access a variety of data sources for which ODBC-compliant drivers exist. The application uses SQL as the standard data access language.

### ODBC conformance

Sybase IQ supports ODBC 3.5.2.

Levels of ODBC support

ODBC drivers manufactured by different vendors may vary widely in the functions they provide. ODBC features are arranged according to a level of conformance. Features are either Core, Level 1, or Level 2, with Level 2 being the most complete level of ODBC support. These features are listed in the *ODBC Programmer's Reference*, which is available from Microsoft Corporation as part of the ODBC software development kit or from the Microsoft Web site. Using your browser, go to the Microsoft Web site at <http://www.microsoft.com>.

Features supported by Sybase IQ

Sybase IQ ODBC 3.5.2 support is as follows:

- **Core conformance** Sybase IQ supports all Core level features.
- **Level 1 conformance** Sybase IQ supports all Level 1 features, except for asynchronous execution of ODBC functions.

Sybase IQ does support multiple threads sharing a single connection. The requests from the different threads are serialized by Sybase IQ.

- **Level 2 conformance** Sybase IQ supports all Level 2 features, except for the following:
  - Three part names of tables and views. This is not applicable for Sybase IQ.
  - Asynchronous execution of ODBC functions for specified individual statements.
  - Ability to time out login request and SQL queries.

ODBC 3.5.x new features

While you can use new ODBC 3.5.x features, such as descriptors, in your ODBC applications, ODBC 2.x applications will continue to work with Sybase IQ.

## Installing ODBC drivers

When you install Sybase IQ on your UNIX or Linux server, the installation procedure also installs the ODBC driver, which can be directly accessed by applications. If you are using an ODBC application that uses *libodbc.so* (*libodbc.so.1*) or *libodbcinst.so* (*libodbcinst.so.1*), simply create symbolic links to that point to *\$SYBASE/ASIQ-12\_7/lib/libdbodbc9.so.1* for single threaded or *\$SYBASE/ASIQ-12\_7/lib/libdbodbc9\_r.so.1* for multi-threaded applications. If you are creating an ODBC application, you can link directly to *libdbodbc9.so* for non-threaded applications and *libdbodbc9\_r.so* for threaded applications. References to ODBC functions are resolved at run time.

---

**Note** The filenames cited above have platform-specific suffixes. The *so* suffix shown is specific to the Sun Solaris system. See “Linking ODBC applications on UNIX” in Chapter 7 of the *Adaptive Server Anywhere Programming Guide* for a list of files included in the driver managers for supported UNIX platforms.

---

You need to install the Sybase IQ Client Components on each client computer in your network, which contains the Sybase IQ 32-bit ODBC Driver.

The ODBC Driver shipped with Sybase IQ connects clients on a Windows platform or the platform of the IQ server to the IQ server. To connect clients on other UNIX or Linux platforms to your server, download and install a platform-specific Sybase IQ ODBC Driver. Check the EBF/Update information on the Web for the appropriate driver, following the steps in “Sybase EBFs and software maintenance” on page ix.

### 32-bit and 64-bit drivers

UNIX 64-bit applications, including many third party tools, can use 64-bit ODBC drivers to connect to 64-bit IQ servers.

32-bit applications can use 32-bit ODBC drivers to connect to 64-bit IQ servers. (32-bit applications *cannot* use 64-bit ODBC drivers to connect to 64-bit IQ servers.)

The Sybase IQ Network Client CD supplied with all platforms contains a 32-bit ODBC driver for connecting from Windows-based ODBC applications. The Sybase IQ CD contains a 64-bit ODBC driver.

To connect via ODBC from 32-bit UNIX client applications, you need to download and install the 32-bit ODBC driver kit. Check the EBF/Update information on the Web for the appropriate driver, following the steps in the procedure “Sybase EBFs and software maintenance” on page ix.

## Using UNIX or Linux-based query tools through ODBC

Applications that use ODBC connect to a software component called a driver manager, which provides a standard interface and a variety of basic services. The driver manager then connects to the specific ODBC driver, which accesses the requested data source. On Windows, the driver manager is a standard part of the environment. On UNIX or Linux, no standard ODBC driver manager is provided.

There are several ways driver manager functionality can be presented to an application. The easiest approach is to use the driver manager emulation capabilities provided by the Sybase IQ ODBC driver. Many tools (like Brio) which do not require extensive driver manager services can use the symbolic links provided with Sybase IQ to connect directly to the driver.

Some tools require the presence of a driver manager. Some (like Whitelight) ship with a driver manager, others do not. For information and recommendations about compatible driver managers available, see the documentation for the application.

## Third-party ODBC applications

Several popular PC applications have been tested in-house with Sybase IQ using the ODBC interface. Other front-end clients may work with Sybase IQ, but have not been tested.

For information on third-party vendor applications that are certified with Sybase IQ, refer to the section “Sybase certifications on the Web” in the *Sybase IQ Release Bulletin*.

The Sybase IQ ODBC Driver is shipped with Sybase IQ as part of the Network Client CD and installed automatically.

See “Creating ODBC data sources” for information on how to set up an ODBC Data Source if you need to access a database or data file over a network using ODBC.

## Usage notes for client applications

The following note applies to third-party PC client applications certified with Sybase IQ:

With BrioQuery, each query requires you to connect to the database. Be sure to close the query after processing to ensure that the connection to Sybase IQ is closed. If you leave multiple queries open, you could consume more connections than you realize, eventually preventing other users from connecting to Sybase IQ (since the number of configured connections would be exceeded).

See the *Sybase IQ Release Bulletin* for problems that may affect using PC client applications with Sybase IQ.

## Creating ODBC data sources

You need an ODBC data source on the client computer for each UNIX or Linux database you wish to access using ODBC. A data source describes how to get to data on a network. For example, a data source may include the name of a database, the server where it resides, and the network used to access the server.

On UNIX or Linux, ODBC data sources are held in a file named *.odbc.ini*. You can edit this file with any text editor to specify data sources. For details, see “Using ODBC data sources on UNIX,” in the *Sybase IQ System Administration Guide*.

You can also use the cross-platform *iqdsn* utility to create data sources. See “The Data Source utility” in the *Sybase IQ Utility Guide*.

On Windows, the ODBC Administrator adds new data sources for you. Each data source allows you to access a database over a network by means of ODBC.

### ❖ Creating an ODBC data source

- 1 To start the ODBC Administrator on your Windows client system, select Sybase > Data Access > ODBC Data Source Administrator.
- 2 In the ODBC Data Source Administrator, click Add on the User DSN tab.
- 3 In the Create New Data Source dialog box, select the Sybase IQ 12 driver and click Finish.

The Configuration dialog box appears.

- 4 Type the Data Source Name in the appropriate text box, Type a Description of the data source in the Description text box if desired. Do not click OK yet.
- 5 Click the Login tab. Type the User ID and Password for your database. For the sample database used in this example, use “DBA” and “SQL”.

- 6 Click the Database tab. If the data source is on a remote machine, type a server name and database file name (with the .DB suffix) in the appropriate text boxes.
- 7 If the data source is on your local machine, type a start line and database name (without the .DB suffix) and skip to Step 8.
- 8 If the data source is on a remote system, click the Network tab. Click the check box for the appropriate protocol and type the options in the adjacent text box. For example, to connect to server on system fiona-pc using TCP/IP protocol and port 1870, you would click TCP/IP and type  
`host=fionaw2k:port=1870`

You could also specify the host network address. For example,

```
host=157.133.66.75:1870
```

---

**Note** When specifying network connections, you need a different *systemname:port#* combination for each database server. The port number must match the one you use when you start the server.

---

- 9 Click OK when you have finished defining your data source.
- 10 The ODBC Data Source Administrator returns you to the User DSN tab.

---

**Note** You cannot connect to a Sybase IQ 12.6 or 12.7 server using an ODBC Data Source Name created for a 12.5 server, even if you specify the same server name, port number, and database name. Use the ODBC Data Source Administrator to remove DSNs created in 12.5 and add new DSNs.

---

You may use files as data sources instead of databases. File data sources are stored as files with the extension *.dsn*. For information about creating a file data source, see *Sybase IQ System Administration Guide*.

#### ❖ Testing an ODBC data source

- 1 Start the database. (To start the Sample Database, use Start > Programs > Sybase > Adaptive Server IQ 12.7 > Start ASIQ Demo Database.)
- 2 In the ODBC Data Source Administrator, select your new data source from the list of User Data Sources.
- 3 Click Configure.
- 4 On the ODBC Configuration dialog box, click Test Connection.

If you cannot access the data source, check that you have filled out the various tabs with correct file and pathnames.

## Storing connection information

If you are running a UNIX client, an *.odbc.ini* file on your system stores the information used to access each database. (Note that the filename begins with a period.)

To connect with ODBC data sources, the location of your *.odbc.ini* file must be referenced by one of the following variables. Sybase IQ searches the directories specified by the variables below in the following order:

- \$ODBCINI – must contain the exact full pathname of the *.odbc.ini* file.
- \$HOME
- Current directory
- \$PATH

Sybase IQ clients ignore the following environment variables when searching for *.odbc.ini*:

- \$ODBC\_HOME
- \$ODBC\_INI

You need to edit the *.odbc.ini* file with any text editor to add entries for your data sources.

Each entry in the *.odbc.ini* file should have the following format:

```
[an_entry_name]
Driver — the driver path
Userid — the user ID
Password — the password
EngineName — the desired engine
CommLinks — tcpip(port=engine_port_number)
AutoStop — no (Required parameter - must be set to no)
DatabaseName — the database name
DatabaseFile — the desired database with path. Used with embedded
databases.
```

For example:

```
[sample_dsn]
Driver=/s3/mysybase12.4.3/ASIQ-12_6/lib/dbodbc9_r.so.1
Userid=DBA
```



```
Password=SQL
EngineName=test_server1
CommLinks=tcPIP(port=1870)
AutoStop=no
DatabaseName=asIQdemo
DatabaseFile=asIQdemo.db
```

Once you have created a data source entry, you can connect to your database, by entering the `dbisql` command at the command prompt and specifying the data source entry name in a connection string. Sybase IQ finds the rest of the connection information in the `.odbc.ini` file. For example:

```
% dbisql -c "dsn=sample_dsn"
```

For more information about `dbisql` and its options, see *Sybase IQ Utility Guide*.

---

**Note** For Sybase IQ Version 12.5 and higher, by default any server that is started from a connection string is *stopped* when there are no more connections to it, and any database that is loaded from a connection string is *unloaded* as soon as there are no more connections to it. (This does not apply in the case of multiplex IQ databases, which are started with Sybase Central.)

---

To have the database continue running after connections disconnect, you must specify the connection parameter `AutoStop=No` in your connection string or data source.

For example, the following data source fragment instructs the client library to keep the database loaded after the connection is dropped:

```
[dbcli7 Connection Parameters]
ServerName=testsrv
Autostop=No
UserID=DBA
Password=SQL
```

To connect without using `.odbc.ini`, enter an Interactive SQL command that specifies the entire entry, like the following. While it is shown here on multiple lines, you must enter the entire command at the command prompt on one line.

```
dbisql -c
"UID=DBA;PWD=SQL;AutoStop=no;DBF=$ASDIR/demo/asIQdemo.
db"
```

## Connecting using OLE DB

OLE DB is a data access model from Microsoft. It uses the Component Object Model (COM) interfaces. Unlike ODBC, OLE DB does not assume that the data source uses a SQL query processor.

This release of Sybase IQ includes an OLE DB provider. If you use the Sybase IQ OLE DB provider, ODBC is not required in your deployment.

OLE DB requires a Windows client. However, you can access both Windows and UNIX servers using OLE DB.

For more information, see *Adaptive Server Anywhere Programming Guide*. For information on connecting to a database using OLE DB, see “Connecting to a database using OLE DB” in Chapter 3, “Sybase IQ Connections,” in the *Sybase IQ System Administration Guide*.

---

**Note** Sybase IQ support for certain features used with OLE DB differs from Adaptive Server Anywhere support. Be aware of these differences when using the Anywhere documentation:

- Sybase IQ does *not* support Windows CE.
  - Sybase IQ does *not* support remote updates through a cursor.
  - Sybase IQ supports Dynamic (dynamic scroll), Static (insensitive), and Forward only (no-scroll) cursors, but does *not* support Keyset (scroll) cursors.
  - In Sybase IQ the isolation level is always 3, no matter what you specify.
- 

## Connecting using Open Client

If you need to insert from an Adaptive Server Enterprise database to a Sybase IQ database, or you want to connect using ISQL, each server must have an entry in the interfaces file on the client computer. Interfaces file entries, also called **server objects**, also simplify database startup. Use DSEDIT (Directory Services Editor) to create entries in the interfaces file. You must be the owner of the Sybase home directory (\$SYBASE) in order to run DSEDIT. For more about DSEDIT, see “Configuring IQ servers with DSEDIT” in Chapter 15, “Sybase IQ as a Data Server,” in the *Sybase IQ System Administration Guide*.

**❖ Adding a server object**

The dsedit utility lets you view and edit server entries in the interfaces file using a GUI based on X11/Motif in UNIX platforms.

- 1 Start the Open Client Directory Service Editor.

```
% $SYBASE/$SYBASE_OCS/bin/dsedit
```

- 2 The default interfaces file and configuration file display.

Click OK to continue or Exit to quit.

- 3 Select “Add new server entry.”

- 4 Type the server name and click Add new network transport. *The server name in your DSEdit entry must be the same as the database name.*

- 5 Select the TCP transport and enter the host name and port number. (The defaults are usually sufficient.) Click OK.

- 6 Click OK.

- 7 The server is now listed under “Available servers.”

- 8 Click Close session to make new server entries usable.

- 9 Click Exit to close dsedit.

- 10 Click Yes to “Are you sure you want to exit dsedit?”

## Running client and server on the same system

Shared memory is the default communications mechanism when the client and server are on the same system. It is configured automatically, and starts up automatically, on both UNIX and Windows platforms. Sybase IQ uses a shared memory segment and several semaphores for communication between the client and server on the same machine.

---

**Note** Local connections through shared memory are not supported for Linux 64-bit. Use standard network connectivity by adding the parameters `-host <hostname>` and `-port <portnumber>` to the client connection string.

---

See the “Connecting using command line utilities” in Chapter 3, “Sybase IQ Connections,” in the *Sybase IQ System Administration Guide* for more on using the `-host` and `-port` parameters.

## Network issues for IQ servers

Properly configured Sybase IQ UNIX servers run under the TCP/IP protocol, which enables non-UNIX clients to communicate with a UNIX database server.

In order for Sybase IQ to run properly, the protocol stack on the client and server computers must be compatible at each layer.

Many vendors supply TCP/IP protocol stacks and associated software. Sybase IQ communications have been explicitly verified with the following TCP/IP implementations:

- **NetWare** TCP/IP For NetWare.
- **Windows** Microsoft Winsock version 2.0.

There are several entries into the TCP/IP protocol stack. Sybase IQ employs the User Datagram Protocol (UDP). While it is called a transport protocol here and elsewhere, UDP provides little more than a user interface to the network layer IP. In particular, UDP is not a guaranteed transmission protocol.

Although the default packet size for TCP/IP is 1460 bytes, a larger packet size may improve query response time, especially for queries transferring a large amount of data between a client and a server process. You can set the maximum packet size using the database server command lines or `CommBufferSize` (CBSIZE) in the client connection string. This option may be used with either the `start_asiq` or the `asiqsrv12` command.

For more information about server startup switches, see the *Sybase IQ Utility Guide*. For more information about connection parameters, see the *Sybase IQ System Administration Guide*.

## Connecting across a firewall

There are restrictions on connections when the client application is on one side of a firewall and the server is on the other. Firewall software filters network packets according to network port. Also, it is common to disallow UDP packets from crossing the firewall.

When connecting across a firewall, you must use a set of communication parameters in the `CommLinks` connection parameter of your application's connection string.

- Set the `ClientPort` parameter to a range of allowed values for the client application to use. You can then configure your firewall to allow these packets across. You can use the short form `CPort`.

- Set the HOST parameter to the host name on which the database server is running. You can use the short form IP.
- Specify the port your database server is using in the ServerPort parameter if it is not using the default port of 2638. You can use the short form Port.
- Set the DoBroadcast=NONE parameter to prevent UDP from being used when connecting to the server.

For more information on these parameters see the section “Network communications parameters” in Chapter 4, “Connection and Communication Parameters,” in the *Sybase IQ System Administration Guide*.

#### Example

In the following example, the connection string fragment:

- Restricts the client application to ports 5050 through 5060
- Connects to a server named myeng running on the machine at address myhost using the server port 2020

No UDP broadcast is carried out because of the DoBroadcast option.

```
CEng=myeng;Links=tcip(ClientPort=5050-5060;Host=myhost;Port=2020;DoBroadcast=NONE)
```



# Index

## A

- Adaptive Server Enterprise
  - inserting data from 78
- after upgrading
  - checking new option settings 52
  - updating configuration files 52
- ALTER DATABASE UPGRADE command 50, 56, 59, 60
- asqdemo.cfg file
  - defaults 67
  - parameters 68
- automounting CD 17
- AUTOSTOP parameter 76, 77

## B

- backing up databases
  - after upgrade 51
  - procedure 51
- before you install 11

## C

- cache settings
  - multiplex upgrade 53
- CD
  - installing from 17
- check constraints
  - sp\_iqprintconstraints** procedure 11
- checking new option settings 52
- client and server, running in same system 79
- client components
  - installing 33
- commands
  - ALTER DATABASE UPGRADE 50, 60
  - autoinstall 25
  - help 25

- COMMLINKS parameter 76, 80
- configuration files 67
  - security 69
- configuration parameters
  - overriding 29, 68
  - set by **start\_asiq** 28
- connecting
  - across firewalls 80
  - using OLE DB 78
  - with JDBC 70
  - with ODBC 71
- connection parameters 76
- connections
  - restricting 50, 65
- conventions
  - documentation ix
  - typographic ix
- creating
  - interfaces file entries 78
  - ODBC data sources 74
  - response file 44

## D

- data sources
  - setting up 74
- data transformation 19, 26
- database options
  - upgrading 49
- databases
  - backing up 51
  - connection parameters 76
  - creating 30
  - sample x, 30
  - upgrading 49, 50
  - upgrading multiplex databases 56, 59
  - verifying 51
- DBF parameter 76
- dbspaces

## Index

- disk space for 9
- debugger 7
- Developer's Kit
  - Sybase IQ 1
- df command 4
- Directory Services Editor 70
  - DSEEDIT 78
- disk space
  - for Sybase Central 3
  - for Sybase IQ ETL Development 38
  - for Sybase IQ Network Client on Linux 35
  - for Sybase IQ Network Client on Windows 38
- disk space requirement 4
- documentation
  - accessibility features x
  - Adaptive Server Anywhere vii
  - conventions ix
  - on CD vii
  - online vii
  - Sybase IQ v
- DSEEDIT 70, 78, 79

## E

- ENG parameter 76, 81
- Enterprise Edition
  - installing 26
  - Sybase IQ 1
- environment
  - setting variables for Sybase IQ 23
  - setting variables for Sybase IQ Network Client 37
- ETL capability 19, 26
- ETL Development
  - installing 39
- Extended Enterprise Edition
  - installing 19
  - Sybase IQ 1
- extract/transform/load capability 19, 26

## F

- Federal Rehabilitation Act
  - section 508 x
- file data sources 75

- file descriptor limits 7
- file protection 7
- firewalls, connecting across 80
- foreign keys 50

## G

- GridNode process
  - stopping 63

## H

- host
  - specifying for ODBC connection 75

## I

- installation
  - testing 30
- installation directory
  - preparing 17
- installation requirements 11
- installing
  - ETL Development 39
  - IQ Agent 54, 58
  - Network Client on Linux 33
  - Network Client on Windows 41
  - without user interaction 43
- interfaces file
  - adding entries 70, 78
- IQ Agent 23
  - installing 54, 58
  - multiple versions 10
  - standalone 10, 54, 58
- IQ servers
  - network connectivity 80
- ISQL
  - connections 78

## J

- jConnect JDBC Driver 16



JDBC  
     configuring connections 70, 78  
     connecting with 70

JRE  
     disk space requirements 35  
     version 16

## K

kernel  
     patches 6  
     kernel configuration file 6

## L

limit command 7  
   Linux 64-bit  
     setting network connectivity 79  
     shared memory restrictions 79  
   LONG BINARY columns 10

## M

memory  
     shared 6, 79  
   migrating data  
     from 32-bit to 64-bit 47, 64  
     from one platform to another 47, 64  
     from prior Sybase IQ version 47, 64  
   mixed-mode multiplex 54, 58  
   mixed-version multiplex 10  
   mounting product CD 17  
   multiplex  
     mixed-mode 54, 58  
     mixed-version 10, 52  
     upgrading 53  
   multiplex databases  
     migrating data 53

## N

network address

    specifying for ODBC connection 75  
   Network Client  
     installing 67  
     installing on Linux 33  
     installing on Windows 41  
   network connections  
     for Linux 64-bit 79  
     specifying 68

## O

ODBC  
     conformance 71  
     connection 71, 75  
     creating data sources 74  
     driver managers 73  
     drivers for UNIX clients 72  
     installing drivers 72  
     performing queries using UNIX or Linux 73  
     testing data source 75  
     third-party applications 73  
   ODBC data sources  
     connecting 76  
     creating 74  
   OLE DB provider 78  
   Open Client 12  
     connecting from 78  
     required for Sybase IQ ETL 15  
   operating system  
     required patches 2  
   option settings, checking 52

## P

packet size 80  
   parameters  
     asqdemo.cfg 68  
     AUTOSTOP 76, 77  
     COMMLINKS 76, 80  
     DBF 76  
     ENG 76, 81  
     overriding startup 68  
     PWD 76, 77  
     sybinstall utility 25, 35

- UID 76, 77
- passwords
  - creating ODBC data source 74
  - protecting 69
  - storing connection information 77
- patches
  - required 2
- performing silent installation 44
- ping command (UNIX) 8
- port number
  - specifying for ODBC connection 75
- preinstallation requirements 11
- PWD parameter 76, 77

## R

- RAM
  - for Sybase IQ 5
- RAM requirement 5
- raw partitions 9
  - message log 9
- readme.txt* file 23
- referential integrity 50
- reinstalling 48
- remote shell 8
- requirements
  - RAM 5
  - Sybase Central 3
- response file, creating 44
- running client and server on same system 79

## S

- sample database x
- SDK 12
- section 508
  - compliance x
- Server Components
  - system requirements 2
- server configuration files 67
- server objects
  - adding 78
- servers
  - shutting down 48

- starting 49
- stopping 30
- setting server configurations 67
- setting up sybase account 17
- shared memory 6, 79
  - setting network connectivity on Linux 64-bit 79
- shutting down servers 48
- silent installation, performing 44
- Software Developer's Kit 12, 16
- Solaris debugger 7
- sp\_iqcheckdb
  - verifying upgraded databases 51
- standalone IQ Agent 10, 54, 58
- standards and compatibility
  - section 508 compliance x
- start\_asiq utility 27
- starting servers 49
  - at command prompt 27
- starting Sybase IQ 27
- starting the IQ Agent
  - procedure 51
  - starting 51
- start-up parameters
  - required 28
- startup parameters
  - overriding 68
- stopping
  - servers 30
- swap space requirement 4
- SYBASE
  - environment variable 18
- sybase account 17
- Sybase Central
  - Java Edition viewer 16
  - requirements 23
  - setup 23
  - system requirements 3
- Sybase IQ
  - reinstalling 48
  - starting 27
  - stopping 30
  - system requirements 2
- Sybase IQ Developer's Kit 1
- Sybase IQ Enterprise Edition
  - installing 26
- Sybase IQ ETL

- Open Client 15
- Sybase IQ ETL Development
  - installing 40
  - launching 41
  - platforms 33
- Sybase IQ ETL Server
  - installing 19, 26
- Sybase IQ Extended Enterprise Edition 1
  - installing 19
- sybinstall
  - bypassing menus 24
- sybinstall utility
  - starting 35
- sybinstall** utility
  - starting 18
- system requirements 2, 3
  - RAM 5
  - Server Components 2
  - swap space 4
  - Sybase Central 3
- utilities
  - DBISQL 30
  - start\_asiq** 27
  - sybinstall** 15
  - utility database 22, 65

## V

- verifying databases
  - after upgrade 51
  - procedure 51

## T

- TCP/IP
  - specifying host and port 75
- telnet
  - trouble logging in 8
- testing
  - ODBC data source 75
- testing the installation 30
- thread limits 7
- transaction log 9

## U

- UID parameter 76, 77
- unenforced foreign keys
  - enforcing referential integrity 50
- updating
  - configuration files 52
- upgrading databases
  - option changes 49
  - procedure 49
- upgrading multiplex databases 53

