

NAG Fortran Library Routine Document

G02GDF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

G02GDF fits a generalized linear model with gamma errors.

2 Specification

```

SUBROUTINE G02GDF(LINK, MEAN, OFFSET, WEIGHT, N, X, LDX, M, ISX, IP, Y,
1          WT, S, A, DEV, IDF, B, IRANK, SE, COV, V, LDV, TOL,
2          MAXIT, IPRINT, EPS, WK, IFAIL)
INTEGER    N, LDX, M, ISX(M), IP, IDF, IRANK, LDV, MAXIT, IPRINT,
1          IFAIL
real     X(LDX,M), Y(N), WT(*), S, A, DEV, B(IP), SE(IP),
1          COV(IP*(IP+1)/2), V(LDV,IP+7), TOL, EPS,
2          WK((IP*IP+3*IP+22)/2)
CHARACTER*1 LINK, MEAN, OFFSET, WEIGHT

```

3 Description

A generalized linear model with gamma errors consists of the following elements:

- (a) a set of n observations, y_i , from a gamma distribution with probability density function:

$$\frac{1}{\Gamma(\nu)} \left(\frac{\nu y}{\mu}\right)^\nu \exp\left(-\frac{\nu y}{\mu}\right) \frac{1}{y}$$

ν being constant for the sample.

- (b) X , a set of p independent variables for each observation, x_1, x_2, \dots, x_p .
(c) a linear model:

$$\eta = \sum \beta_j x_j.$$

- (d) a link between the linear predictor, η , and the mean of the distribution, μ , $\eta = g(\mu)$. The possible link functions are:

- (i) exponent link: $\eta = \mu^a$, for a constant a ,
(ii) identity link: $\eta = \mu$,
(iii) log link: $\eta = \log \mu$,
(iv) square root link: $\eta = \sqrt{\mu}$,
(v) reciprocal link: $\eta = \frac{1}{\mu}$.

- (e) a measure of fit, an adjusted deviance. This is a function related to the deviance, but defined for $y = 0$:

$$\sum_{i=1}^n \text{dev}^*(y_i, \hat{\mu}_i) = \sum_{i=1}^n 2 \left(\log(\hat{\mu}_i) + \left(\frac{y_i}{\hat{\mu}_i}\right) \right).$$

The linear parameters are estimated by iterative weighted least-squares. An adjusted dependent variable, z , is formed:

$$z = \eta + (y - \mu) \frac{d\eta}{d\mu}$$

and a working weight, w ,

$$w = \left(\tau \frac{d\eta}{d\mu} \right)^2, \quad \text{where } \tau = \frac{1}{\mu}.$$

At each iteration an approximation to the estimate of β , $\hat{\beta}$ is found by the weighted least-squares regression of z on X with weights w .

G02GDF finds a QR decomposition of $w^{\frac{1}{2}}X$, i.e.,

$$w^{\frac{1}{2}}X = QR \text{ where } R \text{ is a } p \text{ by } p \text{ triangular matrix and } Q \text{ is an } n \text{ by } p \text{ column orthogonal matrix.}$$

If R is of full rank then $\hat{\beta}$ is the solution to:

$$R\hat{\beta} = Q^T w^{\frac{1}{2}}z$$

If R is not of full rank a solution is obtained by means of a singular value decomposition (SVD) of R .

$$R = Q_* \begin{pmatrix} D & 0 \\ 0 & 0 \end{pmatrix} P^T.$$

where D is a k by k diagonal matrix with non-zero diagonal elements, k being the rank of R and $w^{\frac{1}{2}}X$.

This gives the solution

$$\hat{\beta} = P_1 D^{-1} \begin{pmatrix} Q_* & 0 \\ 0 & I \end{pmatrix} Q^T w^{\frac{1}{2}}z,$$

where P_1 is the first k columns of P , i.e., $P = (P_1 P_0)$.

The iterations are continued until there is only a small change in the deviance.

The initial values for the algorithm are obtained by taking

$$\hat{\eta} = g(y).$$

The scale parameter, ν^{-1} is estimated by a moment estimator:

$$\hat{\nu}^{-1} = \sum_{i=1}^n \frac{[(y_i - \hat{\mu}_i)/\hat{\mu}]^2}{(n - k)}.$$

The fit of the model can be assessed by examining and testing the deviance, in particular, by comparing the difference in deviance between nested models, i.e., when one model is a sub-model of the other. The difference in deviance or adjusted deviance between two nested models with known ν has, asymptotically, a χ^2 distribution with degrees of freedom given by the difference in the degrees of freedom associated with the two deviances.

The parameters estimates, $\hat{\beta}$, are asymptotically Normally distributed with variance-covariance matrix:

$$C = R^{-1} R^{-1T} \nu^{-1} \text{ in the full rank case, otherwise}$$

$$C = P_1 D^{-2} P_1^T \nu^{-1}.$$

The residuals and influence statistics can also be examined.

The estimated linear predictor $\hat{\eta} = X\hat{\beta}$, can be written as $Hw^{\frac{1}{2}}z$ for an n by n matrix H . The i th diagonal elements of H , h_i , give a measure of the influence of the i th values of the independent variables on the fitted regression model. These are known as leverages.

The fitted values are given by $\hat{\mu} = g^{-1}(\hat{\eta})$.

G02GDF also computes the Anscombe residuals, r :

$$r_i = \frac{3(y_i^{\frac{1}{3}} - \hat{\mu}_i^{\frac{1}{3}})}{\hat{\mu}_i^{\frac{1}{3}}}.$$

An option allows the use of prior weights, ω_i . This gives a model with:

$$v_i = v\omega_i.$$

In many linear regression models the first term is taken as a mean term or an intercept, i.e., $x_{i,1} = 1$, for $i = 1, 2, \dots, n$. This is provided as an option.

Often only some of the possible independent variables are included in a model, the facility to select variables to be included in the model is provided.

If part of the linear predictor can be represented by a variables with a known coefficient then this can be included in the model by using an offset, o :

$$\eta = o + \sum \beta_j x_j.$$

If the model is not of full rank the solution given will be only one of the possible solutions. Other estimates may be obtained by applying constraints to the parameters. These solutions can be obtained by using G02GKF after using G02GDF. Only certain linear combinations of the parameters will have unique estimates, these are known as estimable functions, and can be estimated and tested using G02GNF.

Details of the SVD are made available in the form of the matrix P^* :

$$P^* = \begin{pmatrix} D^{-1} P_1^T \\ P_0^T \end{pmatrix}.$$

4 References

Cook R D and Weisberg S (1982) *Residuals and Influence in Regression* Chapman and Hall

McCullagh P and Nelder J A (1983) *Generalized Linear Models* Chapman and Hall

5 Parameters

1: LINK – CHARACTER*1

Input

On entry: indicates which link function is to be used.

If LINK = 'E', then an exponential link is used.

If LINK = 'I', then an identity link is used.

If LINK = 'L', then a log link is used.

If LINK = 'S', then a square root link is used.

If LINK = 'R', then a reciprocal link is used.

Constraint: LINK = 'E', 'I', 'L', 'S' or 'R'.

2: MEAN – CHARACTER*1

Input

On entry: indicates if a mean term is to be included.

If MEAN = 'M' (Mean), a mean term, intercept, will be included in the model.

If MEAN = 'Z' (Zero), the model will pass through the origin, zero-point.

Constraint: MEAN = 'M' or 'Z'.

- 3: OFFSET – CHARACTER*1 Input
On entry: indicates if an offset is required.
 If OFFSET = 'Y', then an offset is required and the offsets must be supplied in the 7th column of V.
 If OFFSET = 'N', no offset is required.
Constraint: OFFSET = 'N' or 'Y'.
- 4: WEIGHT – CHARACTER*1 Input
On entry: indicates if weights are to be used.
 If WEIGHT = 'U' (Unweighted), no prior weights are used.
 If WEIGHT = 'W' (Weighted), prior weights are used and weights must be supplied in WT.
Constraint: WEIGHT = 'U' or 'W'.
- 5: N – INTEGER Input
On entry: the number of observations, n .
Constraint: $N \geq 2$.
- 6: X(LDX,M) – *real* array Input
On entry: $X(i, j)$ must contain the i th observation for the j th independent variable, for $i = 1, 2, \dots, n$; $j = 1, 2, \dots, M$.
- 7: LDX – INTEGER Input
On entry: the first dimension of the array X as declared in the (sub)program from which G02GDF is called.
Constraint: $LDX \geq N$.
- 8: M – INTEGER Input
On entry: the total number of independent variables.
Constraint: $M \geq 1$.
- 9: ISX(M) – INTEGER array Input
On entry: indicates which independent variables are to be included in the model.
 If $ISX(j) > 0$, then the variable contained in the j th column of X is included in the regression model.
Constraints:
 $ISX(j) \geq 0$, for $j = 1, 2, \dots, M$;
 if MEAN = 'M', then exactly IP – 1 values of ISX must be > 0 ;
 if MEAN = 'Z', then exactly IP values of ISX must be > 0 .
- 10: IP – INTEGER Input
On entry: the number of independent variables in the model, including the mean or intercept if present.
Constraint: $IP > 0$.
- 11: Y(N) – *real* array Input
On entry: the dependent variable, y .
Constraint: $Y(i) \geq 0$, for $i = 1, 2, \dots, n$.

- 12: WT(*) – *real* array *Input*
On entry: if WEIGHT = 'W', then WT must contain the weights to be used in the weighted regression. If $WT(i) = 0.0$, then the i th observation is not included in the model, in which case the effective number of observations is the number of observations with non-zero weights.
 If WEIGHT = 'U', then WT is not referenced and the effective number of observations is n .
Constraint: if WEIGHT = 'W', $WT(i) \geq 0.0$, for $i = 1, 2, \dots, n$.
- 13: S – *real* *Input/Output*
On entry: the scale parameter for the gamma model, ν^{-1} .
 If S = 0.0, then the scale parameter is estimated with the routine using the formula described in Section 3.
Constraint: $S \geq 0.0$.
On exit: if on input S = 0.0, then S contains the estimated value of the scale parameter, $\hat{\nu}^{-1}$.
 If on input S \neq 0.0, then S is unchanged on exit.
- 14: A – *real* *Input*
On entry: if LINK = 'E', then A must contain the power of the exponential.
 If LINK \neq 'E', A is not referenced.
Constraint: if LINK = 'E', $A \neq 0.0$.
- 15: DEV – *real* *Output*
On exit: the adjusted deviance for the fitted model.
- 16: IDF – INTEGER *Output*
On exit: the degrees of freedom associated with the deviance for the fitted model.
- 17: B(IP) – *real* array *Output*
On exit: the estimates of the parameters of the generalized linear model, $\hat{\beta}$.
 If MEAN = 'M', the first element of B will contain the estimate of the mean parameter and $B(i + 1)$ will contain the coefficient of the variable contained in column j of X, where $ISX(j)$ is the i th positive value in the array ISX.
 If MEAN = 'Z', $B(i)$ will contain the coefficient of the variable contained in column j of X, where $ISX(j)$ is the i th positive value in the array ISX.
- 18: IRANK – INTEGER *Output*
On exit: the rank of the independent variables.
 If the model is of full rank then $IRANK = IP$.
 If the model is not of full rank then IRANK is an estimate of the rank of the independent variables. IRANK is calculated as the number of singular values greater than $EPS \times (\text{largest singular value})$. It is possible for the SVD to be carried out but for IRANK to be returned as IP.
- 19: SE(IP) – *real* array *Output*
On exit: the standard errors of the linear parameters.
 $SE(i)$ contains the standard error of the parameter estimate in $B(i)$, for $i = 1, 2, \dots, IP$.

- 20: COV(IP*(IP+1)/2) – *real* array *Output*
- On exit:* the upper triangular part of the variance-covariance matrix of the IP parameter estimates given in B. They are stored in packed form by column, i.e., the covariance between the parameter estimate given in B(*i*) and the parameter estimate given in B(*j*), $j \geq i$, is stored in COV($j \times (j - 1)/2 + i$).
- 21: V(LDV,IP+7) – *real* array *Input/Output*
- On entry:* if OFFSET = 'N', V need not be set.
- If OFFSET = 'Y', V(*i*, 7), for $i = 1, 2, \dots, n$, must contain the offset values o_i . All other values need not be set.
- On exit:* auxiliary information on the fitted model.
- V(*i*, 1) contains the linear predictor value, η_i , for $i = 1, 2, \dots, n$.
- V(*i*, 2) contains the fitted value, $\hat{\mu}_i$, for $i = 1, 2, \dots, n$.
- V(*i*, 3) contains the variance standardization, $\frac{1}{\tau_i}$, for $i = 1, 2, \dots, n$.
- V(*i*, 4) contains the square root of the working weight, $w_i^{\frac{1}{2}}$, for $i = 1, 2, \dots, n$.
- V(*i*, 5) contains the Anscombe residual, r_i , for $i = 1, 2, \dots, n$.
- V(*i*, 6) contains the leverage, h_i , for $i = 1, 2, \dots, n$.
- V(*i*, 7) contains the offset, o_i , for $i = 1, 2, \dots, n$. If OFFSET = 'N', then all values will be zero.
- V(*i*, *j*), for $j = 8, \dots, IP + 7$, contains the results of the QR decomposition or the singular value decomposition.
- If the model is not of full rank, i.e., IRANK < IP, then the first IP rows of columns 8 to IP + 7 contain the P^* matrix.
- 22: LDV – INTEGER *Input*
- On entry:* the dimension of the array V as declared in the (sub)program from which G02GDF is called.
- Constraint:* LDV \geq N.
- 23: TOL – *real* *Input*
- On entry:* indicates the accuracy required for the fit of the model.
- The iterative weighted least-squares procedure is deemed to have converged if the absolute change in deviance between iterations is less than TOL \times (1.0 + Current Deviance). This is approximately an absolute precision if the deviance is small and a relative precision if the deviance is large.
- If $0.0 \leq \text{TOL} < \text{machine precision}$ then the routine will use $10 \times \text{machine precision}$ instead.
- Constraint:* TOL \geq 0.0.
- 24: MAXIT – INTEGER *Input*
- On entry:* the maximum number of iterations for the iterative weighted least-squares.
- If MAXIT = 0 then a default value of 10 is used.
- Constraint:* MAXIT \geq 0.

25: IPRINT – INTEGER

Input

On entry: indicates if the printing of information on the iterations is required.

If $\text{IPRINT} \leq 0$, then there is no printing.

If $\text{IPRINT} > 0$, then every IPRINT iteration, the following are printed:

the deviance;

the current estimates;

and if the weighted least-squares equations are singular then this is indicated.

When printing occurs the output is directed to the current advisory message unit (see X04ABF).

26: EPS – *real**Input*

On entry: the value of EPS is used to decide if the independent variables are of full rank and, if not, what is the rank of the independent variables. The smaller the value of EPS the stricter the criterion for selecting the singular value decomposition.

If $0.0 \leq \text{EPS} < \textit{machine precision}$ then the routine will use *machine precision* instead.

Constraint: $\text{EPS} \geq 0.0$.

27: WK((IP*IP+3*IP+22)/2) – *real* array*Workspace*

28: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL \neq 0 on exit, the recommended value is -1. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $N < 2$,
 or $M < 1$,
 or $\text{LDX} < N$,
 or $\text{LDV} < N$,
 or $\text{IP} < 1$,
 or $\text{LINK} \neq \text{'E'}$, 'I' , 'L' , 'S' , or 'R' ,
 or $S < 0.0$,
 or $\text{LINK} = \text{'E'}$ and $A = 0.0$,
 or $\text{MEAN} \neq \text{'M'}$ or 'Z' ,
 or $\text{WEIGHT} \neq \text{'U'}$ or 'W' ,
 or $\text{OFFSET} \neq \text{'N'}$, or 'Y' ,
 or $\text{MAXIT} < 0$,
 or $\text{TOL} < 0.0$,
 or $\text{EPS} < 0.0$.

IFAIL = 2

On entry, WEIGHT = 'W' and a value of WT < 0.0.

IFAIL = 3

On entry, a value of ISX < 0,
or the value of IP is incompatible with the values of MEAN and ISX,
or IP is greater than the effective number of observations.

IFAIL = 4

On entry, $Y(i) < 0$ for some $i = 1, 2, \dots, n$.

IFAIL = 5

A fitted value is at the boundary, i.e., $\hat{\mu} = 0.0$. This may occur if there are small values of y and the model is not suitable for the data. The model should be reformulated with, perhaps, some observations dropped.

IFAIL = 6

The singular value decomposition has failed to converge. This is an unlikely error exit.

IFAIL = 7

The iterative weighted least-squares has failed to converge in MAXIT (or default 10) iterations. The value of MAXIT could be increased but it may be advantageous to examine the convergence using the IPRINT option. This may indicate that the convergence is slow because the solution is at a boundary in which case it may be better to reformulate the model.

IFAIL = 8

The rank of the model has changed during the weighted least-squares iterations. The estimate for β returned may be reasonable, but the user should check how the deviance has changed during iterations.

IFAIL = 9

The degrees of freedom for error are 0. A saturated model has been fitted.

7 Accuracy

The accuracy depends on TOL as described in Section 5. As the adjusted deviance is a function of $\log \mu$, the accuracy of the $\hat{\beta}$ s will be a function of TOL, so TOL should be set to a smaller value than the accuracy required for $\hat{\beta}$.

8 Further Comments

None.

9 Example

A set of 10 observations from two groups is input and a model for the two groups is fitted.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      G02GDF Example Program Text
*      Mark 14 Release.  NAG Copyright 1989.
*      .. Parameters ..
INTEGER          NMAX, MMAX
PARAMETER        (NMAX=10,MMAX=2)
INTEGER          NIN, NOUT
PARAMETER        (NIN=5,NOUT=6)
*      .. Local Scalars ..
real           A, DEV, EPS, S, TOL
INTEGER          I, IDF, IFAIL, IP, IPRINT, IRANK, J, M, MAXIT, N
CHARACTER        LINK, MEAN, OFFSET, WEIGHT
*      .. Local Arrays ..
real           B(MMAX), COV((MMAX*MMAX+MMAX)/2), SE(MMAX),
+               V(NMAX,7+MMAX), WK((MMAX*MMAX+3*MMAX+22)/2),
+               WT(NMAX), X(NMAX,MMAX), Y(NMAX)
INTEGER          ISX(MMAX)
*      .. External Subroutines ..
EXTERNAL         GO2GDF
*      .. Executable Statements ..
WRITE (NOUT,*) 'G02GDF Example Program Results'
*      Skip heading in data file
READ (NIN,*)
READ (NIN,*) LINK, MEAN, OFFSET, WEIGHT, N, M, S, IPRINT
IF (N.LE.NMAX .AND. M.LT.MMAX) THEN
  IF (WEIGHT.EQ.'W' .OR. WEIGHT.EQ.'w') THEN
    DO 20 I = 1, N
      READ (NIN,*) (X(I,J),J=1,M), Y(I), WT(I)
20    CONTINUE
  ELSE
    DO 40 I = 1, N
      READ (NIN,*) (X(I,J),J=1,M), Y(I)
40    CONTINUE
  END IF
  READ (NIN,*) (ISX(J),J=1,M)
*      Calculate IP
  IP = 0
  DO 60 J = 1, M
    IF (ISX(J).GT.0) IP = IP + 1
60  CONTINUE
  IF (MEAN.EQ.'M' .OR. MEAN.EQ.'m') IP = IP + 1
  IF (LINK.EQ.'E' .OR. LINK.EQ.'e') READ (NIN,*) A
*      Set control parameters
  EPS = 0.000001e0
  TOL = 0.00005e0
  MAXIT = 10
  IFAIL = -1
*
  CALL GO2GDF(LINK,MEAN,OFFSET,WEIGHT,N,X,NMAX,M,ISX,IP,Y,WT,S,A,
+             DEV,IDF,B,IRANK,SE,COV,V,NMAX,TOL,MAXIT,IPRINT,EPS,
+             WK,IFAIL)
*
  IF (IFAIL.EQ.0 .OR. IFAIL.GE.7) THEN
    WRITE (NOUT,*)
    WRITE (NOUT,99999) 'Deviance = ', DEV
    WRITE (NOUT,99998) 'Degrees of freedom = ', IDF
    WRITE (NOUT,*)
    WRITE (NOUT,*) '      Estimate      Standard error'
    WRITE (NOUT,*)
    DO 80 I = 1, IP
      WRITE (NOUT,99997) B(I), SE(I)
80    CONTINUE
    WRITE (NOUT,*)
    WRITE (NOUT,*) '      Y      FV      Residual      H'
    WRITE (NOUT,*)
    DO 100 I = 1, N

```

```

          WRITE (NOUT,99996) Y(I), V(I,2), V(I,5), V(I,6)
100      CONTINUE
          END IF
        END IF
      STOP
*
99999 FORMAT (1X,A,e12.4)
99998 FORMAT (1X,A,I2)
99997 FORMAT (1X,2F14.4)
99996 FORMAT (1X,F7.1,F10.2,F12.4,F10.3)
      END

```

9.2 Program Data

G02GDF Example Program Data

```

'R' 'M' 'N' 'U' 10 1 0.0 0
1.0 1.0
1.0 0.3
1.0 10.5
1.0 9.7
1.0 10.9
0.0 0.62
0.0 0.12
0.0 0.09
0.0 0.50
0.0 2.14
1

```

9.3 Program Results

G02GDF Example Program Results

Deviance = 0.3503E+02

Degrees of freedom = 8

	Estimate	Standard error		
	1.4408	0.6678		
	-1.2865	0.6717		
Y	FV	Residual	H	
1.0	6.48	-1.3909	0.200	
0.3	6.48	-1.9228	0.200	
10.5	6.48	0.5236	0.200	
9.7	6.48	0.4318	0.200	
10.9	6.48	0.5678	0.200	
0.6	0.69	-0.1107	0.200	
0.1	0.69	-1.3287	0.200	
0.1	0.69	-1.4815	0.200	
0.5	0.69	-0.3106	0.200	
2.1	0.69	1.3665	0.200	
