NAG Toolbox for MATLAB

d02ha

1 Purpose

d02ha solves the two-point boundary-value problem for a system of ordinary differential equations, using a Runge–Kutta–Merson method and a Newton iteration in a shooting and matching technique.

2 Syntax

$$[u, soln, w, ifail] = d02ha(u, v, a, b, tol, fcn, m1, 'n', n)$$

3 Description

d02ha solves the two-point boundary-value problem for a system of n ordinary differential equations in the range a, b. The system is written in the form:

$$y'_i = f_i(x, y_1, y_2, \dots, y_n), \qquad i = 1, 2, \dots, n$$
 (1)

and the derivatives f_i are evaluated by user-supplied (sub)program **fcn**. Initially, n boundary-values of the variables y_i must be specified, some of which will be specified at a and some at b. You must supply estimates of the remaining n boundary-values (called parameters below), and the (sub)program corrects them by a form of Newton iteration. It also calculates the complete solution on an equispaced mesh if required.

Starting from the known and estimated values of y_i at a, the (sub)program integrates the equations from a to b (using a Runge–Kutta–Merson method). The differences between the values of y_i at b from integration and those specified initially should be zero for the true solution. (These differences are called residuals below.) The (sub)program uses a generalized Newton method to reduce the residuals to zero, by calculating corrections to the estimated boundary-values. This process is repeated iteratively until convergence is obtained, or until the function can no longer reduce the residuals. See Hall and Watt 1976 for a simple discussion of shooting and matching techniques.

4 References

Hall G and Watt J M (ed.) 1976 Modern Numerical Methods for Ordinary Differential Equations Clarendon Press, Oxford

5 Parameters

5.1 Compulsory Input Parameters

1: u(n,2) – double array

 $\mathbf{u}(i,1)$ must be set to the known or estimated value of y_i at a, and $\mathbf{u}(i,2)$ must be set to the known or estimated value of y_i at b, for $i=1,2,\ldots,n$.

2: $\mathbf{v}(\mathbf{n},\mathbf{2}) - \mathbf{double}$ array

 $\mathbf{v}(i,j)$ must be set to 0.0 if $\mathbf{u}(i,j)$ is a known value, and 1.0 if $\mathbf{u}(i,j)$ is an estimated value to be corrected.

Constraint: precisely n of the $\mathbf{v}(i,j)$ must be set to 0.0, i.e., precisely n of the $\mathbf{u}(i,j)$ must be known values, and these must not be all at a or all at b.

3: **a – double scalar**

a, the initial point of the interval of integration.

[NP3663/21] d02ha.1

d02ha NAG Toolbox Manual

4: **b** – **double scalar**

b, the final point of the interval of integration.

5: tol – double scalar

Must be set to a small quantity suitable for

- (a) testing the local error in y_i during integration,
- (b) testing for the convergence of y_i at b,
- (c) calculating the perturbation in estimated boundary-values for y_i , which are used to obtain the approximate derivatives of the residuals for use in the Newton iteration.

You are advised to check your results by varying tol.

Constraint: tol > 0.0.

6: fcn – string containing name of m-file

fcn must evaluate the functions f_i (i.e., the derivatives y_i'), for i = 1, 2, ..., n, at a general point x. Its specification is:

$$[f] = fcn(x, y)$$

Input Parameters

1: x - double scalar

x, the value of the argument.

2: $\mathbf{y}(n)$ – double array

The value of the argument y_i , for i = 1, 2, ..., n.

Output Parameters

1: $\mathbf{f}(n)$ – double array

The value of $f_i(x)$, for i = 1, 2, ..., n.

7: m1 - int32 scalar

a value which controls output.

m1 = 1

The final solution is not evaluated.

m1 > 1

The final values of y_i at interval $(b-a)/(\mathbf{m1}-1)$ are calculated and stored in the array **soln** by columns, starting with values y_i at a stored in $\mathbf{soln}(i,1)$, for $i=1,2,\ldots,n$.

Constraint: $m1 \ge 1$.

5.2 Optional Input Parameters

1: n - int32 scalar

Default: The dimension of the arrays **u**, **v**, **soln**, **w**. (An error is raised if these dimensions are not equal.)

n, the number of equations.

Constraint: $\mathbf{n} \geq 2$.

d02ha.2 [NP3663/21]

5.3 Input Parameters Omitted from the MATLAB Interface

sdw

5.4 Output Parameters

1: $\mathbf{u}(\mathbf{n},\mathbf{2}) - \mathbf{double}$ array

The known values unaltered, and corrected values of the estimates, unless an error has occurred. If an error has occurred, **u** contains the known values and the latest values of the estimates.

2: soln(n,m1) - double array

The solution when m1 > 1 (see below).

3: w(n,sdw) - double array

If **ifail** = 2, 3, 4 or 5, $\mathbf{w}(i, 1)$ contains the solution at the point where the integration fails, for i = 1, 2, ..., n, and the point of failure is returned in $\mathbf{w}(1, 2)$.

4: ifail – int32 scalar

0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

ifail = 1

One or more of the parameters v, n, m1, sdw, or tol is incorrectly set.

ifail = 2

The step length for the integration is too short whilst calculating the residual (see Section 8).

ifail = 3

No initial step length could be chosen for the integration whilst calculating the residual.

Note: if ail = 2 or 3 can occur due to choosing too small a value for tol or due to choosing the wrong direction of integration. Try varying tol and interchanging a and b. These error exits can also occur for very poor initial estimates of the unknown initial values and, in extreme cases, because this function cannot be used to solve the problem posed.

ifail = 4

As for ifail = 2 but the error occurred when calculating the Jacobian of the derivatives of the residuals with respect to the parameters.

ifail = 5

As for **ifail** = 3 but the error occurred when calculating the derivatives of the residuals with respect to the parameters.

ifail = 6

The calculated Jacobian has an insignificant column.

Note: **ifail** = 4, 5 or 6 usually indicate a badly scaled problem. You may vary the size of **tol** or change to one of the more general functions d02hb or d02sa which afford more control over the calculations.

[NP3663/21] d02ha.3

d02ha NAG Toolbox Manual

ifail = 7

The linear algebra function (f08kb) used has failed. This error exit should not occur and can be avoided by changing the estimated initial values.

ifail = 8

The Newton iteration has failed to converge.

Note: ifail = 8 can indicate poor initial estimates or a very difficult problem. Consider varying tol if the residuals are small in the monitoring output. If the residuals are large try varying the initial estimates.

ifail = 9 ifail = 10 ifail = 11 ifail = 12 ifail = 13

Indicate that a serious error has occurred in "temp_tag_xref_d02saz d02saw d02sax d02sau d02sav"doned02saz d02saw d02sav respectively. Check all array subscripts and (sub)program parameter lists in calls to d02ha. Seek expert help.

7 Accuracy

If the process converges, the accuracy to which the unknown parameters are determined is usually close to that specified by you; the solution, if requested, may be determined to a required accuracy by varying the parameter tol.

8 Further Comments

The time taken by d02ha depends on the complexity of the system, and on the number of iterations required. In practice, integration of the differential equations is by far the most costly process involved.

Wherever it occurs in the function, the error parameter **tol** is used in 'mixed' form; that is **tol** always occurs in expressions of the form **tol** \times $(1 + |y_i|)$. Though not ideal for every application, it is expected that this mixture of absolute and relative error testing will be adequate for most purposes.

You are strongly recommended to set **ifail** to obtain self-explanatory error messages, and also monitoring information about the course of the computation. You may select the channel numbers on which this output is to appear by calls of x04aa (for error messages) or x04ab (for monitoring information) – see Section 9 for an example. Otherwise the default channel numbers will be used. The monitoring information produced at each iteration includes the current parameter values, the residuals and two norms: a basic norm and a current norm. At each iteration the aim is to find parameter values which make the current norm less than the basic norm. Both these norms should tend to zero as should the residuals. (They would all be zero if the exact parameters were used as input.) For more details, you may consult the specification of d02sa, and especially the description of the parameter (sub)program **monit** there.

The computing time for integrating the differential equations can sometimes depend critically on the quality of the initial estimates. If it seems that too much computing time is required and, in particular, if the values of the residuals printed by the monitoring function are much larger than the expected values of the solution at b, then the coding of the user-supplied (sub)program **fcn** should be checked for errors. If no errors can be found, an independent attempt should be made to improve the initial estimates. In practical problems it is not uncommon for the differential equation to have a singular point at one or both ends of the range. Suppose a is a singular point; then the derivatives y_i' in (1) (in Section 3) cannot be evaluated at a, usually because one or more of the expressions for f_i give overflow. In such a case it is necessary for you to take a a short distance away from the singularity, and to find values for y_i at the new value of a (e.g., use the first one or two terms of an analytical (power series) solution). You should experiment with the new position of a; if it is taken too close to the singular point, the derivatives f_i will be inaccurate, and the function may sometimes fail with **ifail** = 2 or 3 or, in extreme cases, with an overflow condition. A more general treatment of singular solutions is provided by the (sub)program d02hb.

d02ha.4 [NP3663/21]

Another difficulty which often arises in practice is the case when one end of the range, b say, is at infinity. You must approximate the end point by taking a finite value for b, which is obtained by estimating where the solution will reach its asymptotic state. The estimate can be checked by repeating the calculation with a larger value of b. If b is very large, and if the matching point is also at b, the numerical solution may suffer a considerable loss of accuracy in integrating across the range, and the program may fail with **ifail** = b or b. (In the former case, solutions from all initial values at b are tending to the same curve at infinity.) The simplest remedy is to try to solve the equations with a smaller value of b, and then to increase b in stages, using each solution to give boundary-value estimates for the next calculation. For problems where some terms in the asymptotic form of the solution are known, b02h will be more successful.

If the unknown quantities are not boundary-values, but are eigenvalues or the length of the range or some other parameters occurring in the differential equations, d02hb may be used.

9 Example

```
d02ha_fcn.m
 function f = fcn(x,y)
   f = zeros(3,1);
   f(1) = tan(y(3));
   f(2) = -0.032*tan(y(3))/y(2) - 0.02*y(2)/cos(y(3));
   f(3) = -0.032/y(2)^2;
u = [0, 0;
     0.5, 0.46;
     1.15, -1.2];
v = [0, 0;
     0, 1;
     1, 1];
a = 0;
b = 5;
tol = 0.0005;
m1 = int32(6);
[uOut, soln, w, ifail] = dO2ha(u, v, a, b, tol, 'dO2ha_fcn', m1)
uOut =
         0
                    0
    0.5000
              0.4597
    1.1681
             -1.2014
soln =
         0
               1.9177
                         2.9280
                                    2.9770
                                               2.0210
                                                         -0.0000
    0.5000
                                    0.1955
                         0.2070
                                               0.3095
                                                         0.4597
              0.3343
              0.9749
                         0.4929
                                   -0.4194
                                              -0.9752
                                                         -1.2014
    1.1681
Tw7 =
  Columns 1 through 7
                         0.0005
                                    1.0000
                                               0.0000
                                                         -0.0000
                                                                    0.0000
    0.4597
              0.0005
              0.0005
                         0.0005
                                    1.0000
                                               0.0000
                                                         0.0000
                                                                    0.0000
    1.1681
   -1.2014
              0.0005
                         0.0005
                                    1.0000
                                               0.0000
                                                          0.0000
                                                                   -0.0001
  Columns 8 through 14
    0.4597
               0.0000
                         0.0000
                                   -0.0006
                                              25.3719
                                                          0.0394
                                                                   -0.9939
                        -0.0000
                                               1.0000
                                                          1.0000
                                                                    0.0600
    1.1681
              0.0000
                                    0.0000
             -0.0000
                         0.0000
                                    0.0000
                                               0.9939
                                                          1.0061
                                                                   -0.0925
   -1.2015
  Columns 15 through 21
   -0.0000
              -0.1103
                        -0.0024
                                    1.0000
                                               0.0036
                                                         -0.0000
                                                                    0.4597
   -0.8390
              -0.5407
                         0.8390
                                    0.0000
                                               0.5441
                                                         0.4597
   -0.5441
               0.8339
                         0.5441
                                    0.0043
                                              -0.8390
                                                         -1.2014
                                                                   -1.2014
  Columns 22 through 28
   -2.5827
              0.0524
                        -2.5591
                                    0.1596
                                              -2.5101
                                                         -0.0000
                                                                    0.0005
    0.1543
              0.4565
                         0.1543
                                    0.4500
                                               0.1542
                                                          0.0000
                                                                    0.0005
   -0.1514
              -1.1983
                        -0.1535
                                              -0.1580
                                                          0.0000
                                   -1.1917
                                                                    0.0005
  Columns 29 through 35
                        -0.0000
                                    0.0005
                                               0.0000
                                                               0
                                                                          0
    0.0000
             -0.0000
                                                               0
                                                                   -1.0000
    0.0000
              0.4597
                         0.0000
                                    0.0005
                                               0.0000
    0.0000
             -1.2014
                         0.0000
                                    0.0005
                                               0.0000
                                                               0
                                                                          0
```

[NP3663/21] d02ha.5

d02ha NAG Toolbox Manual

```
Columns 36 through 37

-25.2173 0

1.5202 0

-2.3445 -1.0000

ifail =
```

d02ha.6 (last) [NP3663/21]