


Application System/400

SC41-0011-02

Guide to Programming Application and Help Displays

Version 2



Application Development



Application System/400

SC41-0011-02

**Guide to Programming Application
and Help Displays**

Version 2

Take Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page xxix.

Third Edition (November 1993)

This edition applies to the licensed program IBM Operating System/400 (Program 5738-SS1), Version 2 Release 3 Modification 0, and to all subsequent releases and modifications until otherwise indicated in new editions. This major revision makes obsolete SC41-0104-00 and SC41-0011-01. Make sure you are using the proper edition for the level of the product.

Order publications through your IBM representative or the IBM branch serving your locality. Publications are not stocked at the address given below.

A Customer Satisfaction Feedback form for readers' comments is provided at the back of this publication. If the form has been removed, you can mail your comments to:

Attn Department 245
IBM Corporation
3605 Highway 52 N
Rochester, MN 55901-7899 USA

or you can fax your comments to:

United States and Canada: 800+937-3430
Other countries: (+1)+507+253-5192

When you send information to IBM, you grant IBM a non-exclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you or restricting your use of it.

© Copyright International Business Machines Corporation 1991, 1993. All rights reserved.

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

Notices	xxix
Programming Interface Information	xxix
Trademarks and Service Marks	xxx
 About This Guide	 xxxi
Who Should Use This Guide	xxxi
 Summary of Changes	 xxxiii

Part 1. Building a Sample Display with Online Help Information

Chapter 1. Building a Sample Display with Online Help Information	1-1
---	-----

Part 2. Programming Application Displays Using Display Files

Chapter 2. Defining Your Display in a Display File	2-1
Establishing a Display File	2-1
Determining File Descriptions	2-2
Deciding Whether to Describe Data Inside or Outside Your Program	2-3
Creating a Display File and Description	2-4
Changing the File Description	2-5
Detecting File Description Changes	2-6
Defining Display Fields and Functions in a Record Format	2-7
Understanding the Field Attribute Characters	2-8
Understanding How Record Format Fields Can Be Used	2-9
Defining Function Keys	2-11
Defining Command Attention (CAnn) and Command Function (CFnn) Keys	2-12
Specifying Alternative Keys	2-13
Passing Information via Indicators	2-14
Inserting Constant Field Text from a Message Description	2-15
Allowing for Right-to-Left Cursor Movement	2-16
Specifying Right-to-Left Display Processing	2-16
Emphasizing Fields	2-17
Adding Color	2-18
Editing Output Fields	2-18
Defining Your Own Edit Codes	2-19
Specifying Valid Screen Sizes	2-20
Enabling Your Display to Be Printed	2-21
Defining Windows	2-22
Using Program-Described Data	2-22
Defining Input-Only Files	2-23
Defining Output-Only Files	2-23
Defining Input and Output Files	2-24
 Chapter 3. Working with Display Files in an Application	 3-1
Understanding How the System Allocates Resources	3-1
Opening Display Files	3-2
Acquiring a Display Station for I/O Operations	3-2
Obtaining Information about Display Files and Display Stations	3-3

Obtaining Information about Open and I/O Operations	3-3
Obtaining Attribute Information about Display Stations	3-4
Sending and Receiving Data	3-4
Determining Which Record Formats Are Active on a Display	3-5
Writing Output to the Display	3-5
Inviting Input to the Display	3-30
Reading Invited Input from the Display	3-31
Reading Input from the Display	3-33
Writing Output and Reading Input at the Same Time	3-40
Canceling Input That Was Not Waited For	3-41
Locking the Keyboard and Positioning the Cursor During I/O Operations	3-41
Saving Previously Displayed Information	3-42
Understanding the Effects of I/O Operations on Command Keys	3-45
Avoiding Record Format Problems on the 5250 Display Station	3-45
Releasing an Acquired Display Station from I/O Operations	3-49
Closing Display Files	3-49
Mapping Display Operations to High-Level Language Operations	3-49
Sharing Display Files in the Same Job	3-50
Understanding the Open Operation for Files Shared in a Job	3-51
Understanding the Input/Output Operation for Files Shared in a Job	3-51
Understanding the Close Operation for Files Shared in a Job	3-52
Chapter 4. Displaying Groups of Records Using Subfiles	4-1
Recognizing Subfile Uses	4-1
Describing Subfiles in Your DDS Source	4-3
Using a Subfile in a Program	4-7
Requesting I/O Operations for a Subfile	4-9
Requesting I/O Operations for a Subfile Record Format	4-9
Requesting I/O Operations for a Subfile Control Record Format	4-11
Recognizing Subfile I/O Requests in High-Level Languages	4-12
Controlling the Appearance of Subfiles	4-12
Displaying Horizontal Subfiles with Display Modes	4-14
Specifying Subfile Size Equal to Page Size	4-15
Specifying Subfile Size Not Equal to Page Size	4-17
Checking Validity on Subfile Data	4-18
Displaying Error Messages from Subfiles	4-19
Positioning the Cursor on the Displayed Subfile	4-20
Positioning the Cursor Initially	4-20
Positioning the Cursor When a Roll Key Is Used	4-21
Positioning the Cursor When a Fold or Truncate Key Is Used	4-24
Positioning the Cursor and Rolling When Two or More Records Are Displayed	4-24
Understanding Subfile DDS and Program Logic—Example	4-28
Chapter 5. Defining Windows with Display Files	5-1
Window Terminology	5-2
DDS Window Keywords	5-2
Window Representation and Hardware Configuration	5-2
Creating Windows	5-3
Window Definition Records	5-3
Window Reference Records	5-3
Window Size and Location	5-4
Cursor Position	5-5
Error Messages	5-5

Subfiles	5-6
DDS Help Records	5-6
Defining Window Borders	5-7
Border Defaults	5-7
Multiple Border Definitions	5-7
UIM Help Window Borders	5-8
Reading Data from Windows	5-9
Changing Window Borders and Contents	5-9
Moving and Duplicating Windows	5-9
Making Two Windows Seem Active at Once	5-9
Making One Window in a Series Stand Out	5-10
Removing Windows	5-11
Removing All Windows	5-11
Removing More Recent Windows	5-11
Improving Application Performance	5-11
System Save and Restore Operations	5-12
Bypassing System Save and Restore Operations	5-12
Programming Examples	5-14
Using Basic Window Functions	5-14
Defining Windows in a Separate Display File	5-19
RPG Program Source	5-20
RPG Program Source for WINPGM	5-20

Chapter 6. Creating a Graphical Look for Displays	6-1
Factors Affecting the Graphical Look	6-1
Hardware Configuration	6-2
Enhanced Display Parameter	6-3
DDS Keywords	6-4
Creating Menu Bars	6-6
Defining the Menu-Bar Choices	6-6
Defining the Menu-Bar Separator	6-6
Creating Selection Fields	6-9
Single-Choice Selection Field	6-9
Multiple-Choice Selection Field	6-10
Controlling the Availability of Choices	6-11
Creating Pull-Down Menus Using Single-Choice Selection Fields	6-13
Controlling the Selection Characters	6-15
Defining Accelerator Keys	6-16
Defining a Menu-Bar Switch Key	6-17
Defining a Cancel Key	6-18
Defining Mnemonics	6-19
Defining Choice Colors and Attributes	6-19
How the Menu Bar Interacts with the Application	6-22
Defining the MNUBARDSP Keyword on the Application Record	6-22
Defining the MNUBARDSP Keyword on the Menu-Bar Record	6-24
Receiving Input from the Pull-Down Menus	6-25
Removing a Pull-Down Menu after Receiving Input	6-27
Updating a Pull-Down Menu before Displaying	6-28
Defining Application Help	6-29
Defining Choice-Level Help	6-29
Defining Help for a Field	6-31
Key Interaction for Menu Bars and Pull-Down Menus	6-32
Creating Continued-Entry Fields	6-33
Forward Field-Exit Processing	6-36

Backward Field-Exit Processing	6-36
Defining Cursor Progression for Entry Fields	6-36
Defining Attributes for Entry Fields	6-37
Protecting Entry Fields Using Edit Masks	6-38
Cursor Movement	6-38
Pressing the Tab Key	6-39
Pressing the Cursor Keys	6-39
Simple Hotspots	6-40
Command Key Emulation	6-40
Page Up and Page Down Key Emulation	6-41
Programming Examples	6-41
Using the MNUBARDSP Keyword on the Application Record	6-41
Using the MNUBARDSP Keyword on the Menu-Bar Record	6-43
How the Displays Look	6-45
 Chapter 7. Overriding Display Files and Display File Attributes	 7-1
Determining Whether or Not to Use Overrides	7-1
Overriding File Attributes in HLL Programs	7-1
Overriding File Names in HLL Programs	7-3
Overriding Both File Names and Attributes in HLL Programs	7-3
Applying Overrides When Compiling a Program	7-4
Deleting Overrides	7-5
Displaying Overrides	7-6
Using File Redirection to Override File Names and Libraries or File Types	7-6
Overriding Files with the Same File Types	7-6
Overriding Files with Different File Types	7-6
Recognizing Commands That Ignore or Restrict Overrides	7-9
 Chapter 8. Handling Messages and Errors for Display Files	 8-1
Creating and Displaying Your Own Messages	8-1
Displaying a Message on the Message Line	8-2
Displaying a Message on the Message Line When a Subfile Control Record is Written	8-2
Displaying a Message on the Message Line Using a Message Field	8-3
Priorities for Displaying Messages on a Message Line	8-3
Displaying Messages in a Field on the Display	8-3
Displaying Messages on a Program Message Queue	8-4
Displaying Error Messages through a Subfile	8-4
Sounding an Alarm for Messages	8-7
Automatically Handling Permanent I/O Errors on Display Stations	8-7
Analyzing Error Messages Sent from the System	8-8
Understanding Messages and Message Monitors	8-9
Understanding Major/Minor Return Codes	8-10
Recovering from Errors	8-11
 Chapter 9. Creating and Accessing Menus Using Display Files	 9-1
Running System and User-Defined Menus	9-1
Returning to a Menu after Running the GO command	9-1
Determining the Previous Menu	9-1
Using the Cancel and Exit Keys on Menus	9-2
Choosing the Menu That Is Shown at Sign-On Time	9-3
Defining Your Own Display File Menus	9-4
Understanding DDS and Display File Considerations for Menus	9-4
Describing Menu Actions in a Message File	9-5

Naming Help Formats for Menus	9-6
Building a Display File Menu	9-7
Defining Your Own Program Menus	9-10
Passing Parameters for Program Menus	9-10
Building a Program Menu	9-11
Exiting from a Program Menu without Returning to the Previous Menu	9-13
Avoiding Menu Name Conflict	9-15
Naming Your Menus	9-15
Placing Your Menu in a Higher Library in the Library List	9-16
Specifying the Library That Contains the Menu	9-16
Using the Generic Menu Specification	9-16
Changing the Command Default after Duplicating a Command	9-16
Displaying Menu Attributes	9-16
Changing Menu Attributes	9-16
Deleting Menus	9-17
 Chapter 10. Using User-Defined Data Streams	 10-1
Understanding Display Station Differences	10-1
Understanding User-Defined Data Stream Limitations	10-2
 Chapter 11. Passing Data between Programs	 11-1
Passing Data in the Same Routing Step in a Job	11-1
Passing Data between Routing Steps in a Job	11-3
 Chapter 12. Waiting for Input from a Display File, an ICF File, and a Data Queue	 12-1
 Chapter 13. Using Alternative Character Sets and Code Pages	 13-1
Specifying Character Translation for Fields	13-2
Determining the Character Identifier (CHRID) Value for Your Display	13-4
 Chapter 14. Improving System Performance with Displays	 14-1
Deferring the Write Operation for a Display File	14-1
Designating the Primary Screen Size for a Display File	14-1
Writing Only One Page of Subfile Records at a Time	14-1
Sharing an Open Data Path (ODP) for the Same Job	14-2
Sending Records with Input Fields to the Display in Order	14-2
Overlapping and Not Deleting Repeatedly Sent Records	14-2
Restoring the Display	14-3
Defining Command Attention Keys Rather Than Command Function Keys	14-3
Using the Invite Operation	14-3
Using Windows	14-4

Part 3. Programming Application Displays Using Panel Groups

 Chapter 15. Improving Productivity with User Interface Manager	 15-1
Increasing User Productivity	15-1
Increasing Application Programmer Productivity	15-1
What to Consider before Using UIM Instead of Data Description Specifications (DDS)	15-1
 Chapter 16. Introduction to the User Interface Manager	 16-1
Overview of UIM	16-1

What the UIM Supports	16-1
What Is a Panel Group	16-2
What Is a Menu	16-2
Creating Objects	16-3
Elements Within a Panel Group	16-3
Using the UIM Language Tags	16-3
Using Dialog Commands	16-4
Using Control Language (CL) Commands	16-5
Using an Application Programming Interface (API)	16-5
Defining a Menu Object Using UIM	16-6
Creating a Menu Panel	16-6
Required Tags for a Menu Panel	16-8
Source for Example Menu	16-9
Defining a Panel Group Object Using UIM	16-13
Creating a List Panel	16-13
Required Tags for a List Panel	16-17
Source for Example List Panel	16-18
Application Programming for a List Panel	16-26
Creating a Confirmation List Panel	16-27
Required Tags for a Confirmation List Panel	16-28
Source for Example Confirmation Panel	16-28
Automatic Confirmation Processing	16-31
Application Programming for Confirmation Processing	16-32
Creating a Data Presentation Panel	16-32
Required Tags for a Data Presentation Panel	16-35
Source for Example Data Presentation Panel	16-36
Application Programming for a Data Presentation Panel	16-47
Data Entry Panel	16-50
Creating a Panel with a Menu Bar	16-51
Required Tags for a Panel with a Menu Bar	16-53
Source for Example Panel with a Menu Bar	16-54
Application Programming for a Menu Bar Panel	16-64
Chapter 17. Details of Using User Interface Manager	17-1
Opening a UIM Application	17-1
Defining Dialog Variables	17-1
Restrictions on Using Dialog Variables	17-2
Dialog Variable Error Messages	17-3
Providing Field Values for a Display Panel Using Dialog Variables	17-4
Using Variable Pool Services	17-4
Character Set and Code Page Considerations	17-5
Managing a List	17-6
Defining a List	17-6
Initializing a List	17-6
Displaying a List	17-7
Updating a List	17-7
Removing and Inserting an Entry from a List	17-7
Controlling List Entries on a List Display	17-8
Improving Interactive Response Time for a List Display	17-9
Using Action Lists and Selection Lists	17-9
Using Selection Characters	17-11
Managing Panel Functions	17-11
Scrolling Support	17-12
Defining Scrollable Areas	17-12

Defining Function Key Scrolling	17-12
Scrolling and Error Conditions	17-13
Scrolling a List Area	17-13
Scrolling a Menu Area	17-13
Scrolling an Information Area	17-13
Scrolling Data Item Groups	17-14
Defining Contextual Help	17-14
Command Line Restrictions	17-16
Command Line Interpretation	17-16
Entering Commands That Are Too Long	17-17
Defining Function Keys	17-17
Formatting Function Keys	17-17
Handling Function Keys and VARUPD Value	17-18
Panel Formatting Concepts	17-19
When Panel Formatting Is Performed	17-19
Application Control of Panel Formatting	17-20
Limits of the Panel Formatter	17-21
Folding Up Multiple Panels When EXIT Is Requested	17-21
Folding Up a List Panel	17-23
Adding a Pop-Up Window over Another Panel	17-24
Using Menu Bars	17-24
Differences Between Pull-Down Menus and Pop-Up Windows	17-25
Using Pop-Up Windows	17-27
Defining Application Windows	17-27
Adding and Removing Windows	17-28
Using the Command Line in a Window	17-29
UIM as a Request Processor Program When Displaying a Panel	17-30
Printing Concepts	17-30
Printing a Print Head Panel	17-32
Printing a Print Panel	17-32
Using Blank Lines for Separating	17-33
Fonts and Highlighting	17-33
Printing the Trailer	17-33
Defining Prolog Areas	17-33
Defining Header Areas	17-33
Using the Page-Eject Function During Printing	17-34
Sharing and Overriding Printer Files	17-34
Printing Double-Byte Character Set (DBCS) Considerations	17-34

Part 4. Programming Help Displays

Chapter 18. Making Online Help Information Accessible for Your Display File	18-1
Enabling the Help Key	18-2
Choosing between Panel Groups, Documents, and Records for Help	18-2
Defining Which Areas of Your Display Need Online Help Information	18-3
Specifying Panel Groups for Help in Your Display File	18-6
Copying QUSRTOOL Examples That Specify Help Using Panel Groups	18-9
Specifying Documents in Your Display File	18-9
Specifying Records in Your Display File	18-12
Entering the Records That Contain the Help Information	18-14
Using Records and Documents for Help in the Same Display File	18-15
Understanding the Restrictions on Records	18-15

Paging between Help Displays That Use Records	18-16
Returning Control to Your Program after Pressing the Help Key	18-20
Returning Control to Your Program after Showing the Help Display	18-20
Returning Control to Your Program without Showing the Help Display	18-21
Chapter 19. Making Online Help Accessible for Your Panel Group	19-1
Definitions and Explanations	19-1
Help in a List Area	19-3
Coding Help	19-4
Help in a Menu Area	19-4
Coding Help	19-5
Help in a Data Area	19-6
Coding Help	19-8
Help in a Menu Bar Area	19-11
Coding Help	19-12
Help in a Function Key Area	19-13
Coding Help	19-14
Chapter 20. Defining Online Help Information	20-1
Defining Online Help Information in a Panel Group	20-1
Entering the UIM Source for a Panel Group for Help	20-1
Creating and Deleting Panel Groups	20-14
Assigning Panel Groups as Help for Commands	20-15
Using Panel Groups in a Search Index	20-15
Copying QUSRTOOL Examples That Define Help in a Panel Group	20-17
Defining Online Information in a Document	20-17
Creating a Document for Help	20-17
Viewing the Document without Pressing the Help Key	20-18
Defining Online Help Information in a DDS Record	20-18

Part 5. Guidelines for IBM AS/400-Style Displays

Chapter 21. Designing IBM AS/400-Style Displays	21-1
Using the Displays Example in the QUSRTOOL Library	21-1
Recognizing the Example Objects	21-1
Installing the Example Objects	21-3
Viewing the Sample Displays, Command, and Online Help Information	21-3
Copying the Source for the Example Objects for Your Own Use	21-6
Defining Special Functions and Attributes for All Displays	21-7
Designing the Single-Choice Menu Display	21-7
Title	21-8
Instruction Line	21-8
Menu Options	21-8
Menu Selection Entry Field	21-9
Function Keys	21-9
Online Help Information	21-9
General Menu Display Operation	21-9
Designing the Entry Display	21-10
Title	21-10
Instruction Line	21-11
Prompt Area	21-11
Function Keys	21-16
Online Help Information	21-16

General Entry Display Operation	21-16
Designing the Information Display	21-17
Title	21-18
Location Information	21-18
Prompt Area 1	21-18
Prompt Area 2	21-19
Instruction Line	21-19
Function Keys	21-19
Online Help Information	21-19
General Information Display Operation	21-20
Designing the List Display	21-20
Title	21-20
Prompt Area	21-21
Instruction Line	21-21
Options Line	21-21
Column Headings	21-22
Extended Action Entry	21-23
List Fields	21-23
Paging Location Information	21-23
Function Keys	21-24
Online Help Information	21-24
General List Display Operation	21-24
Defining the Function Key Area for All Displays	21-32
Optional Command Line and Identifier Field	21-32
Common Key Assignments	21-36
Defining Help Information for All Displays	21-41
Help for the Menu Display	21-41
Help for the Entry Display	21-42
Help for the Information Display	21-43
Help for the List Display	21-44
Defining and Presenting Messages	21-46
Designing Common User Access (CUA) Entry Level Models	21-47
Entry Dialog Actions	21-48
Single-Choice Selection (Menu)	21-49
Entry Display	21-50
Information Display	21-52
List Display	21-52
Help Information	21-54

Part 6. Appendixes

Appendix A. UIM Panel Group Definition Language	A-1
Panel Group Organization	A-4
Name Syntax	A-4
Symbols	A-5
Comments	A-6
Imbeds	A-6
DBCS Graphic Literals	A-6
Hexadecimal Literals	A-6
APPFMT (Application Formatted Area)	A-8
Required Attributes	A-8
Optional Attribute	A-8
Application Formatted Data	A-9

Example: Application Formatted Area	A-9
BOTINST (Bottom Instruction)	A-10
Optional Attribute	A-10
Optional Text	A-10
CHECK (Validity Checking)	A-11
Required Attribute	A-11
Optional Attributes	A-11
Example: Validity Checking	A-12
CIT (Title Citation)	A-13
Optional Text	A-13
Example: Title Citations	A-13
CLASS (Class Definition)	A-14
Required Attributes	A-14
Optional Attributes	A-17
Example: Class Definitions	A-22
Display Forms of Numeric Values	A-22
Display Forms of Character, Date, and Time Values	A-23
CMDLINE (Command Line)	A-24
Required Attribute	A-24
Optional Attribute	A-24
Optional Text	A-24
COND (Condition Definition)	A-25
Required Attributes	A-25
Optional Attribute	A-26
Example: Conditioning an Option	A-27
COPYR (Copyright)	A-28
Required Text	A-28
DATA (Data Presentation Area)	A-29
Required Attribute	A-30
Optional Attributes	A-30
Optional Text	A-31
Print Formatting Considerations	A-31
Example 1: Data Entry Panel	A-32
Example 2: Two-Column Format in a Data Entry Panel	A-32
Example 3: Two Presentation Areas for Data Items	A-33
Example 4: Data Presentation Area with a Menu Area	A-34
Example 5: Data Entry Panel with a Nested Data Group	A-34
DATAC (Data Item Choices)	A-36
Optional Attribute	A-36
Optional Text	A-36
DATACOL (Data Column)	A-37
Required Attribute	A-37
Optional Text	A-37
DATAGRP (Data Group)	A-38
Optional Attributes	A-38
Optional Text	A-39
DATAI (Data Item)	A-40
Required Attributes	A-40
Optional Attributes	A-41
Optional Text	A-43
DATAIX (Data Item Extender)	A-45
Required Attributes	A-45
Optional Attributes	A-46
DATASLT (Data Selection Field)	A-49

Required Attributes	A-49
Optional Attributes	A-49
Optional Text	A-50
Example 1: Data Entry Panel	A-51
Example 2: Multiple-Selection Field	A-51
DATASLTC (Data Selection Field Choice)	A-53
Optional Attributes	A-53
Optional Text	A-54
DL (Definition List)	A-55
Optional Attribute	A-55
Required Tags	A-55
Optional Tags	A-56
Example 1: Definition List	A-56
Example 2: Compact Definition List	A-56
FIG (Figure)	A-57
Optional Attribute	A-57
Optional Tag	A-57
Example: Sample Figure	A-57
HELP (Help Module)	A-58
Required Attribute	A-58
Optional Attributes	A-58
Optional Text	A-59
Example: Help Panel Definition	A-60
HP0 through HP9 (Highlighted Phrase)	A-61
Optional Text	A-61
H1 through H4 (Heading)	A-63
Required Text	A-63
Example: Heading Tags	A-63
IMHELP (Imbed Help)	A-64
Required Attribute	A-64
Example: Imbedded Help	A-64
IMPORT (Import)	A-65
Required Attributes	A-65
Optional Attributes	A-65
INFO (Information Area)	A-66
Required Attribute	A-66
Optional Attributes	A-66
Optional Text	A-66
Print Formatting Considerations	A-67
ISCH (Index Search)	A-68
Required Attribute	A-68
Required Text	A-68
Example: Index Search	A-68
ISCHSUBT (Index Search Subtopic)	A-69
Required Attribute	A-69
Example: Index Search Hierarchy	A-69
ISCHSYN (Index Search Synonym)	A-70
Required Attribute	A-70
Required Text	A-70
Example: Index Search Synonyms	A-70
KEYI (Key List Item)	A-72
Required Attributes	A-72
Optional Attributes	A-73
Optional Text	A-73

Example: Key Definitions	A-73
KEYL (Key List)	A-74
Required Attribute	A-74
Optional Attribute	A-74
Example: Key List	A-74
LINES (Unformatted Lines)	A-75
Optional Text	A-75
Example: Unformatted Lines	A-75
LINK (Hypertext Link Definition)	A-76
Required Attribute	A-76
Optional Attributes	A-76
Conditional Expressions	A-77
Bidirectional Considerations	A-78
Example: Hypertext Link	A-78
LIST (List Area)	A-80
Required Attributes	A-81
Optional Attributes	A-81
Optional Text	A-83
Print Formatting Considerations	A-84
Example 1: List Area	A-84
Example 2: List Area with Three Layout Columns	A-85
Example 3: List Area with List Column Groups	A-85
Example 4: Dynamic List Column Heading Formatting	A-86
LISTACT (List Action)	A-88
Required Attributes	A-88
Optional Attributes	A-89
Optional Text	A-92
Confirmation Panel Requirements	A-92
Confirmation Panel Conventions	A-92
Example: List Actions	A-93
LISTCOL (List Column)	A-94
Required Attributes	A-94
Optional Attributes	A-95
Optional Text	A-96
Formatting Considerations	A-97
LISTDEF (List Definition)	A-98
Required Attributes	A-98
Optional Attributes	A-98
LISTGRP (List Column Group)	A-101
Required Attributes	A-101
Optional Attribute	A-101
Optional Text	A-101
LISTVIEW (List View)	A-103
Required Attribute	A-103
Optional Attribute	A-103
LP (List Part)	A-105
Example: List Part	A-105
MBAR (Menu Bar)	A-106
Required Attribute	A-106
Optional Attributes	A-106
Example: Menu Bar	A-106
MBARC (Menu Bar Choice)	A-108
Required Attributes	A-108
Required Text	A-108

MENU (Menu Area)	A-109
Required Attribute	A-109
Optional Attribute	A-109
Optional Text	A-110
Example 1: Simple Menu Area	A-110
Example 2: Menu Area with Groups	A-110
MENUGRP (Menu Group)	A-112
Optional Attribute	A-112
Optional Text	A-112
MENUI (Menu Item)	A-113
Required Attributes	A-113
Optional Attributes	A-113
Optional Text	A-114
NT (Note)	A-115
Optional Text	A-115
Example: Using a Note	A-115
OL (Ordered List)	A-116
Optional Attribute	A-116
Required Tag	A-117
Example: Ordered List	A-117
OPTLINE (Option Line)	A-118
Optional Attribute	A-118
Optional Text	A-118
P (Paragraph)	A-119
Optional Text	A-119
Example: Paragraph Tag	A-119
PANEL (Display Panel)	A-120
Required Attributes	A-120
Optional Attributes	A-121
Optional Text	A-124
Example: Panel Definition	A-124
PARML (Parameter List)	A-126
Required Tags	A-126
Example: Parameter List	A-127
PC (Paragraph Continuation)	A-128
Example: Paragraph Continuation	A-128
PDACCEL (Pull-Down Accelerator)	A-129
Required Text	A-129
PDFLD (Pull-Down Field)	A-130
Optional Attribute	A-130
PDFLDC (Pull-Down Field Choice)	A-131
Required Attributes	A-131
Optional Attributes	A-131
Optional Text	A-133
Confirmation Panel Requirements	A-133
Confirmation Panel Conventions	A-133
PK (Programming Keyword)	A-135
Optional Attribute	A-135
Required Text	A-135
PNLGRP (Panel Group)	A-136
Optional Attributes	A-136
PRTHEAD (Print Head Panel)	A-139
Required Attribute	A-139
Optional Attributes	A-139

Optional Text	A-140
Layout of the Title Lines	A-140
Example: Print Title Line	A-142
PRTPNL (Print Panel)	A-143
Required Attribute	A-143
Optional Attributes	A-143
Optional Text	A-143
PRTRAIL (Print Trailer Message)	A-145
Required Text	A-145
Example: Trailer Message	A-145
PV (Programming Variable)	A-146
Required Text	A-146
RT (Reverse Text)	A-147
Example 1: Left-to-Right Formatting on a Right-to-Left Panel	A-147
Example 2: Left-to-Right Formatting on a Left-to-Right Panel	A-148
SL (Simple List)	A-149
Optional Attribute	A-149
Required Tag	A-149
Example: Simple Lists	A-150
TI (Translation List Item)	A-151
Optional Attribute	A-151
Optional Text	A-151
TL (Translation List)	A-152
Optional Attributes	A-152
Examples: Translation List	A-152
TOPINST (Top Instruction)	A-154
Optional Attribute	A-154
Optional Text	A-154
TT (Truth Table)	A-155
Required Attributes	A-155
Example: Truth Table	A-155
TTROW (Truth Table Row)	A-156
Required Attribute	A-156
UL (Unordered List)	A-157
Optional Attribute	A-157
Required Tag	A-157
Example: Unordered Lists	A-158
VAR (Variable Definition)	A-159
Required Attribute	A-159
Optional Attributes	A-159
Dialog Variables Defined by UIM	A-159
VARRCD (Variable Record Definition)	A-162
Required Attributes	A-162
Optional Attributes	A-162
XH1 through XH4 (Extended Help Headings)	A-163
Required Text	A-163
Formatting Rules	A-163
Example: Sample Headings	A-163
XMP (Example)	A-164
Example: Formatting an Example	A-164
 Appendix B. UIM Dialog Commands	 B-1
The VARUPD Attribute	B-4
ACTIONS (Menu Bar Cursor Action)	B-4

CALL (Call Program)	B-4
CANCEL	B-6
CHGVIEW (Change View)	B-6
CMD (System Command)	B-7
CMDLINE (Command Line)	B-7
DSPHELP (Display Help)	B-7
ENTER	B-8
EXIT (Exit Display)	B-8
EXTHELP (Extended Help)	B-9
HELP	B-9
HELPHELP	B-9
HELPIDX	B-9
HOME (Display Home Menu)	B-10
KEYSHELP	B-10
MENU	B-10
MOREKEYS (Display More Function Keys)	B-10
MOVETOP (Move to Top)	B-11
MSG (Display Message)	B-11
PAGEDOWN	B-12
PAGEUP	B-12
PRINT (Print Display)	B-12
PROMPT	B-12
PULLDOWN (Display Pull-Down Menu)	B-14
RETRIEVE (Retrieve Command String)	B-14
RETURN (Return Control to Application)	B-14
 Appendix C. Feedback Area Layouts for Display Files	 C-1
Open Feedback Area	C-1
Device Definition List	C-4
I/O Feedback Area	C-6
Common I/O Feedback Area	C-6
I/O Feedback Area for Display Files	C-9
Get Attributes	C-12
 Appendix D. Double-Byte Character Set Support for Displays	 D-1
Double-Byte Character Set Fundamentals	D-1
DBCS Code Scheme	D-1
Shift-Control Characters	D-3
Using Double-Byte Data	D-3
Double-Byte Character Size	D-4
Processing Double-Byte Characters	D-4
Basic Characters	D-4
Extended Characters	D-4
What Happens When Extended Characters Are Not Processed	D-4
Device File Support	D-5
What a DBCS File Is	D-5
When to Indicate a DBCS File	D-5
How to Indicate a DBCS File	D-5
Improperly Indicated DBCS Files	D-6
Display Support	D-6
Inserting Shift-Control Characters	D-6
Number of Displayed Extended Characters	D-6
Number of Input Fields on a Display	D-6
Effects of Displaying Double-Byte Data at Alphanumeric Work Stations	D-7

Effects of Displaying DBCS-Graphic Fields on Double-Byte Displays	D-7
Application Program Considerations	D-7
Designing Application Programs That Process Double-Byte Data	D-7
Changing Alphanumeric Application Programs to DBCS Application Programs	D-7
DBCS Font Tables	D-8
Finding Out if a DBCS Font Table Exists	D-8
Copying a DBCS Font Table onto Tape or Diskette	D-9
Copying a DBCS Font Table from Tape or Diskette	D-9
Deleting a DBCS Font Table	D-10
Starting the Character Generator Utility	D-10
Copying User-Defined Double-Byte Characters	D-10
DBCS Font Files	D-10
DBCS Sort Tables	D-11
Using DBCS Sort Tables on the System	D-12
Finding Out if a DBCS Sort Table Exists	D-12
Saving a DBCS Sort Table onto Tape or Diskette	D-12
Restoring a DBCS Sort Table from Tape or Diskette	D-12
Copying a Japanese DBCS Master Sort Table to a Data File	D-12
Copying a Japanese DBCS Master Sort Table from a Data File	D-13
Deleting a DBCS Sort Table	D-14
DBCS Conversion Dictionaries	D-14
System-Supplied Dictionary (for Japanese Use Only)	D-14
User-Created Dictionary	D-15
Commands for DBCS Conversion Dictionaries	D-15
Displaying and Printing the DBCS Conversion Dictionary	D-19
Deleting a DBCS Conversion Dictionary	D-19
DBCS Conversion (for Japanese Use Only)	D-19
Where You Can Use DBCS Conversion	D-20
How DBCS Conversion Works	D-20
Using DBCS Conversion	D-20
Performing DBCS Conversion	D-21
 Appendix E. Display File Return Codes	E-1
Major Code 00	E-1
Major Code 02	E-1
Major Code 03	E-2
Major Code 04	E-2
Major Codes 08–11	E-3
Major Code 34	E-3
Major Code 80	E-3
Major Code 81	E-6
Major Code 82	E-7
Major Code 83	E-10
 Appendix F. Edit Codes	F-1
OS/400 Edit Codes	F-1
Examples of Editing Using OS/400 Edit Codes	F-3
User-Defined Edit Codes	F-4
Using User-Defined Edit Codes	F-5
Example of a User-Defined Edit Code	F-5
 Appendix G. System/36-Compatible Display Data Management	G-1
Clearing Lines on the Display	G-1

Input Data for Display File Records	G-2
Input Data from the Work Station Controller	G-2
Self-Check	G-2
Return Input	G-3
Erase Input Fields	G-3
Display Attributes	G-3
Positioning the Cursor	G-4
Displaying Messages	G-4
Put Override	G-6
Handling Signed Numeric Data	G-7
Function Keys	G-7
Help Key Considerations	G-7
Using Command Keys to Exit Application Help	G-8
Cancel-Invite Operation	G-8
Retain Command and Function Keys	G-9
System/36 Functions Not Supported	G-9
Restricted DDS Keywords/Functions	G-10
 Bibliography	 H-1
 Index	 X-1

Figures

2-1.	Sample DDS Source for a Display File	2-7
2-2.	Record Formats in the Program and on the Display	2-8
2-3.	Sample DDS for Right-to-Left Display Processing	2-16
2-4.	Sample DDS for Program-to-System Fields	2-17
2-5.	Sample DDS for Two Display Sizes	2-20
2-6.	Sample DDS for Subfiles for Two Display Sizes	2-21
3-1.	Valid Placement of Records on a Screen When the CLRL Keyword Is Not Used	3-6
3-2.	Wrong Placement of Records on Screen When CLRL Keyword Not Used	3-8
3-3.	Replacing Record Formats	3-9
3-4.	Sample DDS Source Showing Use of the SLNO(*VAR) Keyword	3-12
3-5.	Sample DDS Source Showing Difference between CLRL and OVERLAY	3-15
3-6.	Sample DDS Source Showing Use of the PUTOVR Keyword	3-19
3-7.	Sample DDS Source Showing Efficient Use of PUTOVR Keyword	3-20
3-8.	Sample DDS Source Showing Another Use of PUTOVR Keyword	3-22
3-9.	Sample DDS Source Showing Use of the PUTRETAIN Keyword	3-24
3-10.	Sample DDS Source Showing Use of the PUTRETAIN Keyword	3-25
3-11.	Sample DDS Source Showing Use of the DSPMOD Keyword	3-27
3-12.	Sample DDS to Show Record Format Problems	3-47
4-1.	DDS Keyword Processing Order for Subfile Control	4-7
4-2.	Vertically Displayed Subfile	4-13
4-3.	Horizontally Displayed Subfile	4-13
4-4.	Horizontally and Vertically Displayed Subfiles Displayed at the Same Time	4-13
4-5.	Sample DDS Using DSPMOD with Subfiles	4-14
4-6.	Sample DDS Using SFLSIZ, SFLPAG, and ROLLUP Keywords	4-16
4-7.	Sample DDS for a Variable-Length Record	4-17
4-8.	Sample DDS Using the SFLNXTCHG Keyword	4-19
4-9.	Sample DDS for a Message Subfile	4-20
4-10.	Sample DDS Using the DSPATR(PC) Keyword	4-21
4-11.	Sample DDS Showing Customer Name Search Subfile	4-28
6-1.	Radio Buttons and Check Boxes	6-1
6-2.	Example of a Menu Bar	6-6
6-3.	DDS for a Menu Bar	6-7
6-4.	Menu Bar on a Graphical Display Station with Enhanced Interface	6-8
6-5.	Menu Bar on a Nongraphical Display Station with Underline Capability	6-8
6-6.	Menu Bar on a Nongraphical Display Station without Underline Capability	6-8
6-7.	Menu Bar on a Display Station without Enhanced Interface	6-8
6-8.	Selection Fields on a Graphical Display Station with Enhanced Interface	6-9
6-9.	DDS for Single-Choice and Multiple-Choice Selection Fields	6-10
6-10.	Selection Fields on a Graphical Display Station with Enhanced Interface	6-11
6-11.	Selection Fields on a Nongraphical Display Station	6-11
6-12.	Control Values for the CHCCTL Keyword	6-12
6-13.	DDS to Control the Availability of Choices	6-12
6-14.	Single-Choice Selection Field with an Unavailable Choice	6-12

6-15.	Example of a Pull-Down Menu	6-13
6-16.	DDS for a Pull-Down Menu	6-14
6-17.	Pull-Down Menu on a Graphical Display Station with Enhanced Interface	6-14
6-18.	Pull-Down Menu on a Nongraphical Display Station with Underline Capability	6-14
6-19.	Pull-Down Menu on a Nongraphical Display Station without Underline Capability	6-14
6-20.	Pull-Down Menu on a Display without Enhanced Interface	6-15
6-21.	DDS for Suppressing Selection Characters	6-15
6-22.	Suppressed Selection Characters on Graphical Display Station	6-15
6-23.	Suppressed Selection Characters on Nongraphical Display Station	6-16
6-24.	DDS for Accelerator Keys	6-17
6-25.	Accelerators in a Pull-Down Menu	6-17
6-26.	DDS for Menu-Bar Switch Key and Cancel Key	6-18
6-27.	Examples of Valid DDS for Mnemonics	6-19
6-28.	Examples of DDS Not Valid for Mnemonics	6-19
6-29.	DDS Using CHCAVAIL and CHCSLT for Menu-Bar Choices	6-21
6-30.	DDS Using CHCAVAIL and CHCUNAVAIL for Selection Fields	6-21
6-31.	DDS Using CHCAVAIL, CHCUNAVAIL, and CHCSLT for Selection Fields	6-22
6-32.	DDS Using MNUBARDSP on the Application Record	6-23
6-33.	DDS Using MNUBARDSP on the Menu-Bar Record	6-24
6-34.	DDS for Pull-Down Input (PULLINPUT) Parameter	6-26
6-35.	DDS for Return-Field Parameter	6-28
6-36.	DDS for Menu-Bar Choice Help	6-29
6-37.	DDS for Single-Selection Field Choice Help	6-30
6-38.	A Help List for a Menu Bar	6-31
6-39.	Help for a Named Field	6-32
6-40.	Help for a Constant Field	6-32
6-41.	Cursor Locations	6-32
6-42.	Continued-Entry Fields in Rectangular Arrangement	6-34
6-43.	DDS for Field-Level Cursor Progression	6-37
6-44.	DDS for Subfile-Level Cursor Progression	6-37
8-1.	Sample DDS Source for ERRSFL Keyword	8-5
8-2.	Sample DDS Source for SFLMSGID Keyword	8-6
9-1.	DDS Source for Sample Menu Called PERSMENU	9-8
9-2.	DDS Source for Program Menu Example	9-11
16-1.	An Example Menu	16-7
16-2.	Required UIM Tags for a Menu Panel	16-8
16-3.	Example List Panel	16-14
16-4.	Example of Alternate View of List	16-15
16-5.	Required UIM Tags for a List Panel	16-17
16-6.	Example Confirmation List Panel	16-28
16-7.	Example Data Presentation Panel	16-33
16-8.	Example Data Presentation Panel after Scrolling	16-34
16-9.	Required UIM Tags for a Data Presentation Panel	16-36
16-10.	Example Panel with a Menu Bar	16-51
16-11.	Required UIM Tags for a Panel with a Menu Bar	16-53
17-1.	Example of Job Exit Flag	17-22
17-2.	Example of Printout	17-32
18-1.	Sample H Specification in DDS Source	18-4
18-2.	Sample DDS Source Showing HLPPNLGRP	18-8
18-3.	Sample DDS Source Showing HLPPNLGRP and Option Indicators	18-9

18-4.	Sample DDS Source Showing HLPDOC	18-11
18-5.	Sample DDS Source Showing HLPDOC and Option Indicators	18-12
18-6.	Sample DDS Source Showing HLPRCD	18-13
18-7.	Sample DDS Source Showing HLPRCD and Option Indicators	18-14
18-8.	Sample DDS Source with HLPRCD	18-14
18-9.	Sample DDS Source to Show Secondary Help	18-18
18-10.	Sample DDS Source to Show HLPCMDKEY	18-20
18-11.	Sample DDS Source to Show HLPCMDKEY and Response Indicators	18-21
21-1.	Sample Menu in QUSRTOOL	21-3
21-2.	Sample Entry Display in QUSRTOOL	21-4
21-3.	Sample Information Display (Two Pages) in QUSRTOOL	21-5
21-4.	Sample List Display in QUSRTOOL	21-6
21-5.	Sample Application Menu	21-8
21-6.	Sample Entry Display	21-10
21-7.	Sample Information Display (Two Pages)	21-17
21-8.	Sample List Display	21-20
21-9.	Layout of Display with Location Information	21-24
21-10.	Create User Profile Entry Display	21-34
21-11.	Create Command Display with Additional Parameters Selected	21-34
21-12.	Second Display of Additional Parameters	21-35
21-13.	Work with Members Using PDM Entry Display	21-36
21-14.	Help Areas for Entry Displays	21-43
21-15.	Help Areas for Information Displays	21-44
21-16.	Help Areas for List Displays	21-45
21-17.	Example of an Application Menu	21-49
21-18.	Entry Display	21-51
21-19.	Example of an Information Display	21-52
21-20.	Example of a List Display	21-53
D-1.	IBM Host-System Code Scheme	D-2

Tables

1-1.	Names Used in Steps for Creating Sample Displays	1-1
1-2.	More Ways to Create Application Displays	1-6
1-3.	More Ways to Create Online Help Information	1-6
2-1.	Column positions for sample DDS	2-8
2-2.	DDS for Emphasizing Fields	2-17
2-3.	PRINT Keyword Results Using Print Key	2-21
3-1.	Display Stations Implicitly Acquired When Display Files Are Opened	3-2
3-2.	Information Available from the Get-Attributes Operation	3-4
3-3.	Results of SLNO(*VAR) Values	3-11
3-4.	Results from CLRL Example	3-16
3-5.	Keywords Ignored If Display Modes Are Changed	3-28
3-6.	Display File Operations Supported by the Operating System and the Equivalent High-Level Language Commands	3-49
4-1.	Optional Functions for Subfiles	4-4
4-2.	Subfile Operations Supported by the System and Equivalent HLL Commands	4-12
6-1.	Functions Supported by Hardware Configurations A, B, and C	6-2
6-2.	Functions Supported by Hardware Configurations D, E, and F	6-3
6-3.	Keywords Used to Define Colors and Display Attributes	6-20
6-4.	Values Returned in MNUCHOICE and PULLINPUT	6-27
6-5.	Actions Performed at Different Cursor Locations	6-33
7-1.	File Redirections	7-7
7-2.	File Redirection Combinations	7-7
8-1.	System Message Number Ranges	8-10
8-2.	Major Return Code Definitions	8-11
9-1.	Restrictions for Display File Menus	9-4
9-2.	Suggestions for Display File Menus	9-5
12-1.	Display File and ICF File Entry Field Attributes	12-1
13-1.	CHRID Values	13-5
17-1.	Initial Values of Dialog Variable	17-2
17-2.	Cursor-Sensitive Function Keys Assigned to Dialog Commands	17-26
18-1.	Different Ways to Define Online Help Information	18-2
18-2.	Characteristics of Different Methods of Online Help Information	18-2
18-3.	Help for Sample Display	18-5
18-4.	Other DDS Keywords for UIM Help	18-6
18-5.	Help for Sample Display Using Panel Groups	18-7
18-6.	Help for Sample Display Using HLPDOC	18-10
18-7.	Help for Sample Display Using HLPRCD	18-13
21-1.	Source Members for Displays Example in QUSRTOOL (Install, Create, and Delete)	21-2
21-2.	Source Members for Displays Example in QUSRTOOL (Sample Displays, Command, and Online Help Information)	21-2
21-3.	Objects Created When Creating Example Objects	21-3
21-4.	Required Functions and Attributes of All AS/400-Style Displays	21-7
21-5.	Optional Functions and Attributes of All AS/400-Style Displays	21-7
21-6.	Function Key Assignments	21-36
21-7.	Type of Help for Each Help Area—Menu Display	21-41
21-8.	DDS Considerations—Help on Menu Displays	21-42
21-9.	Type of Help for Each Help Area—Entry Display	21-42
21-10.	DDS Considerations—Help on Entry Displays	21-43

21-11.	Type of Help for Each Help Area—Information Display	21-43
21-12.	DDS Considerations—Help on Information Displays	21-44
21-13.	Type of Help for Each Help Area—List Display	21-45
21-14.	DDS Considerations—Help on List Displays	21-46
21-15.	CUA Entry Dialog Actions	21-48
A-1.	Tag Attributes That Can Be Continued	A-1
A-2.	Restrictions Associated With Mixed Panels	A-2
A-3.	Tags Allowed Between the CLASS and ECLASS Tag	A-14
A-4.	Attribute Summary for Each BASETYPE	A-16
A-5.	Tags Allowed Between the DATA and EDATA Tags	A-30
A-6.	Tag Allowed Between the DATASLT and EDATASLT Tags	A-49
A-7.	Tags Allowed Between the DL and EDL Tags	A-55
A-8.	Tag Allowed Between the KEYL and EKEYL Tags	A-74
A-9.	Tags Allowed Between the LIST and ELIST Tags	A-81
A-10.	NOCMD and NOEXT Attribute Interaction	A-91
A-11.	Emphasis Values	A-99
A-12.	Layout Values for Width=80	A-104
A-13.	Layout Values for WIDTH=132	A-104
A-14.	Layout Values for WIDTH=132	A-104
A-15.	Tag Allowed Between the MBAR and EMBAR Tags	A-106
A-16.	Tags Allowed Between the MBARC and EMBARC Tags	A-108
A-17.	Tags Allowed Between the MENU and EMENU Tags	A-109
A-18.	Tag Allowed Between the MENUGRP and EMENUGRP Tags	A-112
A-19.	Tags Allowed Between the NOTE and ENOTE Tags	A-115
A-20.	Tags Allowed Between the OL and EOL Tags	A-116
A-21.	Tags Allowed Between the PANEL and EPANEL Tag	A-120
A-22.	Tags Allowed Between the PARML and EPARML Tags	A-126
A-23.	Tags Allowed Between the PDFLD and EPDFLD Tags	A-130
A-24.	Valid Action Text for ACTION Values	A-131
A-25.	Tags Allowed Between the PNLGRP and EPNLGRP Tags	A-136
A-26.	Tags Allowed Between the PRTHEAD and EPRTHEAD Tags	A-139
A-27.	First Line of Heading with Print Width 132	A-141
A-28.	First Line of Heading with Print Width 80	A-141
A-29.	Second Line of Heading with Print Width 132	A-141
A-30.	Second Line of Heading with Print Width 80	A-142
A-31.	Tags Allowed Between the PRTPNL and EPRTPNL Tags	A-143
A-32.	Tags Allowed Between the SL and ESL Tags	A-149
A-33.	Tag Allowed Between the TL and ETL Tags	A-152
A-34.	Tag Allowed Between the TT and ETT Tags	A-155
A-35.	Tags Allowed Between the UL and EUL Tags	A-157
A-36.	Attributes of UIM-Defined Variables (Z-Variables)	A-161
B-1.	Summary of the Valid Uses of Dialog Commands	B-2
B-2.	Summary of the Effects of Dialog Commands	B-3
C-1.	Open Feedback Area	C-1
C-2.	Device Definition List	C-4
C-3.	Common I/O Feedback Area	C-6
C-4.	I/O Feedback Area for Display Files	C-9
C-5.	Get Attributes	C-12
D-1.	IBM Japanese Character Set	D-2
D-2.	IBM Korean Character Set	D-2
D-3.	IBM Simplified Chinese Character Set	D-2
D-4.	IBM Traditional Chinese Character Set	D-3
F-1.	Summary Chart for OS/400 Edit Codes	F-1
F-2.	Valid Edit Codes, Source Data, and Edited Output	F-3

F-3. IBM-Supplied Edit Descriptions F-4

G-1. Message Files for MSGID G-5

G-2. Message Files for MSGID G-5

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of the intellectual property rights of IBM may be used instead of the IBM product, program, or service. The evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, are the responsibility of the user.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Commercial Relations, IBM Corporation, Purchase, NY 10577, U.S.A.

This publication could contain technical inaccuracies or typographical errors.

This publication may refer to products that are announced but not currently available in your country. This publication may also refer to products that have not been announced in your country. IBM makes no commitment to make available any unannounced products referred to herein. The final decision to announce any product is based on IBM's business and technical judgment.

Changes or additions to the text are indicated by a vertical line (|) to the left of the change or addition.

Refer to the "Summary of Changes" on page xxxiii for a summary of changes made to the data description specifications (DDS) and the user interface manager (UIM) and how they are described in this publication.

This publication contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

This publication contains small programs that are furnished by IBM as simple examples to provide an illustration. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. All programs contained herein are provided to you "AS IS". THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE EXPRESSLY DISCLAIMED.

Programming Interface Information

This guide is intended to help the application programmer create and maintain displays for an application. This guide documents Product-Sensitive Programming Interface and Associated Guidance Information provided by the OS/400 licensed program.

Product-Sensitive programming interfaces allow the customer installation to perform tasks such as diagnosing, modifying, monitoring, repairing, tailoring, or tuning of this IBM software product. Use of such interfaces creates dependencies on the detailed design or implementation of the IBM software product. Product-Sensitive programming interfaces should be used only for these specialized purposes. Because of their dependencies on detailed design and implementation, it is to be expected that programs written to such interfaces may need to be changed in order to run with new product releases or versions, or as a result of service.

Trademarks and Service Marks

The following terms, denoted by an asterisk (*) in this publication, are trademarks of the IBM Corporation in the United States or other countries or both:

AFP	InfoWindow
AIX	OfficeVision
Application System/Entry	Operating System/400
Application System/400	OS/2
APPN	OS/400
AS/400	PS/2
C/400	RPG/400
COBOL/400	SAA
Common User Access	Systems Application Architecture
CUA	System/370
FORTTRAN/400	WindowTool
IBM	400
Information Assistant	

The following terms, denoted by a double asterisk (**), used in this publication, are trademarks of other companies as follows:

Microsoft Windows	Microsoft Corporation
RUMBA	Wall Data Incorporated

About This Guide

This guide contains information on:

- Using DDS to create and maintain displays for an application
- Creating and working with display files on the system
- Creating online help information
- Using UIM to define panels and dialogs for an application

Use this guide to program for application and help displays.

This guide does not describe all the DDS keywords or the configuration of display stations. You may need to refer to other IBM manuals for more specific information about a particular topic. The *Publications Guide*, GC41-9678, provides information on all the manuals in the AS/400 library.

For a list of related publications, see the "Bibliography."

Who Should Use This Guide

This guide should be used by application programmers who create or work with application and help displays. You should also have knowledge of the source entry utility (SEU) and data description specifications (DDS). You should have read *System Concepts*, GC41-9802 and *Application Development by Example*, SC41-9852.

This guide assumes that a device description already exists to describe your display station to the system.

Summary of Changes

Creating a Graphical Look with DDS

The graphical look is a change in what you see while you run DDS functions. Instead of dotted windows, you have crisp window borders. Instead of typing numbers in an option column to make a selection, you can use a mouse or mnemonics.

In addition to the fresher look, the enhanced function includes:

- Menu bars
- Pull-Down menus
- Single-choice selection fields
- Multiple-choice selection fields
- Continued-entry fields
- Edit Masks

For more information on the graphical look, see Chapter 5, "Defining Windows with Display Files" and Chapter 6, "Creating a Graphical Look for Displays."

Program-to-System Field Parameter on the DSPATR Keyword

A new program-to-system field parameter can be specified on the DSPATR keyword. The program uses this program-to-system field to set the display attribute for the field to which this DSPATR keyword applies.

For more information, see "Defining Choice Colors and Attributes" on page 6-19.

InfoSeeker Hierarchy

The ISCHSUBT tag lets you create an InfoSeeker hierarchy using subtopics.

For more information, see Chapter 20, "Defining Online Help Information."

Using Alternate Character Set and Code Page

The character identifier (CHRID) parameter on a display file is set by the CHRID parameter on the CRTDSPF, CHGDSPF, or OVRDSPF commands. The CHRID parameter on a panel group or menu is set by the CHRID parameter on the CRTPNLGRP or CRTMNU commands, respectively.

The CHRID parameter value of *JOBCCSID tags the display file, panel group, or menu with the coded character set identifier (CCSID) of the job. When *JOBCCSID is specified and the job CCSID is different than the display station CCSID, named and unnamed (constant) fields are translated to the CCSID of the display station. If *JOBCCSID is specified for display files, you no longer need to use the character identifier (CHRID) DDS keyword on fields you want to be translated. All fields are translated. Use the No CCSID (NOCCSID) DDS keyword on fields you do not want to be translated.

For more information, see "Specifying Character Translation for Fields" on page 13-2.

Right-to-Left Display Processing

The Display Right-to-Left (DSPRL) DDS keyword lets you specify that records in a display file be written in the right-to-left direction.

For more information, see “Specifying Right-to-Left Display Processing” on page 2-16.

Part 1. Building a Sample Display with Online Help Information

Chapter 1. Building a Sample Display with Online Help Information	1-1
--	------------

Chapter 1. Building a Sample Display with Online Help Information

This chapter outlines the steps you need to do to create a sample display with online help information on the Application System/400*. If you are not sure how to do one or more of the steps, see the additional information referred to in each step.

The Application Display: The sample display is created using a display file (also known as a display device file). A **display file** is an object, or named storage space, created by the user that contains the file description. The **file description** identifies the display station used and, optionally, the record formats used by the display station. **Record formats** describe the characteristics and arrangement of the fields on a display. Record formats are defined using **data description specifications (DDS)**, which describe data attributes outside the application program that processes the data.

The Online Help Information: The online help information for the sample display is defined using help panel groups. A **panel group** is an object, or named storage space, that contains text to be used as online help information by the user interface manager. The **user interface manager (UIM)** is a function of the operating system that provides online help information for displays, including help for part or all of a display, help for commands, the InfoSeeker function (selectable help topics), and hypertext (the capability to link different units of online help information).

The following table lists the sample names used in the steps:

Table 1-1. Names Used in Steps for Creating Sample Displays

Name	What It Is
SRCSAM	Sample source file
ADMSAM	Sample source member for application display
DSPSAM	Sample display file
HDMSAM	Sample source member for help display
PNLSAM	Sample panel group
LIBSAM	Sample library that contains source file SRCSAM, display file DSPSAM, and panel group PNLSAM

The steps show only one way to create a sample display with online help information. Other methods are discussed at the end of this chapter.

1. Create the source file SRCSAM using the Create Source Physical File (CRTSRCPF) command; create the library LIBSAM using the Create Library (CRTLIB) command.
2. Enter the Start Programming Development Manager (STRPDM) command to begin using the programming development manager (PDM). When the display appears, select option 3 (Work with members).

AS/400 Programming Development Manager (PDM)

Select one of the following:

1. Work with libraries
2. Work with objects
3. Work with members

9. Work with user-defined options

Selection or command

==> 3

F3=Exit

F4=Prompt

F9=Retrieve

F10=Command entry

F12=Cancel

F18=Change defaults

(C) COPYRIGHT IBM CORP. 1981, 1993.

Additional Information

The **programming development manager (PDM)** is the part of the AS/400* Application Development Tools licensed program that allows users to perform several operations (such as copy, delete, and rename) from lists of libraries, objects, and members.

Since the display file (which will be created in step 9) does not actually contain any data, the DDS source for a display file is entered in a source file. A **source file** is an object that is made up of one or more **source members**, which are the different sets of data that make up your DDS source.

More information about the programming development manager is available in the manuals *Application Development by Example* and *PDM User's Guide and Reference*.

3. When the Specify Members to Work With display appears, complete the file and library information and press the Enter key.

```

                                Specify Members to Work With

Type choices, press Enter.

File . . . . . SRCSAM      Name
Library . . . . . LIBSAM    *LIBL, *CURLIB, name

Member:
Name . . . . . *ALL          *ALL, name, *generic*
Type . . . . . *ALL          *ALL, *BLANK, type, *generic*


F3=Exit      F5=Refresh      F12=Cancel

```

4. The Work with Members Using PDM display appears.

```

                                Work with Members Using PDM

File . . . . . SRCSAM
Library . . . . LIBSAM          Position to . . . . .

Type options, press Enter.
2=Edit      3=Copy      4=Delete      5=Display      6=Print
7=Rename    8=Display description  9=Save      13=Change text

Opt Member   Type      Text

(No members match the subsetting criteria)


Parameters or command
===>
F3=Exit      F4=Prompt      F5=Refresh      F6=Create
F9=Retrieve  F10=Command entry  F23=More options  F24=More keys

```

Press F6 on this display to create a new member.

5. The Start Source Entry Utility display appears. Complete the information on this display and press the Enter key.

```

                                Start Source Entry Utility (STRSEU)

Type choices, press Enter.

Source file . . . . . > SRCSAM          Name, *PRV
Library . . . . . > LIBSAM             Name, *LIBL, *CURLIB, *PRV
Source member . . . . . ADMSAM        Name, *PRV, *SELECT
Source type . . . . . DSPF           Name, *SAME, BAS, BASP, C...
Text 'description' . . . . . DDS for sample display

                                Bottom
F3=Exit   F4=Prompt   F5=Refresh   F12=Cancel   F13=How to use this display
F24=More keys

```

Additional Information

The **source entry utility (SEU)** is a function of the AS/400 Application Development Tools licensed program that is used to create and change source members. More information about the source entry utility is available in the manuals *Application Development by Example* and *SEU User's Guide and Reference*.

6. Because you are creating a new member, the SEU Edit display appears with a screen of blank lines. The text on the last line of the display, *Member ADMSAM added to file SRCSAM* indicates that SEU added the new member to the file you specified.

```
Columns . . . :    1   71              Edit                  LIBSAM/SRCSAM
SEU==>                               ADMSA
FMT DP .....AAN01N02N03T.Name+++++RLen++TdPBLinPosFunctions+++++++++++++++++++
***** Beginning of data *****
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||||
|||
***** End of data *****
F3=Exit          F4=Prompt           F5=Refresh
F10=Top          F11=Bottom            F24=More keys
member ADMSAM added to file LIBSAM/SRCSAM.
```

7. On the SEU edit display, enter the DDS source statements for the new member. Since the instructions in this chapter allow you to provide online help

information for the sample display, make sure your DDS source includes the necessary DDS keywords to enable and access help.

Additional Information

SEU has many functions available to help you enter your DDS. More information about the functions of SEU is available in the *SEU User's Guide and Reference*.

For information about describing your display using DDS, see "Defining Display Fields and Functions in a Record Format" on page 2-7 in this guide. For more information about the DDS keywords needed for online help information, see Chapter 18, "Making Online Help Information Accessible for Your Display File."

8. When you are finished entering your DDS source, press F3 and complete the information on the Exit display. Press the Enter key.
9. To create the new display file, enter the Create Display File (CRTDSPF) command on any command line. Make sure you specify the source file and member that contains your DDS source:

```
CRTDSPF FILE(LIBSAM/DSPSAM) SRCFILE(LIBSAM/SRCSAM) SRCMBR(ADMSAM)
```

Press the Enter key.

Additional Information

For more information about creating display files, see "Creating a Display File and Description" on page 2-4.

10. To add online help information to the sample display, create a second source file member for the UIM source. You are not required to create the second source member in the same source file that you created your DDS source in; however, do not use the same source member for both the DDS and UIM source.

To create the second source file member, repeat steps 2 through 4. When the Start Source Entry Utility display appears again, continue with step 11.

11. Complete the information on the Start Source Entry Utility display by specifying the following:

For this prompt...	Enter this...
Source member	HDMSAM
Source type	PNLGRP
Text description	UIM help for sample display

12. On the SEU edit display, enter the UIM source statements for the new member.

Additional Information

For information about defining your online help information using UIM, see "Defining Online Help Information in a Panel Group" on page 20-1.

13. When you are finished entering your UIM source, press F3 and complete the information on the Exit display. Press the Enter key.
14. Enter the Create Panel Group (CRTPNLGRP) command on any command line:
CRTPNLGRP PNLGRP(LIBSAM/PNLSAM) SRCFILE(LIBSAM/SRCSAM) SRCMBR(HDMSAM)

Press the Enter key.

Additional Information

For more information about panel groups, see “Creating and Deleting Panel Groups” on page 20-14.

Although one library was used in the previous steps, you are not required to create the different objects for your displays in the same library.

Other ways of creating your own application displays on the AS/400 system follow:

Table 1-2. More Ways to Create Application Displays

Method	Description	Where to Find More Information
Screen design aid (SDA)	A function of the Application Development Tools/400 licensed program that helps you design, create, and maintain displays and menus. SDA allows you to design your displays as you want them to look and then the system creates the DDS source and a display file for you.	<i>SDA User's Guide and Reference</i>
QUSRTOOL	A library, which is optionally installable on your system, that provides you access to examples of various tools and programming techniques that may help you with application development and management of your system. The display example in QUSRTOOL provides four sample displays with online help information. You can copy the source for these displays into a library of your choosing and then tailor them for your own use.	“Using the Displays Example in the QUSRTOOL Library” on page 21-1
UIM panel groups	A part of the system that allows you to define panels and dialogs for your application. The UIM controls the panel's appearance and assures consistency with panels developed by IBM.	Chapter 16, “Introduction to the User Interface Manager” on page 16-1

Other ways of creating online help information for your displays follow:

Table 1-3. More Ways to Create Online Help Information

Method	Description	Where to Find More Information
Help documents	Objects for online help information that are created using AS/400 OfficeVision/400*, which is the IBM* licensed program that provides many office functions, such as word processing. This can be accessed from display files and not the UIM application panels.	“Defining Online Information in a Document” on page 20-17 and “Specifying Documents in Your Display File” on page 18-9
Help records	DDS keywords that allow you to create your online help information in the same or a different member as the DDS source for your application display. This can be accessed from display files and not the UIM application panels.	“Defining Online Help Information in a DDS Record” on page 20-18 and “Specifying Records in Your Display File” on page 18-12

To compare and contrast the different ways to create online help information, see “Choosing between Panel Groups, Documents, and Records for Help” on page 18-2.

Part 2. Programming Application Displays Using Display Files

Chapter 2. Defining Your Display in a Display File	2-1
Establishing a Display File	2-1
Determining File Descriptions	2-2
Field-Level Descriptions	2-2
Record-Level Descriptions	2-3
File-Level Descriptions	2-3
Deciding Whether to Describe Data Inside or Outside Your Program	2-3
Externally Described Data	2-3
Program-Described Data	2-4
Creating a Display File and Description	2-4
Changing the File Description	2-5
Detecting File Description Changes	2-6
Defining Display Fields and Functions in a Record Format	2-7
Understanding the Field Attribute Characters	2-8
Understanding How Record Format Fields Can Be Used	2-9
Defining Function Keys	2-11
Defining Command Attention (CAnn) and Command Function (CFnn) Keys	2-12
Specifying Alternative Keys	2-13
Passing Information via Indicators	2-14
Removing Option and Response Indicators from the Record Area	2-14
Enabling Different Response Indicators Simultaneously	2-15
Setting an Indicator Off	2-15
Inserting Constant Field Text from a Message Description	2-15
Allowing for Right-to-Left Cursor Movement	2-16
Specifying Right-to-Left Display Processing	2-16
Emphasizing Fields	2-17
Adding Color	2-18
Editing Output Fields	2-18
Defining Your Own Edit Codes	2-19
Specifying Valid Screen Sizes	2-20
Enabling Your Display to Be Printed	2-21
Defining Windows	2-22
Using Program-Described Data	2-22
Defining Input-Only Files	2-23
Defining Output-Only Files	2-23
Defining Input and Output Files	2-24
 Chapter 3. Working with Display Files in an Application	 3-1
Understanding How the System Allocates Resources	3-1
Opening Display Files	3-2
Acquiring a Display Station for I/O Operations	3-2
Obtaining Information about Display Files and Display Stations	3-3
Obtaining Information about Open and I/O Operations	3-3
Obtaining Attribute Information about Display Stations	3-4
Sending and Receiving Data	3-4
Determining Which Record Formats Are Active on a Display	3-5
Writing Output to the Display	3-5
Placing Records on the Display	3-5
Understanding Which Records Do Not Occupy Space on the Display	3-8

Changing Record Formats on a Display	3-8
Deciding the Order of Record Formats Written to the Display	3-9
Overlaying and Erasing Record Formats on a Display	3-10
Starting Your Record Format on a Specific Line	3-11
Clearing a Specified Number of Lines	3-13
Rolling Data between Two Lines on a Display	3-16
Overriding the Attributes or the Content of a Field	3-18
Erasing All Unprotected Input and Output/Input Fields on the Display	3-23
Resetting Modified Data Tags Associated with Records on the Display	3-23
Keeping a Record or Field on a Display	3-23
Deferring the Write Operation Until a Read Request is Made	3-26
Specifying Default Values for Fields	3-26
Indicating Which Mode to Display Records	3-27
Positioning the Cursor after an Output Operation	3-28
Returning the Cursor Position to an Application	3-29
Returning the Cursor Position Within a Subfile to an Application	3-29
Returning the Mode of a Subfile to an Application	3-29
Initializing Output/Input Fields	3-29
Inviting Input to the Display	3-30
Reading Invited Input from the Display	3-31
Understanding the Read-From-Invited-Devices	3-32
Reading Input from the Display	3-33
Unlocking the Keyboard while the Program Is Processing Data	3-35
Keeping Input Data	3-36
Setting an Indicator When Data Is Changed	3-36
Initializing Records and Unlocking the Keyboard—Diagram	3-36
Specifying Validity-Checking Functions	3-37
Understanding the Limitations on the Number of Input-Capable Fields	3-39
Handling Negative Numeric Input Data	3-39
Understanding How the System Reads Input from the Display	3-40
Writing Output and Reading Input at the Same Time	3-40
Canceling Input That Was Not Waited For	3-41
Locking the Keyboard and Positioning the Cursor During I/O Operations	3-41
Saving Previously Displayed Information	3-42
Understanding the Effects of I/O Operations on Command Keys	3-45
Avoiding Record Format Problems on the 5250 Display Station	3-45
Releasing an Acquired Display Station from I/O Operations	3-49
Closing Display Files	3-49
Mapping Display Operations to High-Level Language Operations	3-49
Sharing Display Files in the Same Job	3-50
Understanding the Open Operation for Files Shared in a Job	3-51
Understanding the Input/Output Operation for Files Shared in a Job	3-51
Understanding the Close Operation for Files Shared in a Job	3-52
 Chapter 4. Displaying Groups of Records Using Subfiles	 4-1
Recognizing Subfile Uses	4-1
Describing Subfiles in Your DDS Source	4-3
Using a Subfile in a Program	4-7
Requesting I/O Operations for a Subfile	4-9
Requesting I/O Operations for a Subfile Record Format	4-9
Adding a Record at a Specified Location in a Subfile	4-9
Updating an Active Record in the Subfile	4-10
Reading an Active Record at a Specified Location in the Subfile	4-10
Reading the Next Changed Record in a Subfile	4-10

Requesting I/O Operations for a Subfile Control Record Format	4-11
Displaying Subfile Records	4-11
Placing Subfile Records on the Display for Processing	4-12
Displaying and Processing Subfile Records at the Same Time	4-12
Recognizing Subfile I/O Requests in High-Level Languages	4-12
Controlling the Appearance of Subfiles	4-12
Displaying Horizontal Subfiles with Display Modes	4-14
Specifying Subfile Size Equal to Page Size	4-15
Specifying Subfile Size Not Equal to Page Size	4-17
Checking Validity on Subfile Data	4-18
Displaying Error Messages from Subfiles	4-19
Positioning the Cursor on the Displayed Subfile	4-20
Positioning the Cursor Initially	4-20
Positioning the Cursor When a Roll Key Is Used	4-21
Positioning the Cursor When a Fold or Truncate Key Is Used	4-24
Positioning the Cursor and Rolling When Two or More Records Are Displayed	4-24
Understanding Subfile DDS and Program Logic—Example	4-28
 Chapter 5. Defining Windows with Display Files	 5-1
Window Terminology	5-2
DDS Window Keywords	5-2
Window Representation and Hardware Configuration	5-2
Creating Windows	5-3
Window Definition Records	5-3
Window Reference Records	5-3
Window Size and Location	5-4
Cursor Position	5-5
Error Messages	5-5
Subfiles	5-6
DDS Help Records	5-6
Defining Window Borders	5-7
Border Defaults	5-7
Multiple Border Definitions	5-7
UIM Help Window Borders	5-8
Reading Data from Windows	5-9
Changing Window Borders and Contents	5-9
Moving and Duplicating Windows	5-9
Making Two Windows Seem Active at Once	5-9
Making One Window in a Series Stand Out	5-10
Removing Windows	5-11
Removing All Windows	5-11
Removing More Recent Windows	5-11
Improving Application Performance	5-11
System Save and Restore Operations	5-12
Response Time	5-12
Bypassing System Save and Restore Operations	5-12
USRRSTDSP Keyword Processing and Interactions	5-13
Programming Examples	5-14
Using Basic Window Functions	5-14
DDS Full-Screen Display and Window Definitions	5-14
RPG Display Program	5-15
Step 1: Display Initial Display	5-16
Step 2: Display Window 1	5-17

Step 3: Display Window 2	5-17
Step 4: Restore Window 1	5-18
Step 5: Display Initial Display	5-18
Defining Windows in a Separate Display File	5-19
DDS Full-Screen Display and Window Definitions	5-19
RPG Program Source	5-20
RPG Program Source for WINPGM	5-20
Step 1: Display Initial Display	5-20
Step 2: Display a Window	5-21
Step 3: Return to the Initial Display	5-22
 Chapter 6. Creating a Graphical Look for Displays	 6-1
Factors Affecting the Graphical Look	6-1
Hardware Configuration	6-2
Enhanced Display Parameter	6-3
DDS Keywords	6-4
Creating Menu Bars	6-6
Defining the Menu-Bar Choices	6-6
Defining the Menu-Bar Separator	6-6
Creating Selection Fields	6-9
Single-Choice Selection Field	6-9
Multiple-Choice Selection Field	6-10
Controlling the Availability of Choices	6-11
Creating Pull-Down Menus Using Single-Choice Selection Fields	6-13
Controlling the Selection Characters	6-15
Defining Accelerator Keys	6-16
Defining a Menu-Bar Switch Key	6-17
Defining a Cancel Key	6-18
Defining Mnemonics	6-19
Defining Choice Colors and Attributes	6-19
How the Menu Bar Interacts with the Application	6-22
Defining the MNUBARDSP Keyword on the Application Record	6-22
Defining the MNUBARDSP Keyword on the Menu-Bar Record	6-24
Receiving Input from the Pull-Down Menus	6-25
Receiving Input from Pull-Down Menus Using the Pull-Down Input Parameter	6-26
Removing a Pull-Down Menu after Receiving Input	6-27
Updating a Pull-Down Menu before Displaying	6-28
Defining Application Help	6-29
Defining Choice-Level Help	6-29
Defining Help for a Field	6-31
Key Interaction for Menu Bars and Pull-Down Menus	6-32
Creating Continued-Entry Fields	6-33
Forward Field-Exit Processing	6-36
Backward Field-Exit Processing	6-36
Defining Cursor Progression for Entry Fields	6-36
Defining Attributes for Entry Fields	6-37
Protecting Entry Fields Using Edit Masks	6-38
Cursor Movement	6-38
Pressing the Tab Key	6-39
Pressing the Cursor Keys	6-39
Simple Hotspots	6-40
Command Key Emulation	6-40
Page Up and Page Down Key Emulation	6-41

Programming Examples	6-41
Using the MNUBARDSP Keyword on the Application Record	6-41
Description	6-42
Using the MNUBARDSP Keyword on the Menu-Bar Record	6-43
Description	6-45
How the Displays Look	6-45
Chapter 7. Overriding Display Files and Display File Attributes	7-1
Determining Whether or Not to Use Overrides	7-1
Overriding File Attributes in HLL Programs	7-1
Overriding File Names in HLL Programs	7-3
Overriding Both File Names and Attributes in HLL Programs	7-3
Applying Overrides When Compiling a Program	7-4
Deleting Overrides	7-5
Displaying Overrides	7-6
Using File Redirection to Override File Names and Libraries or File Types	7-6
Overriding Files with the Same File Types	7-6
Overriding Files with Different File Types	7-6
Recognizing Commands That Ignore or Restrict Overrides	7-9
Chapter 8. Handling Messages and Errors for Display Files	8-1
Creating and Displaying Your Own Messages	8-1
Displaying a Message on the Message Line	8-2
Displaying a Message on the Message Line When a Subfile Control Record is Written	8-2
Displaying a Message on the Message Line Using a Message Field	8-3
Priorities for Displaying Messages on a Message Line	8-3
Displaying Messages in a Field on the Display	8-3
Displaying Messages on a Program Message Queue	8-4
Displaying Error Messages through a Subfile	8-4
Sounding an Alarm for Messages	8-7
Automatically Handling Permanent I/O Errors on Display Stations	8-7
Analyzing Error Messages Sent from the System	8-8
Understanding Messages and Message Monitors	8-9
Understanding Major/Minor Return Codes	8-10
Recovering from Errors	8-11
Normal Completion	8-11
Completion with Exceptions	8-12
Permanent System or File Error	8-13
Permanent Device or Session Error on I/O Operation	8-13
Device or Session Error on Open or Acquire Operation	8-14
Recoverable Device or Session Errors on I/O Operation	8-14
Chapter 9. Creating and Accessing Menus Using Display Files	9-1
Running System and User-Defined Menus	9-1
Returning to a Menu after Running the GO command	9-1
Determining the Previous Menu	9-1
Using the Cancel and Exit Keys on Menus	9-2
Choosing the Menu That Is Shown at Sign-On Time	9-3
Defining Your Own Display File Menus	9-4
Understanding DDS and Display File Considerations for Menus	9-4
Describing Menu Actions in a Message File	9-5
Naming Help Formats for Menus	9-6
Building a Display File Menu	9-7

Describing the Menu and Menu Help Information	9-7
Creating the Display File	9-9
Creating the Message File	9-9
Adding Messages to the Message File	9-9
Creating the Menu Object	9-9
Running the Menu	9-10
Defining Your Own Program Menus	9-10
Passing Parameters for Program Menus	9-10
Building a Program Menu	9-11
Describing the Menu	9-11
Creating the Display File	9-12
Entering the Source and Creating a CL Program	9-12
Creating the Menu	9-13
Running the Menu	9-13
Exiting from a Program Menu without Returning to the Previous Menu	9-13
Program 1	9-14
Program 2	9-15
Avoiding Menu Name Conflict	9-15
Naming Your Menus	9-15
Placing Your Menu in a Higher Library in the Library List	9-16
Specifying the Library That Contains the Menu	9-16
Using the Generic Menu Specification	9-16
Changing the Command Default after Duplicating a Command	9-16
Displaying Menu Attributes	9-16
Changing Menu Attributes	9-16
Deleting Menus	9-17
 Chapter 10. Using User-Defined Data Streams	 10-1
Understanding Display Station Differences	10-1
Understanding User-Defined Data Stream Limitations	10-2
 Chapter 11. Passing Data between Programs	 11-1
Passing Data in the Same Routing Step in a Job	11-1
Passing Data between Routing Steps in a Job	11-3
 Chapter 12. Waiting for Input from a Display File, an ICF File, and a Data Queue	 12-1
 Chapter 13. Using Alternative Character Sets and Code Pages	 13-1
Specifying Character Translation for Fields	13-2
Determining the Character Identifier (CHRID) Value for Your Display	13-4
 Chapter 14. Improving System Performance with Displays	 14-1
Deferring the Write Operation for a Display File	14-1
Designating the Primary Screen Size for a Display File	14-1
Writing Only One Page of Subfile Records at a Time	14-1
Sharing an Open Data Path (ODP) for the Same Job	14-2
Sending Records with Input Fields to the Display in Order	14-2
Overlapping and Not Deleting Repeatedly Sent Records	14-2
Restoring the Display	14-3
Defining Command Attention Keys Rather Than Command Function Keys	14-3
Using the Invite Operation	14-3
Using Windows	14-4

Chapter 2. Defining Your Display in a Display File

A display file defines the format of the information to be presented on a display station, and how that information is processed by the system on its way to and from the display station. Data description specifications (DDS) describe the data referred to by a display file.


This chapter tells you about display files, including how to create them and how to provide DDS source for them to describe your display.

Establishing a Display File

A display file is an object on the system. An **object** is a named storage space that consists of a set of characteristics that describe itself and, in the case of a display file, the data. Like other objects on the system, display files have the following characteristics:

- A display file is named and placed in a library when it is created. The file name and library name allow you to refer to the display file in your applications.
- Once a display file is created, it can be changed, secured, saved, restored, or deleted.

Before an application program can work with a display station, a display file must be opened to allow data to flow between the program and the display station.



A **device description**, which is a system object that describes the display station to the system, must also exist for the display station. A device description contains information such as device address, device type, model number, and features. Device descriptions are usually created by system personnel or, for locally attached devices, can be created during the automatic configuration of the system.

A program may work with more than one display station at a time by doing one of the following:

- Opening more than one display file
- Opening a display file that allows more than one display station to be attached to an open file

Since a display file does not have a set of data uniquely associated with it, the relationship between the data and the display file is established when the display file is opened and ends when the display file is closed.

Determining File Descriptions

The **file description**, which is created at the same time the display file is created, describes the characteristics of the display file and determines how the display file does the following:

- Controls the display station
- Formats output data from the program for presentation at the display station
- Formats input data from the display station for presentation to the program

A file description determines how a program is able to use the file. If a program attempts to perform an operation that is inconsistent with the display file description, the system does not allow the operation.

The file description is created and deleted at the same time as the display file it describes. Some parts of a file description may be changed, either permanently with the Change Display File (CHGDSPF) command or temporarily with the Override with Display File (OVRDSPF) command.

A file description describes data at three different levels:

- Field level
- Record level
- File level

The following sections describe these levels.

Field-Level Descriptions

A **field** is the smallest unit of data that is recognized and handled by the data management support of the system. A **field-level description** allows you to give the system detailed characteristics of a field, such as:

- Where on the screen the field is to appear
- What type of data is valid for the field
- Whether the field should be highlighted in some way
- How it will be presented from the program to the system on output and from the system to the program on input.
- Where each field is relative to the start of a record
- What the characteristics of each field will be while in the system
- Where the data for each field should be acquired from for output
- Where and how input from the display station should be placed so the program can use it
- Whether the field is an input-capable field or output-capable field only

Only field-level descriptions can determine that valid data is specified for individual fields on a display.

Record-Level Descriptions

A **record** is an ordered set of one or more fields. A **record-level description** allows you to tell the system what a particular record looks like, or its **record format**.

A record-level description is given in one of two ways:

- *If field-level descriptions are also used*, you identify what fields make up the record format and the order of these fields within the record format. The system can then perform separate operations on each field described with a field-level description in the record-level description. For example, one field can be highlighted while another is not.
- *If field-level descriptions are not used*, the record format is given by specifying the length of the record. The system handles the entire record as a unit and cannot perform operations on one part of the record one way and another part a different way.

Since records are used to transfer data between the system and the application program, a record-level description is required for display files.

File-Level Descriptions

A **file** is an organized set of zero or more records (a file with zero records is empty). A **file-level description** is a description that applies to the file as a whole. For a display file, you can specify the following in the file-level description:

- What record formats are valid for the display file
- What display station should be usable with the display file
- What graphic character set is to be assumed for the data that will be entered through the display file

Deciding Whether to Describe Data Inside or Outside Your Program

When the detailed description of the display file and the data it refers to is contained in a display file rather than imbedded in a program, the data is called **externally described data**. When the data is described within the source program, the data is called **program described data**.

Externally Described Data

Externally described data exists independently of any program that uses the file. Using externally described data, you can produce a detailed and standard description of both the display file and any data that can be processed through the display file.

To use externally described data, you need to declare that the display file is to be used as an externally described file. The language compiler or interpreter extracts the file description from the display and then incorporates it into the program.

There are several advantages to using externally described data:

- *Increased programmer productivity.* The language automatically describes the record layouts for you without additional coding. You need to describe records and fields only once (when the file is created). You can then refer to these fields within the program.

- *Ease of file and program maintenance.* When fields are added, deleted, or changed, it can be done in one place instead of maintaining the record layout in each program that uses the file.
- *Increased data integrity.* Since the fields and records are described in one central location, there is less chance of programming errors when describing the data in the file to the program. All application programs using the file will have the same view of the data. Moreover, the system view of the data becomes the same as the application program view.
- *Level checking provided.* Level checking is an automatic method used when the program is run that determines if the file description has changed since the program was last compiled. Depending on the type of change, the program may only need to be recompiled without modification. This allows better control over program maintenance. There is more information on the level-checking function in “Detecting File Description Changes” on page 2-6.

Program-Described Data

You are not required to use external descriptions to describe your displays in your program. If you do not use externally described data, you must declare variables in your source program that define to the compiler or interpreter what the data looks like.

When program-described data is used, the program and the system may not have the same view of the data:

- If the file does not have any field-level descriptions, the system must operate at the record level. The only concern in this case is that the record length the program is using is the same as what the system is using. It need not be, but the system always operates with the record length it has. If the record length that the system is using differs from the record length the program is using, the system truncates or pads as necessary.
- If the file has field-level descriptions but the program does not use them, the system uses the field-level descriptions even though the program does not. The system expects the program to present data according to the file description and, conversely, provides data to the program according to the description.

More information about program-described data is found in “Using Program-Described Data” on page 2-22.

Creating a Display File and Description

Display files are created using the Create Display File (CRTDSPF) command.

You can define the DDS for your display file in one of two ways:

- Using the screen design aid (SDA) utility
- Entering your own DDS source

You can specify certain attributes about your display file. Information about these attributes is found in the following:

- “Deferring the Write Operation Until a Read Request is Made” on page 3-26
- “Saving Previously Displayed Information” on page 3-42
- *CL Reference*
- *Security Reference*

The following illustration compares the two ways to create display files:

Two Ways to Define Display Files

Enter your own DDS and then use the
Create Display File (CRTDSPF) Command ...

```

A          R GOTO          ALTHelp
A          BLINK
A          CF03(03)
A          CF12(12)
A          HELP
A          HLPCLR
A          1 32'Go To Another List'
A          DSPATR(HI)
A          3 2'Select one of the following:'
A          COLOR(BLU)
A          5 7'1. Work with documents in folder'
A          6 7'2. Work with documents to be print-
A          ed'
A          7 7'3. Work with folders'
A          8 7'4. Work with nontext document data'
A          9 7'5. Work with text profiles'
A          20 2'Selection'
A          01          FLDD01          1A B 21 7
A          DSPATR(RI PC)
A          23 2'F3=Exit'          F12=Cancel'
A          COLOR(BLU)

```



CRTDSPF command compiles DDS and creates
display file object.

Go To Another List

Select one of the following:

1. Work with documents in folder
2. Work with documents to be printed
3. Work with folders
4. Work with nontext document data
5. Work with text profiles

Selection

-

F3=Exit F12=Cancel

Design your display as it will look
using the screen design aid (SDA) utility ...

Go To Another List

Select one of the following:

1. Work with documents in folder
2. Work with documents to be printed
3. Work with folders
4. Work with nontext document data
5. Work with text profiles

Selection

-

F3=Exit F12=Cancel



SDA generates DDS and runs the CRTDSPF command.

```

A          R GOTO          ALTHelp
A          BLINK
A          CF03(03)
A          CF12(12)
A          HELP
A          HLPCLR
A          1 32'Go To Another List'
A          DSPATR(HI)
A          3 2'Select one of the following:'
A          COLOR(BLU)
A          5 7'1. Work with documents in folder'
A          6 7'2. Work with documents to be print-
A          ed'
A          7 7'3. Work with folders'
A          8 7'4. Work with nontext document data'
A          9 7'5. Work with text profiles'
A          20 2'Selection'
A          01          FLDD01          1A B 21 7
A          DSPATR(RI PC)
A          23 2'F3=Exit'          F12=Cancel'
A          COLOR(BLU)

```

RV2W000-5

You may also combine the two methods, creating an initial display using SDA and then tailoring the generated DDS.

Changing the File Description

After a display file has been created, the file description can be changed:

- To change the file description that was originally specified on the CRTDSPF command, use the Change Display File (CHGDSPF) command.
- To change the file-level, record-level, or field-level information contained in the DDS source, you must first update the DDS source and then create the display file again using the CRTDSPF command. A new display file can be created without deleting the existing display file by specifying REPLACE(YES) on the CRTDSPF command.
- To change both the CL command file-level descriptions and the DDS source, specify the new values when you create the display file again.

Changes to display file descriptions are applied according to the following:

- If the file-level description was changed with a CL command, any program that uses the file will automatically use those new descriptions.
- If the DDS descriptions were changed and the program uses the file as a program-described file, the system uses the new file-level description. However, if the DDS descriptions were changed and the program uses the file as an externally described file, then the record-level and field-level descriptions used when the program was compiled may not match the changed file. If the system detects a mismatch when the program opens the file, an error occurs. See “Detecting File Description Changes.”

You may also temporarily change a file-level description when a display file is opened. More information about these temporary changes is found in Chapter 7, “Overriding Display Files and Display File Attributes” on page 7-1.

Detecting File Description Changes

When a program that uses externally described files is compiled, the high-level language compiler extracts the record-level and field-level descriptions for the files referred to in the program and makes those descriptions part of the compiled program. When you run the program, you can verify that the descriptions with which the program was compiled are the current descriptions.

The system assigns a unique **level identifier** for each record format when the file it is associated with is created. The system uses the following information to determine the level identifier:

- Record format name
- Field name
- Total length of the record format
- Number of fields in the record format
- Field attributes (for example, length and decimal positions)
- Order of the fields in the record format

Display files may also use the number of and order of special fields called indicators to determine the level identifier.

If you change the DDS for a record format and change any of the items in the preceding list, the level identifier changes.

To check for changes in the level identifiers when you run your program, specify *YES for the LVLCHK parameter on the CRTDSPF or CHGDSPF command. When the display file is opened, the level identifiers of the display file and the file description that is part of the compiled program are compared format-by-format. If the identifiers differ or if any of the formats specified in the program do not exist in the file, a message is sent to the program to identify the condition.

If the identifiers differ, either the formats have been changed or your program does not use the changed formats. If the changed format does affect your program, you may decide to do the following:

- Compile the program again so that the changes are included
- Determine if the changes affect your program before deciding what action to take.

To check the changes to the record format, run one of the following commands:

- Display File Field Description (DSPFFD) command to display the record-level and field-level descriptions
- Start Source Entry Utility (STRSEU) command to display the source file containing the DDS for the file
- Display File Description (DSPFD) or the DSPFFD command to display the format level identifier defined in the file
- Display Program References (DSPPGMREF) command to display the format level identifier that was used when the program was created

Defining Display Fields and Functions in a Record Format

A record format in a display file describes both the format of the record as it is used in the application program and the format of the record when it is displayed (see Figure 2-2 on page 2-8).

A record format contains field descriptions, which are defined using data description specifications (DDS). For each field in a record format, you describe the following:

- Location of the field on the display
- Length of the field
- Type of data contained in the field (character, zoned decimal, or floating point)
- Field type (output, input, or output/input).

Information about DDS keywords

This section describes how DDS keywords are used to describe the information on your display. For more information about specific DDS keywords, see the *DDS Reference*.

DDS for Display File: The following source shows the DDS for a sample display file:

```
| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|      A          R RECORD
|      A          3  2'Customer Number:'
|      A          CUST          5  0  3  20
|      A          NAME          20    3  44
|      A          ADDR          20    4  44
|      A          CITY          20    5  44
|      A          STATE         2     5  66
|      A          ZIP           5  0  5  70
```

Figure 2-1. Sample DDS Source for a Display File

Table 2-1 on page 2-8 shows the column positions and descriptions for the DDS specifications.

Table 2-1. Column positions for sample DDS

Column	Definition	Starting Position
17	Type of name	17
19 - 28	Field name	19
30 - 34	Length	34
36 - 37	Decimal positions	37
39 - 41	Line location	41
42 - 44	Position location	44
45 - 80	Function	45

Record Format Used by the Program: The program passes the fields in the record in the same order that you described them in the DDS source.

CUST	NAME	ADDR	CITY	STATE	ZIP
1	5 6	25 26	45 46	65 66	67 68 72

RV2W028-1

Record Format on the Display: The fields are displayed according to the display positions you assigned them in the DDS source.




Figure 2-2. Record Formats in the Program and on the Display

Understanding the Field Attribute Characters

Each field displayed has a **beginning attribute character** and an **ending attribute character** associated with it that define the displayed field. The beginning character precedes the first character of a field and is displayed as a blank. The ending attribute character follows the last character of a field and is also displayed as a blank. For example, if you specify a field for positions 2 through 8, the beginning attribute character is in position 1 and the ending attribute character is in position 9. These characters are not included in the field length you specify in DDS. A beginning attribute character can overlap an ending attribute character; that is, they can occupy the same position on the display. However, nothing else can overlap the beginning attribute character. Therefore, when you design a display, you must allow one space for the beginning attribute character of each field. You can use the blank attribute character to space between fields when they are displayed.

If field-level descriptions are not used, the entire record is treated as a field with a beginning attribute character and an ending attribute character.

When a record is displayed so that the last field in the record ends in the last position on the line, the ending attribute character for that field is in the first position of the next line. The beginning attribute character of the first field in the next record can be superimposed on the ending attribute character. For example, if the ending attribute character for the last field in record 1 is in position 1 of line 5, the beginning attribute character for record 2 can also be in position 1 of line 5. In this case, the first record is not considered to be overlapped. However, if the first field in a record begins in position 1, which means that the beginning attribute character is in the last position of the preceding line, the previous record is overlapped and is cleared from the display.

To see the locations of fields in the input records and output records used by the program, see the printed DDS output produced when you created your display file using the CRTDSPF command.

Understanding How Record Format Fields Can Be Used

The fields you describe in the record format can be used in the following ways:

Note: To see the location of positions on a DDS form, see Table 2-1 on page 2-8.

- **Input fields** are fields that are passed from the display station to the program when the program reads a record. Input fields can be initialized with a default value (specified in the record format for the display file). If the user does not change the field and the field is selected for input, the default value is passed to the program. Input fields that are not initialized are displayed as blanks into which the user can enter data. By default, input fields are underlined on the display.

Note: Trailing blanks on input fields are replaced by null and not blank characters; therefore, the Insert key can be used to insert characters in all input fields that end in blanks.

- **Output fields** are fields that are passed from the program to the display station when the program writes a record to a display. Output fields contain data provided by the program, not by the user. To specify an initial value for a named output field, see “Specifying Default Values for Fields” on page 3-26.

In the case of **subfiles**, which are special records used to display lists of information, output fields are returned to the program as if they were output/input fields.

- **Output/input fields** are fields that are passed from the program when the program writes a record to a display and are passed to the program when the program reads a record from the display and the field is selected for input. By default, these fields are underlined on the display. Output/input fields are usually used when the program displays data that can be changed by a user. To specify an initial value for a named output field, see “Specifying Default Values for Fields” on page 3-26.
- **Hidden fields** are fields that are passed from and to the program but are not sent to the display. Hidden fields are useful in applications involving subfiles. For example, a subfile record can contain record key information in a hidden field. The hidden field cannot be seen by the user, but is returned to the

program with the subfile record so that the program can return the record to the database.

- **Constant fields** are fields that are passed to the display but are unknown to the program. These fields are unnamed and have their constant values defined in the DDS for the file. DATE, TIME, and MSGCON are examples of keywords that are allowed only on constant fields and whose constant values are determined during program run time (DATE and TIME) or DDS compile time (MSGCON).
- **Message lines** are output fields that are treated as messages.
- **Program-to-system fields** are output-only fields that are named, numeric or alphanumeric. They are used to communicate between an application program and the system. Program-to-system fields do not appear on the display. That is, your program can place data in these fields and the system will use that data to control its processing on an output operation, but the user cannot see the contents of these fields.

A field is input-capable if it is an input field or an output/input field. Each input-capable field has a special attribute called a **modified data tag (MDT)**. The MDT is set on by the display station when any data is typed into the field. It can also be set on and cleared by the application program.

The maximum number of fields that you can specify for each record format is 32 763. (See “Understanding the Limitations on the Number of Input-Capable Fields” on page 3-39 for information on the number of input-capable fields that can be specified.) The maximum combined length for all fields and indicators in a record format is 32 763.

The following display shows output fields and input fields displayed in response to a request (in the form of entering a customer number in an input field) from a user.

Customer number:	41394
Order number:	41882
Order date:	11/01/81
Order amount:	\$580.00
A/R balance:	\$580.00
Enter next customer number:	_____

The prompts, *Customer number:*, *Order number:*, *Order date:*, *Order amount:*, *A/R balance:*, and *Enter next customer number:* are constants. The data associated with these fields (41394, 41882, 11/01/81, \$580.00, and \$580.00) is displayed in

output fields. The data is passed from the application program to the system, and the system displays it. The field following the constant *Enter next customer number:* is an input field. The user must enter data into this field (the cursor is positioned at the beginning of the input field). Input fields are underlined by default. Editing of the field is normally defined within DDS.

You must specify the location for each field except when the field is a hidden field, a message line, or a program-to-system field, or when the field is in a subfile message record format. You cannot specify line 1, position 1 for location, except when you define a record that can start in any line.


The maximum length of a character field or numeric (zoned decimal) field is the number of positions remaining (relative to the start location of the field) on the display minus 1. Another restriction of the numeric (zoned decimal) field is that it can be no longer than 31, even if more than 31 positions are remaining on the display.

Specifications for the fields you describe can be retrieved from a previously described field. The previously described field can be either in a database file or already defined in the DDS source for the display file. When you use field-level descriptions from a database file, binary and packed decimal fields are changed to zoned decimal fields. These fields that you use to define other fields are called **reference fields**.

You can define two fields to occupy the same positions on the display, and use option indicators to select which of the overlapping fields is to be displayed. If more than one overlapping field is selected on the same output operation, only the first field selected is displayed.

Defining Function Keys

To write an application using a display station, you have to control both the functions of the keys at the keyboard, and the contents of the display.



The Enter key can always be used by the user. So that the user can use the other function keys, you must specify the following DDS keywords to enable the corresponding function key:

- CAnn, where nn is 1-24
- CFnn, where nn is 1-24
- CLEAR

- HELP (not required if you only need the Help key to retrieve the message help on the display)
- HOME
- PRINT
- ROLLDOWN or PAGEUP (not required to be able to roll a subfile when the subfile page is not equal to the subfile size)
- ROLLUP or PAGEDOWN (not required to be able to roll a subfile when the subfile page is not equal to the subfile size)

To tell which function key is pressed when you perform the read operation, you need to define your function keys using one of the following:

- Define a response indicator for the function key. A **response indicator** is an indicator that returns information back to an application. There are 99 response indicators available to you.

Note: Response indicators are used for more than function keys. For example, you can use them to tell when the data in a field on the display has changed.

- Examine the input/output feedback area. The **input/output feedback area** is status information provided by the system about the operations performed on an opened file. To find out how to get information from the input/output feedback area, see the manual for the programming language you are using. See Appendix C, "Feedback Area Layouts for Display Files" on page C-1 for a description of the information available from the feedback areas.

Defining Command Attention (CAnn) and Command Function (CFnn) Keys

The command function (CFnn) keys and command attention (CAnn) keys are numbered 1 through 24 and are the same physical set of keys on the keyboard. These keyboard keys are usually labeled *Cmdnn* or *PFnn* or *Fnn*, where nn is the associated key number. They can be used to set a response indicator or to perform a certain function.

The different command keys do the following:

Command function	A record containing changed fields is returned to the program.
Command attention	A record is returned to the program but the record does not contain the data entered by the user and no field validation is performed.

If a key is specified as a CFnn key in a file, it cannot also be specified as a CAnn key in the file. Likewise, if it is specified as a CAnn key, it cannot also be a CFnn key. For example, if function key 01 is specified as a CAnn key (CA01), you cannot specify CF01 anywhere in the same file.

If a response indicator is specified for a CFnn key and the key is pressed, the response indicator is set on and passed to the program with the input data. If a response indicator is not specified for a CFnn key, only the input data is passed.

Note: The input/output feedback area contains the 1-character attention identifier (AID), which also identifies the key pressed. See Appendix C, "Feedback Area Layouts for Display Files" on page C-1 for a description of the input/output feedback area.

If a response indicator is specified for a CAnn key and the key is pressed, the response indicator is set on and passed to the program. Fields sent to the display and hidden fields are returned to the program. If a CFnn key or the Enter key was previously pressed, the input-only field is returned as previously typed data. If data was never entered into an input-only field, the field is returned as blanks (character field) or zeros (numeric field). Fields changed by the user since the last time a CFnn key or Enter key was pressed are not returned.

The use of CAnn keys can cause the input buffer of the program to contain user-entered data that does not meet the validation specified in the display file. For example, the user enters data and presses a CFnn key or the Enter key, and the data is validated as defined in your DDS. Input data is processed one field at a time with data manipulation taking place before the validity checking. If a validity-checking error occurs, a message is selected and all the other input data is processed. After all input data is processed and one or more errors have occurred, a message is sent to the user. Then, if the user presses a valid CAnn key, no changed data is sent from the display. The data is moved from the input buffer save area to the input buffer. The input buffer now contains the data that is in error. If your program is not going to process this data when the CAnn key is pressed, you do not have a problem. If this is a problem, avoid using CAnn keys; only use CFnn keys so that data that is not valid can be detected.

If you want to use CAnn keys, you should not specify the following validity-checking DDS keywords:

```
CHECK(M10)
CHECK(M11)
CHECK(VN)
CHECK(VNE)
CHKMSGID
COMP/CMP
RANGE
VALUES
```

The Print, Help, Clear, and Home keys operate in the same manner as the CAnn keys. The Roll Up, Roll Down, Page Up, and Page Down keys operate in the same manner as CFnn keys.

Specifying Alternative Keys

You can also define command attention or command function keys to perform the functions of the Help, Page Up (or Roll Down) and Page Down (or Roll Up) keys. The function key specified on the keyword identifies the alternative key to be used.

The DDS keywords are:

- **ALTHELP**: Indicates that the help function will be started when either the Help key or the key specified on the ALTHELP keyword is pressed. If the ALTHELP keyword is specified but an alternative key is not specified, the default is CA01. Note that the Help key is an attention key, not a function key, because it does not return input.
- **ALTPAGEUP** and **ALTPAGEDWN**: Indicate that the paging functions will be started when the page keys or the keys specified on the keywords are pressed. If alternative keys are not specified on the ALTPAGEUP or ALTPAGEDWN

keywords, the defaults are CF07 and CF08, respectively. Note that the page keys are function keys, because they return input.

The alternative keys specified on the ALTHELP, ALTPAGEUP, and ALTPAGEDWN keywords provide the same function as the actual keys. For example, if pressing the Help key starts the help function, then pressing the alternative key defined by the ALTHELP keyword will also start the help function. Likewise, if pressing the Page Up or Page Down key returns control to the application program, then pressing the alternative key will also return control to the application program. Both of these examples appear to the program as if the actual key was pressed.

The user profile option for paging (USROPT(*ROLLKEY)) applies to the PAGEUP, PAGEDOWN, ALTPAGEUP, ALTPAGEDWN, ROLLUP, and ROLLDOWN keywords.

The alternative help key function does not work when the keyboard is locked. For example, if you type information into a field that is not input-capable, a controller-detected error occurs and flashing numbers appear. The Help key can be used to get more information about the error. The function key specified as the alternative help key will not be valid until the Reset key is pressed, and then the help information will no longer be available.

Passing Information via Indicators

Indicators are one-character fields that exist either in the input records and output records used by the program or in a special indicator area. An indicator is on if it has the value 1 and off if it has the value 0. You can use indicators to pass information from a program to the system or from the system to a program. You specify how indicators are to be used through the DDS for the display file.

There are two types of indicators for display files:

- | | |
|-----------------------------|--|
| Option indicators: | Pass information from an application program to the system. These typically are used to control the processing of a particular record format by the system. |
| Response indicators: | Pass information from the system to an application program when an input request completes. Response indicators can inform the program which function keys were pressed by the user or whether data was changed by the user. |

Both option and response indicators can be specified at the file level, record format level, and field level. Indicators specified at the file level apply to all record formats within the file.

Removing Option and Response Indicators from the Record Area

You can use the Indicator Area (INDARA) keyword to separate the option and response indicators from the input and output records used by the program. If you use the INDARA keyword, the indicators are placed in a separate 99-character area; see your appropriate high-level language manual for information on how this 99-character area is defined.

If you use the same indicator number as both a response indicator and as an option indicator, you can use the status of the response indicator to set the option

indicator for a subsequent output operation. For example, indicator 15 is used as both a response indicator and an option indicator. If the response indicator is on when an input operation is performed on the record format, option indicator 15 is set on and will be on when an output operation is performed for that record format.

The maximum number of record formats that you can define for a display file is 1024. If you do not use the INDARA keyword, the maximum number of fields that you can specify depends on the number of indicators (1 character each) you use and the length of each field you describe. The total combined length of all fields and indicators in a record format cannot exceed 32 763 characters. If you use the INDARA keyword to specify a separate indicator area, the maximum number of fields that you can specify depends only on the length of each field. The total number of all fields cannot exceed 32 763.

Enabling Different Response Indicators Simultaneously

It is possible to have different response indicators for the ROLLUP/ROLLDOWN keywords on record formats displayed at the same time. For example, record A has specified a roll-up indicator of 52 and record B has specified a roll-up indicator of 25 and both records are displayed. When a read operation is requested to record A in your program, the operator presses the Roll Up key which returns control to your program. Record A is passed to your program with response indicator 52 set on; response indicator 25 is not set. Your program can then do a read operation to record B. When record B is passed to your program, response indicator 25 is set on; response indicator 52 is not set. Only the response indicator specified on the record format for which the read operation is done is set. The record format in which the cursor was located when the Roll Up key was pressed does not affect the setting of the response indicator associated with the ROLL keyword.

Setting an Indicator Off

An indicator specified on the SETOF or SETOFF keyword becomes a response indicator that is set off and returned to the program. The indicator is not set off until an input operation is performed. If the same indicator is specified elsewhere in the record format as a response indicator, the indicator is returned to the program based on the status of the associated keyword condition. For example, if response indicator 01 is specified both for the SETOF/SETOFF keyword and the CF5 key, indicator 01 is returned in the on condition when the CF5 key is pressed. If the indicator is specified elsewhere as a response indicator, there is no need to use the SETOF/SETOFF keyword.

Inserting Constant Field Text from a Message Description

You can specify that the text for constant fields is contained in a message description using the Message Constant (MSGCON) keyword.

If the message description used for the constant text is shorter than the field on the display, the remaining portion of the field is padded with blanks. If the message description is longer than the field, the message description is truncated.

If the message description does not exist when the DDS is compiled, the file is not created. If you change the message description, you will have to create the file again if you want the display file to contain the updated messages.

Allowing for Right-to-Left Cursor Movement

The cursor can be made to move from right to left on the display between fields and in input fields. Two parameters for the DDS CHECK keyword can be used to do this:

- CHECK (RL): Moves the cursor from right to left in specified nonnumeric input fields or all nonnumeric input fields on the display.
- CHECK (RLTB): Moves the cursor from right to left between fields.

When using these parameters, remember the following:

- Modulus check digit verification is supported, but the check digit is still the byte to the extreme right of the field.
- A field for which right-to-left cursor movement is specified can occupy more than one line on the display. However, the cursor still moves from the top of the display to the bottom.
- You cannot use right-to-left cursor movement with user-defined data streams.

Note: If no cursor positioning is specified in the display file or by the program, the cursor is placed in the input-capable field to the extreme left of the top line.

Specifying Right-to-Left Display Processing

You can specify that records in a display file be written in the right-to-left direction by using the Display Right-to-Left (DSPRL) keyword. This keyword is allowed only at the file level.

Figure 2-3 shows an example of the DDS coding.

```
| .....1.....+.....2.....+.....3.....+.....4.....+.....5.....+.....6.....+.....7...
|      A                                         DSPRL
|      A      R RECORD
|      A      FLD1      20A      5  5')Customer Name(:'
```

Figure 2-3. Sample DDS for Right-to-Left Display Processing

The DDS in Figure 2-3 produces this output on the display:

```

: (emaN remotsuC)
```

Notice that the left and right parentheses in the DDS are reversed; this is so they appear correctly on the display. All symmetrical characters have to be specified in this way.

If your application program uses one display file with the DSPRL keyword and another display file with the WINDOW keyword, make sure that the display file with the WINDOW keyword also specifies the DSPRL keyword. Otherwise, the display assumes the orientation of the display file that has the WINDOW keyword.

If you specify the DSPRL keyword, the cursor moves from right to left when you enter data. Therefore, it is not necessary to use the CHECK(RL) keyword. If you specify CHECK(RL) and DSPRL, the CHECK(RL) keyword is ignored.

The DSPRL keyword causes all records in a display file to be written in the right-to-left direction. You cannot specify that individual records be written in the left-to-right direction.

If you specify the ERRMSG or the ERRMSGID keywords with the DSPRL keyword, the messages associated with these keywords display in the left-to-right direction.

Emphasizing Fields

You can emphasize a field of a record on the display by specifying the following in the DDS for the file:

Note: Any function not supported for your display station is ignored.

Table 2-2. DDS for Emphasizing Fields

Type of Emphasizing	DDS keyword
Underlining a field (the default for input fields)	DSPATR(UL)
Placing vertical separators between the characters in a field	DSPATR(CS)
Highlighting a field by displaying it with greater intensity than is normally used on the display	DSPATR(HI)
Reversing the image of a field from light on dark to dark on light or from dark on light to light on dark	DSPATR(RI)
Making the data in the field invisible to the display station user	DSPATR(ND)
Placing the cursor at a specific field	DSPATR(PC)
Blinking a field when it is displayed	DSPATR(BL)

Another way of specifying attributes for a field is by using a program-to-system field parameter on the DSPATR keyword. Your application program uses the program-to-system field to set the display attributes or protection attribute for the field to which the DSPATR keyword applies.

Figure 2-4 shows an example of the DDS coding for program-to-system fields:

	...	1	...	2	...	3	...	4	...	5	...	6	...	7	...
	A			R		RECORD									
	A			FLD1			5A		2		2DSPATR(&PFLD1)				
	A			FLD2			5A		2		9DSPATR(&PFLD2)				
	A			PFLD1			1A		P						
	A			PFLD2			1A		P						

Figure 2-4. Sample DDS for Program-to-System Fields

One program-to-system field may be used for multiple fields within a record. Only one program-to-system field can be used per field. You cannot specify the following attributes using the program-to-system field:

- MDT** Set changed data tag when displayed
- OID** Operator identification

PC Position cursor

SP Select by light pen

For the valid hexadecimal values that your program can pass to the program-to-system field, see the *DDS Reference*.

Adding Color

You can design your displays for use on display stations that show color. The DDS keyword **COLOR** allows you to specify the following colors for fields: green, white, red, turquoise, yellow, pink, and blue. This keyword is ignored if it is selected for a field displayed on a display station that does not support color.

If the **COLOR** keyword is not specified in the DDS for the display file but the display station is specified in the display station description as a color display station, displays that you have designed for display stations that do not support color can also be used for the color display station. The keywords **DSPATR(UL)** and **DSPATR(RI)**, if specified on separate fields, function the same as they do for the 5250 display station. However, the keywords **DSPATR(CS)**, **DSPATR(HI)**, and **DSPATR(BL)** produce the following colors on a color display station (the specified display attributes **CS**, **HI**, and **BL** are suppressed):

Color Produced on the Color Display Station when No COLOR Keyword is Specified	Display Attribute Selected: DSPATR(CS)	Display Attribute Selected: DSPATR(HI)	Display Attribute Selected: DSPATR(BL)
Green (normal)			
Turquoise	X		
White		X	
Red, no blinking			X
Red, blinking		X	X
Yellow	X	X	
Pink	X		X
Blue	X	X	X

Editing Output Fields

The system provides editing support that makes fields more readable when they are displayed. With the system editing support, you can do the following:

- Suppress leading zeros
- Punctuate a field with commas and periods to show decimal column and to group digits by threes
- Show negative values with a minus sign to the left or right
- Show negative values with the letters **CR** (credit) to the right
- Show zero values as zeros or blanks
- Show asterisks to the left of significant digits to provide asterisk protection
- Show a currency symbol corresponding to the system value **QCURSYM**

The system provides this editing support with edit codes and edit words. **Edit codes** are a defined set of editing patterns. In addition to those provided by the system, you may also define your own edit codes. You identify edit codes by

name, and the system edits a field according to the pattern defined by the named edit code. **Edit words** are edit patterns that you define to produce the desired results. Edit codes cover most commonly used editing requirements. You need to use the edit word support only for those editing needs not covered by edit codes.

Edit codes are used as follows:

- If your application is using program-described data, your high-level language may allow you to identify edit codes or create your own edit words.
- If your application is using externally described data, the edit code (EDTCDE) DDS keyword allows you to identify an edit code, and the edit word (EDTWRD) DDS keyword allows you to define your own editing pattern.

The system provides several edit codes. The editing patterns defined by these codes are contained in Appendix F, "Edit Codes."

Defining Your Own Edit Codes

You can define five edit codes to provide more editing function than is available with the OS/400* edit codes, and to handle common editing functions that would otherwise require the use of an edit word. These are called user-defined edit codes. For example, you may need to edit numbers that include hyphens (like some telephone numbers), or more than one decimal point. You can use user-defined edit codes for these functions. These edit codes are named QEDIT5, QEDIT6, QEDIT7, QEDIT8, and QEDIT9 and can be referred to in DDS or a high-level language program by number (5, 6, 7, 8, or 9).

These edit codes are created by using the Create Edit Description (CRTEDTD) command. Edit descriptions are always placed in library QSYS. They cannot be moved or renamed; only one occurrence of each is allowed. Edit descriptions have an object type of *EDTD.

Even though they are user-defined edit codes, your system comes with a version of each one of them. You can use these edit descriptions as they are, or you can delete them and create your own. The editing performed by the IBM-supplied versions of these edit descriptions as well as a definition of the contents of and the rules for using any user-defined edit code are described in Appendix F, "Edit Codes."

Before using any of the user-defined edit codes, you should check its contents on your system, since it may have been changed from the IBM-supplied version. The Display Edit Description (DSPEDTD) command will display the contents of a user-defined edit code.

Changing a user-defined edit code description does not affect any application or display file that has already been created using that edit description. If you want your application to use the changed edit description, you must either create the high-level language program again (if the edit code is referred to in the program) or create the file again (if the application is using an externally described file that contains EDTCDE keywords).

Specifying Valid Screen Sizes

In some cases, you can use the following screen size condition names to select keywords and display locations based on screen size:

- *DS3, 24 by 80 (5251 Models 11 and 12, 5291, 5292, 3179 Model 2, 3180-2, 3196, and 3197)
- *DS4, 27 by 132 (3180-2; 3197 Models D1, D2, W1, W2; 3477 Models FA, FC, FD, FE, FG, FW; 3487 Models HA, HG, HW, HC)

Note: The capability to display in 27 by 132 mode is allowed on 3180-2, 3197, 3477 Models FA, FC, FD, FE, FG, FW, and 3487 Models HE, HD, HW, HC display stations attached to a 6040 or 6041 or 2638 local display station controller, or remotely attached to a 5294 or 5394 controller. The display size for 27 by 132 mode is ignored for the DSPSIZ keyword unless these controllers are specified.

These condition names can be used to place fields in different locations on different sizes of screens. However, the fields must still be specified in the same order on each size of screen. For example, the following DDS formats a display for both a 24 by 80 screen and a 27 by 132 screen:

1....	+....2....	+....3....	+....4....	+....5....	+....6....	+....7...
A							DSPSIZ(*DS3 *DS4)
A							.
A							.
A							.
A		R	RECORD				
A			NAME	20	5	2	
A	*DS4					3112	
A			ADDR	30	6	2	
A	*DS4					4102	

Figure 2-5. Sample DDS for Two Display Sizes

Normally, the display files are set up for a 24 by 80 screen (default size). The DSPSIZ keyword specifies which display sizes are valid for a file and indicates which sizes are the primary and secondary screen sizes. (The primary screen size is the first or only DSPSIZ value.) On the DSPSIZ keyword, the screen size can be specified as *DS3, *DS4, 24 80, or 27 132. For example, DSPSIZ (24 80) specifies a screen size of 24 by 80.

The screen size designated as the primary screen size should be the one with which the display file will most often be used. A performance benefit will be realized by coding the DSPSIZ keyword in this manner. Additional processing is performed when the actual screen size is the secondary screen size.

The screen size condition names let you improve the use of a single display file for any size screen. For example, when you are using subfiles, you can specify 22 records per page for a 24 by 80 screen or 25 records per page for a 27 by 132 screen:

1	2	3	4	5	6	7
A				DSPSIZ	(*DS4 *DS3)	
A				.		
A				.		
A				.		
A				SFLPAG	(25)	
A	*DS3			SFLPAG	(22)	
A				.		
A				.		
A				.		

Figure 2-6. Sample DDS for Subfiles for Two Display Sizes

You can also define your own screen size condition names.

Enabling Your Display to Be Printed

If the Print key is enabled for your display, the user can print the current display by pressing the Print key. The parameter (or lack of parameter) you specify for the DDS PRINT keyword controls how your display is printed:

Table 2-3. PRINT Keyword Results Using Print Key

Parameter	Action
No parameter	The output goes to the display station printer associated with this display (the PRINTER parameter on the Create Device Description for Display (CRTDEVDSP) or Change Device Description for Display (CHGDEVDSP)). If the operation to the display station printer fails or if there is no display station printer specified, the output goes to the printer file specified on the PRTFILE parameter on the display station description. The default for the PRTFILE parameter is QSYSVRT.
File name and, optionally, library name	The print operation is directed to the specified printer file. If the operation fails, it is directed to the default printer file, which is specified on the PRTFILE parameter on the CRTDEVDSP or CHGDEVDSP command.
Response indicator	Control returns to the program with the response indicator set on.
*PGM	Control returns to the program which must check the attention identifier in the input/output feedback area to determine which key was pressed.

The PRINT keyword can be used at the file level and also at the record level. When PRINT is specified at the record level, several records with different forms of the PRINT keyword (or with no PRINT keyword) may be displayed on the screen at the same time. The last record format written to the screen controls the use of the Print key for the entire screen.

If you specify the PRINT keyword in any form, the user can print a display containing the message help.

The PRTKEYFMT parameter allows you to control what information is included when you print your display:

- Output only

- Output with header information (rows and columns)
- Output with border information (title lines, which include the system name, date and time, and formatted user and display device name)
- Output with both border and header information

The PRTKEYFMT parameter on the Change Job (CHGJOB) and Retrieve Job Attributes (RTVJOBA) commands allows you to select how you want your Print key output to look.

When you change the device description of a display station printer (by using the CHGDEVPRT command or the DLTDEVD and CRTDEVPRT commands), you should also change the device description of the associated display station, using the PRINTER parameter on the CHGDEVDS command. You should do this even if the name of the printer, whose device description you changed, remains the same.

Defining Windows

There are applications that could make use of a window on the display to assist the user in entering data.

A **window** is information that overlays part of the current display and allows the user to read the information inside the window. The remainder of the display is not overlaid by the window and can still be read by the user.

You can create windows by using standard DDS or by using user-defined data streams. To use standard DDS, see Chapter 5, “Defining Windows with Display Files” on page 5-1. Examples are also available in the QUSRTOOL library.

Using Program-Described Data


You can create a display file without using data description specifications. Such a display file then uses program-described data, and has no record or field level descriptions of its own.

When you are using program-described data with a display file to communicate with one or more display stations, only simple display formatting can be performed, and that formatting must be specified in the high-level language program that is using the file. All field descriptions are defined and all processing is performed in the program that uses the file. More than one display file can be opened to the same display station at the same time within the same program, but only two can be used on the same display station at the same time: one for input and one for output.

When a display file that uses program-described data is opened, the system treats the area on the display as a single field. That is, the field length is the same as the record length. The record length is defined by the program that is using the file, and stays the same from the time the file is opened until it is closed. Indicators cannot be passed when records are passed from the program to a display station, or from the display station to a program. Also, command keys cannot be used for program-described display files.

The space on the display is assigned to program-described display files as shown in the following example.

Records for the first file used by the program appear on the first (top) part of the display. Records for the second file appear on the display immediately following the area used by records in the first file.



RSLH705-0

The record from file B starts at the beginning of the first full line after the last line of the record from file A. If the record from file A does not completely fill its last line, the space is used by neither record and must be accounted for when calculating the maximum record lengths. In program-described display files, the maximum record lengths are:

- For an input file, the screen size minus 2
- For an output file, the screen size minus 2
- For an output/input file, the screen size minus 2
- For two files (one output and one input), the screen size minus 3

When a program-described display file is opened, it can be defined as:

- Input only
- Output only
- Input and output

Defining Input-Only Files

When an input-only file is opened, the record is initialized to a single blank field on the screen. The cursor is positioned at the first position of the field and the user can type in any type of data.

When the program reads the record, the input is passed to the program. The record is not erased from the screen. The cursor is again positioned at the first position of the record (field) and the keyboard is unlocked when the program reads the next record. The user can then type in the next record over the previous record.

Defining Output-Only Files

When an output-only file is opened, the record is initialized to a single blank field on the screen. When the program writes a record to the file, the record is displayed and the keyboard is locked. The user must press the Enter key before another record can be written to the file. Subsequent records written to the file erase the currently displayed record because only one record can be displayed for the output file.

Defining Input and Output Files

When an input and output file is opened, the record is initialized to a single blank field on the screen. The cursor is positioned at the first position of the file and the user can type in any kind of data.

The program that is using the file can read records or write records in any sequence. Whenever a record is written to the file, the modified data tag is set off (to indicate that data was not entered into the field) and the keyboard is unlocked. If the user then enters data into the field, the modified data tag is set on. If the next operation is a write operation instead of a read operation, the data typed in by the user is written over and the modified data tag is set off again.

Chapter 3. Working with Display Files in an Application

After you define your display file, you can use it in an application. This chapter discusses the operations performed when a display file is used in an application.

Understanding How the System Allocates Resources

When a high-level language program uses a display file, several operations require that the system allocate the resources needed to perform that operation. Allocating file resources causes the system to obtain a lock on a display file when it is opened. Multiple users then cannot use the same display file in conflicting ways. For example, the system will not allow you to delete a file while any application program is using it.

File resources are allocated in two ways:

- The system performs the allocation whenever an operation is requested that requires it. The following operations for display files require allocation:
 - *Open*: The file resources include the file description and the display station. More information about the open operation is found in “Opening Display Files” on page 3-2.
 - *Acquire*: The display station is allocated as a resource. More information about the acquire operation is found in “Acquiring a Display Station for I/O Operations” on page 3-2.
 - *Starting a program on a remote system*: The file resources include session resources needed for APPC/APPN*.
- If you prefer to ensure that all the resources that are needed by a program are available before the program is run, you may use the Allocate Object (ALCOBJ) CL command in the job prior to running the program.

When allocating resources, the system waits for a predefined time if the resources are not immediately available. If the resources do not become available within the time limit, the following happens:

- If you are using the ALCOBJ command, the command fails.
- If your program is performing a file operation, that operation fails and an error message is sent to the program message queue.

You may attempt to use the error handling functions of your high-level language to try the operation again. For example, if an open operation fails because another job is using the display station associated with the file, you could retry the open operation later when the display station is no longer being used.

The length of time that the system waits when allocating resources is specified on the ALCOBJ command and on the WAITFILE parameter of the CRTDSPF command. If the ALCOBJ command is used prior to running a program, then the value of the WAITFILE parameter is ignored because resources are available. If your application has error handling procedures for display station errors occurring on display files, you should specify a value other than *IMMED to allow the system to recover from the display station error. The system recovery procedures for the display station must be completed before your program can recover from errors due to the allocation of resources.

Opening Display Files

The **open operation** connects a display file to a program for processing.

When a display file is opened, usually one or more display stations are implicitly acquired, or automatically prepared for I/O operations, for the display file:

Table 3-1. Display Stations Implicitly Acquired When Display Files Are Opened

How the Display File is Defined When Opened	Other Specifications	Display Station Implicitly Acquired
Defined with a single display station	*REQUESTER specified	Display station at which the user requested the program
	*REQUESTER not specified	Display station specified on the DEV parameter of the CRTDSPF, CHGDSPF, or OVRDSPF command
Defined with multiple display stations	Opened by a CL program	All display stations specified on the DEV parameter of the CRTDSPF, CHGDSPF, or OVRDSPF command
	Opened by any high-level language other than CL	The first display station specified on the DEV parameter of the CRTDSPF, CHGDSPF, or OVRDSPF command
Defined with no display stations	—	None

The value specified on the WAITFILE parameter for the CRTDSPF, CHGDSPF, or OVRDSPF command is used to determine how long the open operation should wait for file resources to become available so they can be allocated. If a file resource, such as a display station, does not become available and the wait time specified ends, the open operation fails.

Implicitly acquiring a display station when the file is opened results in the following:

- The screen is cleared completely and the cursor is placed in the upper-left corner of the display.
- The keyboard is unlocked.

Any display station to be implicitly acquired at the open operation must be varied on. Switched-line display stations can also be acquired if they are in a vary-on-pending state. Also, a display station other than the *REQUESTER display station cannot be acquired if it is signed on.

Acquiring a Display Station for I/O Operations

The system implicitly acquires, or automatically assigns, a display station to a display file when the display file is opened. However, you may also acquire additional display stations for your program using the **acquire operation**. The acquire operation is used in multiple display file applications or if you are performing error recovery in your application.

A successful acquire operation results in the following:

- The screen is cleared completely and the cursor is placed in the upper-left corner of the display.
- The keyboard is unlocked.

The value specified for the WAITFILE parameter on the CRTDSPF, CHGDSPF, or OVRDSPF command is used to determine how long the acquire operation should wait for a display station to become available so it can be allocated. If a display station does not become available and the wait time ends, no display is acquired.

A display station cannot be allocated unless it is varied on. Switched-line display stations can be allocated if they are in a vary-on-pending state. Also, a display station other than the *REQUESTER display station cannot be allocated if it is signed on.

The system allows only one *REQUESTER display station to be acquired to any display file, including a multiple-device display file.

If an acquire operation is not successful, the release operation is the only valid operation to the display station.

Obtaining Information about Display Files and Display Stations

You can obtain information about the open and I/O operations performed on an open display file, and attribute information about a display station you are using.

Obtaining Information about Open and I/O Operations

After a display file is successfully opened, the system keeps track of the status of the file in feedback areas.

The **open feedback area** contains information about the display file after it has been successfully opened, including:

- Name and library of the display file
- Number of rows and columns on the display
- Name and library of the file after overrides have been applied
- Information about the display station defined for the file

The **device definition list** part of the open feedback area contains information about each device attached to the display file.

The **I/O feedback area** contains information about the I/O operations performed on the display file after it has been successfully opened. The I/O feedback area has two sections:

- The **common feedback area** contains information about I/O operations that were performed on the file. This includes the number of operations and the last operation.
- The **file-dependent feedback area** contains file-specific information for display files, such as the major/minor return code and the amount of data received from a display station.

As operations are performed on the display file, the feedback area is updated to reflect the latest status.

There is one feedback area for each open file. An exception is for shared files, which share feedback areas as well as the data path between the program and the file. For more information on shared files, see “Sharing Display Files in the Same Job” on page 3-50.

Feedback areas can be used to provide information when errors occur. For example, when an error occurs with a display file, the program could determine predefined error handling operations based on the major/minor return code in the file-dependent feedback area. More information on major/minor return codes is available in Chapter 8, "Handling Messages and Errors for Display Files."

Some high-level languages on the system allow you to access the status and other information about the file against which operations are being performed.

See Appendix C, "Feedback Area Layouts for Display Files," for a description of all the information available from the feedback areas.

Obtaining Attribute Information about Display Stations

The **get-attributes operation** allows you to obtain the following information about a specific display station:

Table 3-2. Information Available from the Get-Attributes Operation

Information	Details
The specific model of the display station	Valid only when the display station is acquired to the file
The screen size of the display station	Valid only when the display station is acquired to the file
Device acquired indicator	Indicates whether or not the display station is currently acquired to the file
Device invite status	Indicates whether or not the display station is invited, and if so whether or not the display station has data available; valid only when the display station is acquired to the file
*REQUESTER display station indicator	Indicates whether or not the display station is the *REQUESTER display station

Since the information supplied is also available in the open and input/output feedback areas for the display station that is implicitly acquired when the file is opened, the **get-attributes operation** is most useful for multiple display file applications. For more information on how to perform the **get-attributes operation**, see the appropriate high-level language manual.

See Appendix C, "Feedback Area Layouts for Display Files," for a description of all the information available from the **get-attributes operation**.

Sending and Receiving Data

All data written to and read from the display by the application program is done with records. Records consist of fields, which are individual items of data. The high-level languages in which application programs are written have I/O statements that give data to the system to be written to the display and receive data from the system that it read from the display in the form of records.

The I/O statements of the high-level languages also refer to record formats, which are defined using DDS. On output, a record format describes how the data given by the program is to be presented on the display as well as how the data is to be processed before presenting it. On input, the record format is used to control some display functions, to extract the program data from all the data which is on the display, and to present that data back to the application program.

Information about DDS keywords

This section uses DDS keywords that control sending and receiving information to the display. For more information about specific DDS keywords, see the *DDS Reference*.

Determining Which Record Formats Are Active on a Display

The system maintains the **active record format table**, a table of all record formats that are currently on the display. Read operations may take place against only those record formats that are in the active record format table. Certain DDS keywords cause records in the table to be altered.


A record format is added to the table when a write operation that contains the record format is performed. A record format is removed from the table when a read operation can no longer be correctly performed for this record.

The active record format table is cleared whenever the display is cleared.

Writing Output to the Display

A **write operation** passes a record from the program to the system. The record format in the display file contains the information necessary for the system to handle the record. The write operation results in the following:

Write Operation



RV2W010-1

Placing Records on the Display

One record format can occupy an entire screen or the screen can be divided to display more than one record format.

If a record is displayed on more than one line, the following rules apply:

- The lines must be consecutive lines on the display. For example, if one record occupies two lines and the record begins on line 2, the record must continue on line 3.
- Only a beginning attribute character can occupy line 1, position 1.

- If only the ending attribute character for the last field in a record is in position 1 of the next line, another record format can begin on that same line.
- Only one record can occupy a line on the display at a time. If you want to display a record format that overlaps one or more lines of a record format already on the display, specify *NO for the clear lines (CLRL) keyword. CLRL(*NO) clears the common lines before displaying the new record format.

The following three figures show how screens can be divided when the CLRL keyword is not specified:




Figure 3-1 (Part 1 of 3). Valid Placement of Records on a Screen When the CLRL Keyword Is Not Used




Figure 3-1 (Part 2 of 3). Valid Placement of Records on a Screen When the CLRL Keyword Is Not Used





Figure 3-1 (Part 3 of 3). Valid Placement of Records on a Screen When the CLRL Keyword Is Not Used

The following figure shows how screens *cannot* be divided when the CLRL keywords is not specified:



RV2W048-0

Figure 3-2. Wrong Placement of Records on Screen When CLRL Keyword Not Used

Understanding Which Records Do Not Occupy Space on the Display

The following types of records do not occupy space on a display but are assumed to be at line 0:

- Records with no fields defined
- Records with only hidden, program-to-system, or message fields
- Records with the CLRL keyword specified and with no input-capable fields

The system keeps track of only one of these records at a time. If an output operation for a record assumed to be at line 0 replaces another record assumed to be at line 0, you can no longer issue an input operation for the replaced record.

Changing Record Formats on a Display


The formats displayed can change while a file is being processed because information on a display can be deleted when new formats are displayed.

When your program displays a new record format for output or to allow input, the existing display is usually erased before the new record format is displayed. For example, if three record formats are on the display at the same time and you write another record to the display, the three record formats on the display are erased. Several DDS keywords, such as the OVERLAY keyword, let you control the displaying of records and input fields on input and output operations. For more information about these DDS keywords, see “Overlaying and Erasing Record Formats on a Display” on page 3-10 and “Clearing a Specified Number of Lines” on page 3-13.

In the follow example, the fields are defined for a record format as follows:

- Fields from record format A occupy lines 1 through 4.
- Fields from record format B occupy lines 5 through 7.
- Fields from record format C occupy lines 8 through 10.
- Fields from record format D, which has the CLRL keyword specified for it, occupy lines 5 through 9.

In the following illustration, record formats A, B, and C are displayed first. When record format D is displayed, it replaces record formats B and C.



RSLH700-0

Figure 3-3. Replacing Record Formats

If record format D did not have the OVERLAY keyword specified for it, the following would have happened in the previous example:

- Record format A would also have been deleted.
- Lines 5 through 7 of record format B would have remained on the display. The data in any fields of record format B overlaid by record format D would have been changed. (see “Clearing a Specified Number of Lines” on page 3-13 for more information).

Deciding the Order of Record Formats Written to the Display

To improve performance, records containing input fields should be sent to the display station in the order in which they appear on the display.

In Figure 3-3, if record formats A and B both contain input fields and appear on the same display, record format A should be sent to the display first.

Overlaying and Erasing Record Formats on a Display

To avoid erasing the existing display when your program displays a new record format for output or to allow input, you can specify the OVERLAY keyword. The OVERLAY keyword causes only those records that are completely or partially overlapping to be erased; all other records remain on the display.

Note: The OVERLAY keyword does not prevent the screen from being erased if it is in effect for the first write operation after a file is opened unless the DDS keyword ASSUME is specified for any record format in the display file.


You can use the OVERLAY keyword to display information from your application that needs to be presented together but naturally falls into two or more pieces. For example, you could use one record format in your application to present information for a state at the top of a display and another record format to provide the information for a particular region within that state.

To place two or more records on the display at the same time, separate the write operations for your display from the read operations. Then, when you perform each write operation, the system takes the data from the record that you have provided it, combines it with the information specified in the record format, and places it on the display. You can lock the keyboard until the display is ready to perform the read operations by doing one of the following:

- Specify the LOCK keyword on all the record formats
- Specify *YES for the Defer Write (DFRWRT) parameter for the display file

You can use multiple record formats when you want to present lists of information in a subfile to the user. A subfile is a group of records that have the same record format and are read from and written to a display station in one operation. For more information about subfiles, see Chapter 4, “Displaying Groups of Records Using Subfiles” on page 4-1.

To erase certain records from the display when you overlay records, use the ERASE keyword with the OVERLAY keyword. The following diagram shows the effect of the OVERLAY and ERASE keywords on an output operation:



- 1** Record format B is erased because record format D overlaps it, and record format D is displayed. Record format D did not use all of the space record format B previously used so it does not overlap record format C.
- 2** Record format B is erased because record format D overlaps it and record format C is erased because ERASE C is specified. Record format D is displayed, and part of the display is no longer in use.

Starting Your Record Format on a Specific Line

To start your record format on a specific line, use the starting line number (SLNO) keyword. On the SLNO keyword, you can specify one of the following:

- *The actual starting line number for the record format (a value from 1 to 27).*
When you specify an actual line number, the system adjusts the line numbers for all fields in a record by the specified value minus 1.
- *A variable starting line number (*VAR), which allows you to specify a starting line number value in your high-level language program at run time.* Depending on the value specified in your program, the following occurs:

Table 3-3. Results of SLNO(*VAR) Values

Value Specified	Results
0 or no value specified	A starting line number of 1 is assumed.
Value exceeds the number of lines on the screen or is a negative value	The system sends a message to the program and the I/O request is not performed.
The starting location for the field for at least one display size is row 1, column 1	A warning message (severity 10) is issued at file creation time. At run time, an error message is issued if the screen size being displayed contains a field starting in row 1, column 1, and the variable starting line number is set to 1 by the program.

Each programming language (except BASIC/400) provides a different way to set and add to the starting line number. See the appropriate manual for the language you are using.

The system adjusts the line numbers for each field in the record format by the specified value minus 1. If the resulting line number exceeds the screen size, the field is not displayed. In addition, if any part of a field goes beyond the last line on the screen, the field is not displayed.

The SLNO keyword cannot be used in a record format that contains the record-level keywords ASSUME, KEEP, USRDFN, SFL, or SFLCTL, or in a display file that contains the file level keyword PASSRCD.

However, the SLNO keyword may be used with several other DDS keywords:

- If the CLRL keyword is used with the SLNO keyword and the CLRL keyword specifies a number of lines to clear, clearing starts with the starting line number on the SLNO keyword.
- If you use the SLNO(*VAR) keyword with the OVERLAY keyword but without the CLRL keyword and then write the record several times, each time with a different starting line number, the previous record is deleted before the new record is displayed.
- If the SLNO keyword is used with the PUTQVR, PUTRETAIN, ERRMSG, or ERRMSGID keyword in effect, the system checks the starting line number to

determine if the previous output operation to the record had the same starting line number:

- If the starting line number is the same, the action specified by the PUTOVR, PUTRETAIN, ERRMSG, or ERRMSGID keyword is performed.
- If the starting line numbers are not the same, the PUTOVR, PUTRETAIN, ERRMSG, or ERRMSGID keyword is ignored, and the record format is displayed with the lines adjusted by the new value.

The following DDS shows an example of using the SLNO(*VAR) keyword:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R ORDET
A
A          1 36'ORDER ENTRY'
A          3 2'Enter customer number:'
A          CUST          5  B  +2
A          5 2'Enter order number:'
A          ORDNBR        6  B  +2
A          7 2'ITEM NUMBER'
A          7 18'DESCRIPTION'
A          7 44'QUANTITY'
A          R LINITM
A          OVERLAY
A          SLNO(*VAR)
A          CLRL(*NO)
A          ITEM          6 00 9 2
A          DESCRP        20 0 9 18
A          QTYORD         3 00 9 44
A          R INPFMT
A          OVERLAY
A          23 2'Enter item number:'
A          ITMNBR         6 0I  +2
A          +5'Enter Qty:'
A          QTY            3 0I  +2

```

*Figure 3-4. Sample DDS Source Showing Use of the SLNO(*VAR) Keyword*

In this example, the record format ORDET contains the prompt for an Order Entry display. When the user enters a customer number and an order number, the following occurs:

1. The program writes the record format INPFMT to the display, which allows the user to enter an item number and quantity ordered.
2. After the user enters the item number and the quantity, the program retrieves the description of the item from a file and writes the record format LINITM to the display.
3. The program writes the INPFMT record format to the display to allow the user to enter another item number.

The design of this display allows the user to enter the item number and quantity on the same line. As a line item is entered, the program uses the LINITM record format to build the order on the display. The SLNO(*VAR) keyword is used so the program can add a line to the display each time the LINITM record format is written. The CLRL(*NO) keyword has to be specified on the LINITM record format so that the previous record is not deleted when a new record is written.

When the LINITM record format is first written to the display, the value of *VAR is 1 so the fields are displayed on line 9. On each successive output operation to this record format, the program adds 1 to the starting line number so that a new line item is added to the display.

After the user enters two item numbers and quantities, the display looks like this:

ORDER ENTRY		
Enter customer number: 34785		
Enter order number: 1J2340		
ITEM NUMBER	DESCRIPTION	QUANTITY
96321	Pliers	115
86768	Saws	125
Enter item number: Enter Qty:		

The SLNO keyword is most efficient when you want the user to always enter data on the same line and yet build a display of previously entered records, as shown in the preceding example. However, for a typical inquiry function where you want to display more than one record at a time, the use of a subfile is more efficient.

Clearing a Specified Number of Lines

To clear a certain number of lines on the screen before you write a record format to the screen, use the clear lines (CLRL) keyword. You can specify the CLRL keyword even when the record contains no fields that are displayed. Clearing begins with the starting line number, and the value specified on the CLRL keyword determines the number of lines to be cleared (any value from 1 to 27). The starting line number is determined as follows:

- If the SLNO keyword is not specified, the field locations determine the starting line number.
- If the SLNO(nn) keyword is specified, nn is the starting line number.
- If the SLNO(*VAR) keyword is specified, the starting line number defaults to 1 at the time the display file is created and can be changed by the application program at the time it is run.


You can also specify the following values to clear specific lines:

Value	Lines Cleared
*END	All lines from the starting line to the end of the display
*NO	Only the lines of the display that are used by the overlapping record format

***ALL** All lines of the display. Since the default action is to clear all the lines of the screen, you do not normally have to specify CLRL(*ALL) unless you also specify a DDS keyword, such as USRDSPMGT, that changes this default.

Note: When you use the CLRL keyword, you should specify *YES for the RSTDSP parameter on the CRTDSPF or CHGDSPF command; otherwise, data on the display may be lost if the file is suspended.

You can use the CLRL(*NO) keyword to prevent an overlapped record from being deleted when the overlapping record is written to the display. If you use this keyword, any records being displayed that are to be overlapped are not deleted from the screen; the new record overlays them entirely or partially. There is a performance advantage to using CLRL(*NO) if you have a display that contains constants and data that is repeatedly sent to the screen. By sending the constants as a separate format and by using CLRL(*NO) for the format containing only the data, you can reduce the time required to send the record format to the display. For example:



If CLRL(*NO) is specified on record format C, all fields of record format B not overlapped by C remain on the screen when record format C is written to the screen. If the OVERLAY or PUTOVR keyword were used for this same situation, record format B would be deleted when record format C is written to the screen because record format C overlaps record format B.

The following considerations apply to the CLRL keyword when used with other DDS keywords:

- If the CLRL keyword is specified in a record format with input-capable fields, any input-capable fields in the overlapped records are no longer input-capable. Fields in all other record formats that are not overlapped remain input-capable. If you do not want these fields to remain input-capable, you should use the PROTECT keyword on the record format along with the CLRL(nn) keyword.
- Records with the CLRL keyword and with no input-capable fields are assumed to be at line 0. Thus, if the CLRL(nn) keyword is specified in a record format that has no input-capable fields, all records already on the display remain on the display and their input-capable fields remain input-capable. Because records that start at line 0 are not known to the system, the ROLLUP and ROLLDOWN keywords do not work for these records. Also, these records may not be cleared completely when they are overlapped by other records that have the OVERLAY keyword specified. The lines needed for the overlapping record

are cleared whereas the lines not needed for the overlapping record remain on the screen.

- The CLRL(nn) keyword is not allowed in a record format with the record-level keywords ASSUME, KEEP, USRDFN, SFL, or SFLCTL, or in a display file with the file level keyword PASSRCD.
- The CLRL(nn) keyword is ignored if either the ERRMSG or ERRMSGID keyword is in effect.
- If the CLRL(nn) keyword is used and the PUTOVR or PUTRETAIN keyword is in effect, the clearing of lines may conflict with the PUTOVR or PUTRETAIN function. The PUTOVR or PUTRETAIN keyword requires that the fields being overridden be on the display whereas the CLRL(nn) keyword may clear those fields first. If a record becomes unavailable for input because of the CLRL(nn) keyword, the input-capable fields remain input-capable if the PUTOVR keyword is in effect. However, the system issues a message if the program attempts to read such a record. Although the CLRL(nn), CLRL(*NO), and CLRL(*END) keywords imply the OVERLAY keyword, the following example illustrates the differences between the CLRL and OVERLAY keywords:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R RECORD1
A          FLD1          10  I  4  5
A          FLD2          10  I  5  5
A                                     5 21'Enter employee number'
A          R RECORD2A
A          FLD3          1  B  5  2
A                                     6 2'Required field'
A                                     7 2'Enter 1, 2, or N'
A          FLD4          19  0  8  2
A          R RECORD2B
A          FLD5          1  B  5  2
A                                     6 2'Required field'
A                                     7 2'Enter 1, 2, or N'
A          FLD6          19  0  8  2
A          R RECORD3
A          FLD7          10  0  8 15
A          .
A          .
A          .
A          FLD8          10  B 12  4
A          R RECORD4
A          FLD9          42  I 11  2
A                                     CLRL(*NO)

```

Figure 3-5. Sample DDS Source Showing Difference between CLRL and OVERLAY

The following results occur if the program performs the output operations on the record format in the following order:

Table 3-4. Results from CLRL Example

Order of Record Formats	Results
RECORD1 RECORD3 RECORD2A	Lines 4 through 12 are deleted when RECORD2A is written to the display because RECORD2A overlaps RECORD1 and RECORD3, and only the OVERLAY keyword is specified for RECORD2A.
RECORD1 RECORD3 RECORD2B	Lines 5 through 8 are cleared before RECORD2B is written to the display because the CLRL(4) keyword is specified. FLD1 in RECORD1 and any input-capable fields in RECORD3 (lines 9 through 12) remain on the screen but are no longer input-capable because part of RECORD1 and RECORD3 is overlapped by RECORD2B.
RECORD1 RECORD3 RECORD4 RECORD2A	RECORD1 remains on the screen when RECORD3 is written to the screen because the OVERLAY keyword is specified in RECORD3. When RECORD4 is written to the screen, it uses part of line 11, which is also used by RECORD3, and because CLRL(*NO) is specified in RECORD4, RECORD3 remains on the screen. However, the system is no longer aware that RECORD3 is on the screen so when RECORD2A is written, only lines 4 through 8 are cleared; the part of RECORD3 below line 8 remains on the screen.

Rolling Data between Two Lines on a Display

If you are using a high-level language program, you can roll the data between two lines on the display up or down by specifying the allow roll (ALWROL) keyword. The lines vacated by the rolled data are set to nulls and another record format can be written to those lines.

In your program, you must specify the following:

- *The starting line number and the ending line number of the lines to be rolled.*
The start and end line numbers define a window on the screen.
- *The number of lines to be rolled.* If the number of lines to be rolled is positive, the data is rolled up. If the number of lines to be rolled is negative, the data is rolled down.
- *Whether the roll is to be up or down.*

In the window, the lines of data are rolled up (or down) by the number of lines you specified in your program. The data rolled off the window is gone. The input-capable fields of any record format partially or completely within the window are no longer input-capable. After the roll, your program cannot issue an input operation to any record format within the window.

The following example shows a display before a program-controlled roll occurs, and the same display after a program-controlled roll occurs. The following is specified in the program:

- The starting line number is 8
- The ending line number is 18
- The number of lines to be rolled down is 6.

Display before the Roll Operation

UPDATE CUSTOMER ORDER RECORD	Line 1	} Record format 1
To end this program, press CF1	Line 3	
Enter your operator number: _____	Line 8	
Enter customer number: _____	Line 10	
Press CF3 to display option menu	Line 12	

RSLH165-0

Display after the Roll Down Operation

UPDATE CUSTOMER ORDER RECORD	Line 1	} Unchanged
To end this program, press CF1	Line 3	

Item number ordered: _____	Line 9	} Record format 2
Quantity ordered: _____	Line 11	

Enter your operator number: 25	Line 14	} Line 16 Line 18
Enter customer number: 12345	Line 16	
Press CF3 to display option menu	Line 18	
	Previous lines 8 through 12 after being rolled down	

RSLH171-0

The ALWROL keyword cannot be used with the file level keyword PASSRCD or with the following record-level keywords: KEEP, ASSUME, USRDFN, SFL, or SFLCTL.

If the ERRMSG, ERRMSGID, PUTOVR, or PUTRETAIN keyword is in effect for the same output operation in which the ALWROL keyword is in effect, the system issues message CPF5014. If an ERRMSG, ERRMSGID, PUTOVR, or record level

PUTRETAIN keyword is not in effect, the message is not issued. However, if the PUTRETAIN keyword is specified at the field level with option indicators, the message (CPF5014) is issued if the option indicators for the PUTRETAIN keyword are on or off.

Overriding the Attributes or the Content of a Field

To send only some of the data and attributes of a record to the display, use the following keywords:

- Put with explicit override (PUTOVR)
- Override data (OVRDTA)
- Override attribute (OVRATR)

By sending less data or attributes, you can shorten the response time at the display, especially for remotely attached displays.

When the PUTOVR keyword is specified, the following occurs:

- The display attributes are overridden for those fields with the OVRATR keyword in effect.
- The data content is overridden for those fields with the OVRDTA keyword in effect.
- The output operation functions as if the OVERLAY keyword were also in effect, even if the OVERLAY keyword is not specified.

The PUTOVR keyword cannot be specified in a record format that contains the PUTRETAIN keyword nor can it be used for subfile records.

The display attributes that can be overridden by the OVRATR keyword are:

CHECK(ER)	End of Record
CHECK(ME)	Mandatory enter
DSPATR(MDT)	Set on modified data tag
DSPATR(PR)	Protect
DSPATR(BL)	Blink
DSPATR(CS)	Column separator
DSPATR(HI)	High intensity
DSPATR(ND)	Nondisplay
DSPATR(PC)	Position cursor
DSPATR(RI)	Reverse image
DSPATR(UL)	Underline
DUP	Dup key capable

The following is an example of the PUTOVR keyword.

```

|...+.1...+.2...+.3...+.4...+.5...+.6...+.7...
A          R ITMRVW
A
A          PUTOVR
A          1 35'ITEM REVIEW'
A          3 2'Item number:'
A          ITMNBR          5  B  +2
A          5 2'Item description:'
A          ITMDSC          20  +2
A 10          OVRDTA
A          7 2'Item price:'
A          ITMPRC          8  2  +2
A 15          OVRDTA
A          9 2'Warehouse location:'
A          WHSLOC          3    +2
A 20          OVRDTA
A          11 2'Quantity on hand:'
A          QTYOH          5  0  +2
A 25          OVRDTA
A          OVRATR
A N25 30      DSPATR(HI)

```

Figure 3-6. Sample DDS Source Showing Use of the PUTOVR Keyword

The DDS describes a display that allows the user to enter an item number, and to review the item description, the item price, the warehouse location, and the quantity on hand:

1. On the first output operation, all fields are sent to the display, and all option indicators are off. The PUTOVR keyword is ignored because the record is not already on the screen. On the first output operation, the current field values in the program are displayed for the output fields. If your program has not set any of these fields, the values will be whatever the high-level language used to initialize the output buffer.

If an output-capable field must always have a specific value on the first output operation, you can use the DFT or DFTVAL keywords to initialize the field to that value. When used on an output-capable field with the PUTOVR and OVRDTA keywords the DFT keyword causes the system to place the default value rather than the program value on the display when the record is first placed on the display.

2. The user enters an item number. The program sets on indicators 10, 15, 20, and 25 and issues a write-read operation to display the output fields. On the write operation, the PUTOVR keyword is in effect because the record is already on the screen. Because the OVRDTA keyword is specified on the ITMDSC, ITMPRC, WHSLOC, and QTYOH fields and because their option indicators are on, these fields are the only data sent to the display.

If the user enters another item number and the data for a field already displayed does not change, the program sets off the option indicator and does not display that field again. For example, assume that for the second item number, the WHSLOC is the same as for the first item number. On the output operation to display the information for the second item number, the program sets off indicator 20. Therefore, the only fields sent to the display are ITMDSC, ITMPRC, and QTYOH because indicators 10, 15, and 25 are on.

For the QTYOH field, the program can change the attributes for the field without changing the data by setting off indicator 25 and setting on indicator 30 before the output operation.

You can use the option indicators on the OVRDTA keyword to control which fields are sent to the display. If no option indicators are used, all fields with the OVRDTA keyword specified are sent to the display on each output operation because the OVRDTA keyword is in effect when the PUTOVR keyword is in effect. In the preceding example, if no option indicators were used, all four fields would be sent to the display on each output operation. You can also use the same indicator to control more than one field.

An alternative design for this same application is to use two record formats and send the constants to the display in one record format and the variables in the other record format. You would have to use the CLRL(*NO) keyword to prevent the record format containing the constants from being erased. However, if the record format is already on the display, the use of the PUTOVR keyword provides the most efficient approach.

The following examples illustrate how to use the PUTOVR keyword for efficient coding:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R PROMPT
A
A          CF03(91 'Return')
A          PUTOVR
A          ERASEINP
A          OVERLAY
A          1 28'Efficient Coding Example'
A          3 2'FLD1'
A          FLD1          5  I 3 7
A          FLD2          5  5 7
A          FLD3          5  7 7
A          FLD4          5  9 7
A          FLD5          5 11 7DFT('ABCDE')
A          OVRDTA
A          DSPATR(HI)
A          11 2'FLD5'
A          13 2'Constant 1'
A          OVRATR
A          DSPATR(BL)
A          15 2'Constant 2'
A          OVRATR
A          DSPATR(ND)
A          17 2'Constant 3'
A          OVRATR DSPATR(RI)

```

Figure 3-7. Sample DDS Source Showing Efficient Use of PUTOVR Keyword

In the preceding example, the following happens:

1. If the record format is not currently on the display, the PUTOVR, OVRATR, and OVRDTA keywords are ignored when the record format is displayed. On subsequent output operations when the record format is already on the display and the PUTOVR keyword is in effect, only the fields or constants defined with the OVRATR or OVRDTA keyword are sent to the display. The ERASEINP keyword is used because it is the most efficient way to clear all input fields, and the OVERLAY keyword is used because it is required with the ERASEINP keyword.
2. FLD1 is an input field that is cleared each time the record format is displayed.
3. FLD2 is sent to the display each time the record format is displayed because its associated OVRDTA keyword is unconditionally specified.
4. FLD3 is sent to the display on the first output operation. On subsequent output operations, FLD3 is not sent to the display unless indicator 15, which is used to condition the OVRDTA keyword, is on.
5. FLD4 is sent to the display on each output operation because its associated OVRDTA keyword is unconditionally specified. When the OVRDTA keyword is in effect, the attributes for the field are always sent to the display. Indicator 16 is used to control the DSPATR(HI) keyword for FLD4.
6. On the first output operation, the default value of ABCDE appears in FLD5. On subsequent output operations, a value from the program is displayed in FLD5 because its associated OVRDTA keyword is unconditionally specified. Indicator 17 is used to control the DSPATR(HI) keyword for FLD5.
7. *Constant 1* is always displayed, but it is only sent to the display on the first output operation. However, the attributes for the field are sent to the display each time the record format is written, and option indicator 18 is used to control whether the field blinks.
8. *Constant 2* is sent to the display only on the first output operation. However, the attributes for the field are sent to the display each time the record format is written, and if option indicator 19 is off, *Constant 2* will not be displayed.
9. *Constant 3* is sent to the display only on the first output operation. However, the attributes for this field are not sent to the display on subsequent output operations unless indicator 20 is on. If option indicator 20 is on when an output operation is done, *Constant 3* is displayed in reverse image, and it will continue to appear in reverse image regardless of the status of indicator 20 on subsequent output operations.

The following example shows how the PUTOVR keyword can be used for an application in which the user enters some information common to a group of records and then repeatedly enters detailed information relating to specific records in the group.

	1	2	3	4	5	6	7
A		R	HEADING			TEXT('Header Display')	
A						SETOF(88 'ERASEINP CTL')	
A						CF03(91 'Return')	
A				1	2	'HEADING INFORMATION'	
A						DSPATR(HI)	
A				1	60	'CF3-End of Program'	
A				2	60	'CF2-New heading'	
A		HDING		5	I	+2	
A		R	DETAIL			TEXT('Detail display')	
A						OVERLAY	
A						PUTOVR	
A						PROTECT	
A	88					ERASEINP	
A						CF02(92 'New header')	
A				8	2	'DETAIL DISPLAY'	
A						DSPATR(HI)	
A				10	2	'Input'	
A		FLDA		5	I	+2	
A				12	2	'Output'	
A		FLDB		5		+2DFT(' ')	
A						OVRDTA	

Figure 3-8. Sample DDS Source Showing Another Use of PUTOVR Keyword

In the preceding example, the following happens:

1. The program displays the HEADING record format, and then performs an input operation to the record format to receive the HDING field as input. The SETOF keyword in the HEADING record format sets off indicator 88, which is used to condition the ERASEINP keyword in the DETAIL record format.
2. The program then displays the DETAIL record format. Because the OVERLAY keyword is in effect, the HEADING record format remains on the display. The PROTECT keyword is also in effect so the input field (HDING) in the HEADING record format is protected. Therefore, the user cannot change this field when the DETAIL record format is displayed.
3. The ERASEINP keyword is conditioned by option indicator 88. Because indicator 88 is off the first time the DETAIL record format is displayed, the ERASEINP keyword is not in effect. On subsequent output operations, indicator 88 is set on and the ERASEINP keyword is in effect. Therefore, FLDA is cleared on subsequent output operations. The option indicator is used on the ERASEINP keyword so that it is not in effect the first time the DETAIL record format is displayed. Because the ERASEINP keyword is processed before the PROTECT keyword, it would clear the HDING field in the HEADING record format if it were in effect the first time the DETAIL record format is written.
4. FLDB is an output field that is sent to the display on each output operation because the OVRDTA keyword is specified unconditionally. The DFT keyword with a value of blanks is used so the field will not contain any data the first time the DETAIL record is displayed for a group.

Erasing All Unprotected Input and Output/Input Fields on the Display

To erase all unprotected input-capable fields, use the erase input (ERASEINP) keyword. The ERASEINP keyword can only be used with the OVERLAY keyword.

To erase all unprotected input-capable fields that have their modified data tags on, specify *MDTON for the ERASEINP keyword. To erase all unprotected input-capable fields whether their modified data tags are on or not, specify *ALL for the ERASEINP keyword.

The ERASEINP keyword can improve response time because it clears fields rather than sends blanks to the display. If the fields erased at the display do not have their modified data tags set on for the next read operation, data is returned for those fields from the input save area. This is data saved by the system from the previous return of the field from the display station.

You can use the INZINP keyword at the record level with ERASEINP(*ALL) and PUTOVR to initialize the input save area without sending data for the cleared fields to the display.

Resetting Modified Data Tags Associated with Records on the Display

To reset the modified data tags, use the modified data tag off (MDTOFF) keyword. The MDTOFF keyword, which can only be used with the OVERLAY keyword, is processed before the next record is displayed.

To reset only the modified data tags of the unprotected fields, specify *UNPR for the MDTOFF keyword. To reset the modified data tags of all input-capable fields, specify *ALL for the MDTOFF keyword.

Keeping a Record or Field on a Display

The PUTRETAIN keyword is used to reduce the number of characters sent to the display. This keyword can only be used with the OVERLAY keyword and can be used to change only the display attributes of a field. Except for not sending data, all other functions are supported when the PUTRETAIN keyword is specified.

Using the PUTRETAIN keyword at either the record format level or the field level can cause fields from this record which were previously written to the display to remain on the display even if they are not selected for this write operation. To avoid this, you can use the PUTRETAIN keyword at the field level and define the field twice: once with option indicators as you want it to appear in the display, and once with no option indicators and as a constant with a value of blanks. If the first field is not selected, the second field is. The second field is displayed so the blanks erase the contents of the field that is not selected.

Note: The ERRMSG and ERRMSGID keywords function as if the PUTRETAIN keyword were specified at the record format level. That is, no fields are sent to the display, no field attributes for other fields are changed, and no command keys are changed when the ERRMSG and ERRMSGID keywords are in effect.

The following is an example of the PUTRETAIN keyword used at the record format level. The following DDS describes a student search menu having three options.

The option selected is highlighted. For example, if option 1 is selected, the character string *1. By number* is highlighted.

```

|...+. ...1...+. ...2...+. ...3...+. ...4...+. ...5...+. ...6...+. ...7...
A          R SELECT                                OVERLAY
A          PUTRETAIN ERASEINP
A N44      1 2'STUDENT SEARCH MENU'
A N44      3 10'1. By number'
A 10      DSPATR(HI)
A N44      4 10'2. By name'
A 11      DSPATR(HI)
A N44      5 10'3. By address'
A 12      DSPATR(HI)
A N44      10 2'Select the number of the item to  +
A          search by:'
A          INPUT          1  I 10 47
A 44      DSPATR(RI)

```

Figure 3-9. Sample DDS Source Showing Use of the PUTRETAIN Keyword

The following happens:

1. On the first output operation, all fields are sent to the display, and all option indicators are off. The PUTRETAIN keyword is ignored because the record is not already on the display.
2. The user selects item 1, 2, or 3. When the program receives the input, it sets on indicator 10, 11, or 12, depending on which item is chosen. If anything other than item 1, 2, or 3 is chosen, the program sets on indicator 44.

On the next output operation, field 1, 2, or 3 is highlighted, or the input field is in reverse image, depending on which indicator is on.

The data for all fields is not resent to the display but the field attributes are resent. No data is sent for constants. To resend attributes for each output field or constant, 4 bytes are needed. To resend attributes for each input-capable field, 9 bytes are needed. By using the PUTRETAIN keyword, you reduce the number of characters sent to the display by 96, from 138 to 42. (These numbers do not include protocol control characters needed to frame data.)

The ERASEINP keyword causes the user's selection to be erased.

The following is an example of the PUTRETAIN keyword used at the field level. Here, the PUTRETAIN keyword is used to keep input that is not valid and to reduce the number of characters sent to the display. The following DDS describes a display containing an item's name, color, shape, and size, and asks for quantity. The user can change the values for color, shape, and size.

		1	2	3	4	5	6	7
A	R CHANGE					OVERLAY		
A					1	2'CHANGE MENU'		
A N43					3	2'Change the underlined fields to		+
A						change the description.'		
A					4	2'Item:'		
A	ITEM	20	0	4	12			
A 44						PUTRETAIN		
A					5	2'Quantity:'		
A	QTY	4Y	0I	5	12			
A 44						PUTRETAIN		
A 09						DSPATR(BL PC)		
A					6	2'Color:'		
A	COLOR	10	B	6	12			
A 44						PUTRETAIN		
A 10						DSPATR(BL PC)		
A					7	2'Shape:'		
A	SHAPE	10	B	7	12			
A 44						PUTRETAIN		
A 11						DSPATR(BL PC)		
A					8	2'Size:'		
A	SIZE	10	B	8	12			
A 44						PUTRETAIN		
A 12						DSPATR(BL PC)		
A 44					9	2'Choice:'		
A 44	CHOICE	20	0	9	12			
A 15					9	12'		

Figure 3-10. Sample DDS Source Showing Use of the PUTRETAIN Keyword

The following happens:

1. On the first output operation, all indicators are off, so all the constants and the fields except CHOICE and the constant field following CHOICE are sent to the display.
2. The user enters a quantity. The program sets on indicator 43. When the next output operation occurs, indicator 43 prevents the second constant field from being resent.
3. When the user is to enter the quantity for another item, the program issues another output operation. The attributes for the fields QTY, ITEM, COLOR, SHAPE, and SIZE are sent to the display. Field selection prevents the CHOICE field from being sent to the display.

At least one field, in this case QTY, must be kept to prevent the entire record area from being erased.

4. If the user enters a quantity, color, shape, or size that is not valid, indicator 44 is set on so that the input fields (QTY, COLOR, SHAPE, and SIZE) are not erased and so that the output field CHOICE is sent to the display. In addition, the appropriate indicator, 9, 10, 11, or 12, is set on so that the input field in error blinks and the cursor position is below the field. (The CHOICE field would show the user valid choices for the field in error.)
5. The CHOICE field and a constant field of blanks are defined for the same location. After the user enters valid data, indicator 15 is set on, indicator 44 is set off, and the constant field initializes the CHOICE field to all blanks.

Deferring the Write Operation Until a Read Request is Made

The DFRWRT parameter on the Create Display File (CRTDSPF) or Change Display File (CHGDSPF) command allows you to specify how the system is to handle write operations. If you specify DFRWRT(*NO), the program does not regain control until the write operation has displayed the data and updated the input/output feedback area.

If you specify the default of DFRWRT(*YES) for the file, the program regains control after the output record is processed. The program can then use the record area where the output was stored to start processing the next write or write-read operation. The data is actually sent to the display only when a read or write-read operation is issued or when the FRCDTA DDS keyword is in effect for a write-only operation.

Using DFRWRT(*YES) on a display file improves systems performance; however, DFRWRT(*YES) should not be used in the following circumstances:

- If you want to find out immediately if the write operation was successful. An error associated with a write operation for a file with DFRWRT(*YES) specified is issued only when the data is actually sent to the display.
- If the time between the write operation and the read or write-read is long. For example, if the program does several database operations after the write operation (before it issues a read or write-read operation), the user will not see the data while the database operations are performed.
- If the file is closed after the write-only operation and the KEEP keyword is not specified. If the display file has the DDS keyword KEEP specified in any of its records, the data accumulated from the write-only operation is displayed when the file is closed. However, if the KEEP keyword is not specified, the data may never be displayed.

The DFRWRT parameter has no effect on the following:

- Write operations using user-defined data streams
- Write operations to display files that use program-described data
- Record formats for which the FRCDTA DDS keyword is in effect

Specifying Default Values for Fields

Both DFT and DFTVAL keywords are used to specify the default values to be displayed for fields. However, there are differences between the way the two are used.

The DFT keyword can be used with constant, input, output, and output/input fields and cannot be optioned. When it is used with output or output/input fields the OVRDTA and PUTOVR keywords must also be specified. If the record is not on the display, this combination of keywords will cause the default value to be placed on the screen. If the record is already on the display, the PUTOVR keyword is in effect and the data from the program appears on the display rather than the default value.

The DFTVAL keyword can be used only on output and output/input fields and can be optioned. If it is in effect on an output operation, the value from the keyword is placed in the field, rather than the value from the program. If the record is on the display and the PUTOVR and OVRDTA keywords are in effect, the program value is used rather than the default value.

The DFT and DFTVAL keywords may not be specified on the same field.

Indicating Which Mode to Display Records

Some display stations, for example the 3180-2 display station, support an alternate screen size. You can specify this alternate size using the DSPMOD keyword. The DSPMOD keyword indicates, for a particular record, which mode is used to display the record. Any record that does not have the DSPMOD keyword specified for it is displayed in the default display mode. The default display mode is the first of the *DS3 or *DS4 display sizes on the DSPSIZ keyword.

The DSPMOD keyword is only valid when both *DS3 and *DS4 are specified on the DSPSIZ keyword. This keyword is valid only at the record level. Option indicators are allowed. The DSPMOD keyword may not be duplicated in a record.

Note: The capability to display in 27 by 132 mode is allowed on 3180-2, 3197, 3477 Models FA, FC, FD, FE, FG, FW, and 3487 Models HE, HD, HW, HC display stations attached to a local display station controller, or remotely attached to a 5294 or 5394 controller. The DSPMOD keyword is ignored unless these controllers are used.

For example, the following DDS would display RECORD1 in 27 by 132 mode, and RECORD2 in 24 by 80 mode (the default mode set up by the DSPSIZ keyword). RECORD3 will be displayed in 27 by 132 mode if option indicator 03 is on, or in 24 by 80 mode if option indicator 03 is not on.

	...	1	...	2	...	3	...	4	...	5	...	6	...	7	...
A															DSPSIZ(*DS3 *DS4)
A				R		RECORD1									DSPMOD(*DS4)
A				R		RECORD2									
A				R		RECORD3									
A	03														DSPMOD(*DS4)

Figure 3-11. Sample DDS Source Showing Use of the DSPMOD Keyword

The use of the DSPMOD keyword can cause the display mode to be changed dramatically. Caution should be used when specifying the DSPMOD keyword. When a record with DSPMOD active causes the mode to be changed, all records currently on the display are cleared and deleted from the active record table. The record with DSPMOD active is then sent to the display. The mode for this record is maintained on the display as long as the DSPMOD keyword is active. Setting DSPMOD off or a write operation to another record without DSPMOD causes the display mode to be placed back in the primary display screen size for the display station.

Using the previous sample DDS source, the DSPMOD keyword gives the following results if records are written to the screen in the following order:

- RECORD1 is displayed in *DS4 mode.
- The display screen is cleared and RECORD2 is displayed in *DS3 mode.
- If indicator 03 is off, RECORD3 is displayed in *DS3 mode. RECORD2 remains on the display if the OVERLAY keyword is specified.
- If indicator 03 is on, RECORD2 is cleared and RECORD3 is displayed in *DS4 mode.

Note: When changing display modes, the displayed subfile data is removed from the display. However, the subfile data is not cleared from the subfile table.

The following keywords are ignored if the display modes have changed:

Table 3-5. Keywords Ignored If Display Modes Are Changed

Keywords	Additional Information
ALWROL	When a record is not on the screen, it cannot be rolled.
ASSUME	The records with the ASSUME keyword remain on the screen when the file is opened. When the display modes change, the records on the screen are cleared. This is similar to specifying the ASSUME keyword without the OVERLAY keyword. The display size of the file with the KEEP keyword must equal the display size of the file with the ASSUME keyword.
CLRL	All lines will be cleared by a change in display mode.
ERASEINP/INZINP ERRMSG ERRMSGID KEEP OVERLAY PROTECT PUTOVR	When the display modes change, the record is displayed with PUTOVR not in effect, even if the record was on the screen before the display modes changed.
PUTRETAIN SFLMSG SFLMSGID	—

Positioning the Cursor after an Output Operation

You can specify where you want the cursor positioned after an output operation by using the CSRLOC or DSPATR(PC) keyword.

On the record-level keyword CSRLOC, you can specify the names of two 3-character hidden fields that contain the exact line and position for the cursor location. With the CSRLOC keyword, you can position the cursor outside the record you are displaying.

The field-level keyword DSPATR(PC) positions the cursor at the first position of the field after the record is written. However, if the OVERLAY keyword is specified at the record level, the cursor position may be lost after subsequent write operations.

Note: The cursor is not positioned if the keyboard is unlocked before the output operation.

If both the CSRLOC and DSPATR(PC) keywords are specified, the cursor is positioned by the CSRLOC keyword. If several fields have DSPATR(PC) keyword specified, the cursor is positioned at the first field for which the DSPATR(PC) keyword is specified.

If a cursor location is not specified on an output operation and there is no other record on the display with a cursor location specified, the cursor is positioned at the first input-capable field on the screen. If there was a record on the display that had the cursor position specified then the cursor remains in the specified position. If there is no input-capable field, the cursor is positioned in the upper-left corner of the screen.

Other DDS functions can affect the write operation. For a write operation to a user-defined data stream (USRDFN keyword), the functions performed are determined by the user-supplied controls.

Returning the Cursor Position to an Application

You can determine where the cursor was positioned on input by using the RTNCSRLOC (return cursor location) keyword. This keyword returns the name of the record and the name of the field on which the cursor was located on input. Optionally, the keyword can also return the position of the cursor within the field. The cursor record name, field name (and, optionally the position within the field) are returned in hidden fields specified as parameters on the RTNCSRLOC keyword.

The fields specified for the parameters are defined in the record format and must be 10 character (A in position 35) hidden fields (H in position 38) with different names.

The field specified for the cursor position is defined in the record format as a signed numeric (S in position 35) with a length of 4 with zero decimal places. Also, it must be a hidden field (H in position 38).

Returning the Cursor Position Within a Subfile to an Application

On input, you can determine where the cursor is located in a subfile by using the SFLCSRNRN (subfile cursor relative record number) keyword. The relative record number on which the cursor is positioned is returned in the hidden field specified as the parameter on the keyword. The field must be defined in the record format as a signed numeric (S in position 35) with a length of 5 with zero decimal places. Also, it must be a hidden field (H in position 38).

Returning the Mode of a Subfile to an Application

You can use the SFLMODE (subfile mode) keyword to determine whether the subfile was in folded or truncated mode on input. The mode parameter is required. The SFLMODE keyword is only valid for subfile control records and the SFLCTL keyword must be specified.

The field specified for the mode parameter is defined in the record format as a 1 character (A in position 35) hidden field (H in position 38). The field is returned with a value of 0 if the subfile is folded and with a value of 1 if the subfile is truncated. If SFLDROP (subfile drop) or SFLFOLD (subfile fold) is not specified on the SFLCTL (subfile control) record, the value is always returned as 0.

Initializing Output/Input Fields

Device support saves all data read from input-capable fields for records currently on the display in a save area. The output/input fields within this save area are updated on output operations.

For output operations, the following happens:

- Input-only fields are initialized to zeros (numeric fields), blanks (character fields), or a default value (DFT keyword) from the display file.
- Output/input fields, hidden fields, and program-to-system fields are initialized to the contents of the output buffer. If this output operation is caused by the initialize record function (INZRCD keyword), no output buffer is available. Output/input fields and hidden fields are initialized similar to input-only fields. Output/input fields are input and output capable.

- Output-only fields are not part of the input buffer unless they are part of a subfile record, in which case they are saved as if they were output/input fields.
- All response indicators for this record are set off.

Note: For input-capable fields, if the PUTRETAIN or ERASEINP keyword is in effect, the save area for the field remains unchanged.

Neither the input nor the output buffer is changed during write operations.

Inviting Input to the Display

The **invite operation** is used to send a request for input to a display station and return to the program without waiting for the input to arrive. This allows a program to request input from one or more display stations but continue processing without waiting for any of the display stations to respond. When the program is ready to process the input, the data can be received from any of the invited display stations by performing a read-from-invited-devices operation.

The invite operation is done by performing a write operation using a record format with the INVITE DDS keyword in effect. Refer to the appropriate high-level language manual to determine how to perform a write operation and how to use indicators to control the INVITE DDS keyword.

Once a display station is invited, the valid operations to receive data from the display station are the read-from-invited-devices operation and the read(wait) operation directed to a specific display station. Cancel invite is also a valid operation to an invited display station.

Before a display station can be used for I/O operations in a multiple-device display file, it must be acquired to the file. A program can direct the invite operation to any display station currently acquired for the file.

If the multiple-device display file was created with DFRWRT(*YES) specified, an output operation with the INVITE DDS keyword optioned on will cause the output that has been postponed to be displayed on the screen before the display station is invited.

If you want to invite a display station but have no data to send to it, perform the output operation with a record format which contains the INVITE DDS keyword optioned on but has no output-capable fields.

Multiple-display station display files are supported in RPG/400*, COBOL/400*, C/400*, and CL.

Inviting Input from CL Programs: The invite operation is available directly to CL programs through CL commands:

- *WAIT(*NO) on RCVF and SNDRCVF Commands:*

WAIT(*NO) allows overlapping of I/O operations and the running program, requests for input from more than one display, and receiving input as it is available. This provides support equivalent to the invite operation.

On a read operation with the no-wait option, the system sends the request to the display and returns to the program. However, the requested record is not available when control returns. The purpose of this operation is to make the

display station eligible to send input data while the program performs other work.

To retrieve the record, issue a WAIT command. The WAIT command issues a read-from-invited-devices operation. The program waits until data is available from the display station or the WAITRCD time elapses. Then, the display station name and any input data are passed to the user program. If more than one read-with-no-wait operation has been issued (each to a different display) and more than one completes, the WAIT command processes only the first read-with-no-wait operation that is completed.

A WAIT command can be issued to process each of the other read-with-no-wait operations. They are processed in the order of completion.

When a record containing the INVITE keyword is sent to the display, the operation is handled as a write-read operation with a no-wait option. The INVITE DDS keyword is ignored on the write-read operation.

A write-read operation with a no-wait option is the same as a write followed by a read-with-no-wait.

- *ENDRCV Command:*

The ENDRCV command is used to end a request for input made with the WAIT(*NO) option. The ENDRCV command ends the input request even if data is available from the display station. If data is being sent by the display station when the ENDRCV operation is performed, the data is lost. If the display station is not invited, the application program is signaled with an error.

Reading Invited Input from the Display

The read-from-invited-devices operation provides a means of waiting for and receiving data from any one of the invited display stations. This method of inviting a display station and then reading from the invited display station is useful when the application must control the amount of time spent waiting for the user to respond. When the read-from-invited-devices operation is performed, the program waits for the time interval specified on the WAITRCD keyword of the CRTDSPF, CHGDSPF, or the OVRDSPF command. The wait can be ended in the following ways:

- *Data becomes available from an invited display station.* The display station name, the results of the operation, and any input data are passed to the program. When data has been received, the display station is no longer invited and must be invited again by an invite operation if more data is to be received from the display station by a read-from-invited-devices operation.
- *No-display station-invited signal.* Indicates that none of the display stations associated with the file are in the invited condition. Refer to the appropriate high-level language manual for information on how this will be communicated to the program.
- *Job-ended-controlled signal.* Indicates that the job that the program is running in is being ended with the controlled option through the End Job (ENDJOB), End System (ENDSYS), Power Down System (PWRDWN SYS), or End Subsystem (ENDSBS) command. Refer to the appropriate high-level language manual for information on how this will be communicated to the program. This occurs only once in a process no matter how many multiple-device display files are in use. All invited display stations remain invited.

- *No-invited-devices-have-data-available signal.* This occurs when no display stations associated with the file have data available, the WAITRCD time is *IMMED, and none of the previous conditions apply. The invited display stations remain invited. Refer to the appropriate high-level language manual for information on how this will be communicated to the program.
- *Time-out-on-wait-for-data-from-invited-devices signal.* This occurs when the WAITRCD value is a finite number of seconds, no data became available during that interval, and none of the previous conditions apply. Refer to the appropriate high-level language manual for information on how this will be communicated to the program. The invited display stations remain invited.

Also, COBOL/400 provides a means of performing the read-from-invited-devices operation as if WAITRCD(*IMMED) had been specified. See the COBOL/400 manuals for information on the NODATA phrase and its effect on the read-from-invited-devices operation.

Understanding the Read-From-Invited-Devices

When the program is ready to process input from one of the invited display stations, it can issue a read-from-invited-devices operation. This operation waits for a specified time for input to arrive from one of the invited display stations. The time limit can be specified when the display file is created and can subsequently be changed or overridden. If no invited display stations respond within the time limit, the program receives an indication that the time limit expired and can continue processing. If an invited display station responds within the time limit, the program can determine which display station responded and the record format used to process the data. The other invited display stations remain invited and can be sending data. The responding display station can also be invited again by another invite operation.

A read operation can also be directed to a specific display station. This operation will not complete until the specified display station responds with data. The display station need not be invited for the read operation, but, if it is, the program will wait for input and the display station is no longer invited.

- The read-from-invited-devices operation only accepts data from display stations which are currently invited.
- If more than one display station acquired to the display file has an invite outstanding, a read-from-invited-devices operation will return the next available record from one of the invited display stations. If records are received from more than one display station before the read-from-invited-devices operation, the other records will be kept for a subsequent read-from-invited-devices operation or for a subsequent read(wait) operation directed to a specific display station.
- When a display station has responded and the input is received by the read-from-invited-devices operation, that display station is no longer invited. It can be invited again by another invite operation but this should not be done until all the record formats on the display with input-capable fields have been read.
- A record format cannot be specified on the read-from-invited-devices operation. The record format returned from a display is the same as the last record format written to the display station.
- The timing function associated with the WAITRCD parameter may not force an end to the wait if the system is processing the Help key. In the following

cases, the read-from-invited-devices function will not end until the user exits from the help information:

- The system is displaying help that is defined by H specifications in the DDS for the display file.
- The system is displaying help for a message when the display station is the requester display station for the job and the display file specifies MAXDEV(1).

You can force message help to end when the WAITRCD time ends by specifying a value greater than 1 for the MAXDEV parameter on the CRTDSPF or CHGDSPF command.

Reading-From-Invited-Devices from CL Programs: The read-from-invited-devices operation is available directly to CL programs through CL commands. To retrieve the record, issue a WAIT command. The WAIT command issues a read-from-invited-devices operation. The program waits until data is available from the display station or the WAITRCD time elapses. Then, the display station name and any input data are passed to the user program. If more than one read-with-no-wait operation has been issued (each to a different display) and more than one completes, the WAIT command processes only the first read-with-no-wait operation that is completed.


A WAIT command can be issued to process each of the other read-with-no-wait operations. They are processed in the order of completion.

When a record containing the INVITE keyword is sent to the display, the operation is handled as a write-read operation with a no-wait option. The INVITE DDS keyword is ignored on the write-read operation.

A write-read operation with a no-wait option is the same as a write followed by a read-with-no-wait.

Reading Input from the Display

A **read operation** passes a record from the system to the program. The display file record format contains the information necessary for the system to handle the record. The user must perform a required action such as pressing the Enter key or a function key to pass the data to the system. The read operation results in the following:



For input operations, the following happens in the order given:

1. For an input-only operation, all response indicators for this record are set off and the read operation is issued.
2. Character fields received from the display are right- or left-justified and padded with blanks or truncated as necessary. The default is left-justify, which can be overridden using the AUTO or CHECK keyword.
3. Numeric fields received from the display have the following done to them:
 - a. If the field is negative, the zone portion of the units position is set to a D (see “Handling Negative Numeric Input Data” on page 3-39).
 - b. All nonnumeric characters are removed and the numeric characters are compressed.
 - c. Signed numeric fields are right-justified and numeric-only fields are decimal aligned.
 - d. The field is padded with zeros or truncated as necessary.
 - e. Field validation is performed.

All fields received from the display whether they are part of the selected record or not are handled in this way.

If any field validation errors are detected, a message is sent to the user so that the error can be corrected. This process is repeated until there are no longer any errors. The save area for the requested record is then copied into the input buffer.

Note: To process input data for a read operation with no record format name, display station support uses the last record written to the display that contains at least one of the following:

- Input-only fields
- Output/input fields
- Hidden fields

If no such format is on the display, display station support uses the last format written to the display that did not contain these kinds of fields, for example, an output-only record that specifies valid command keys. If no such record exists on the display, an error message is returned to the program.

A record does not have to be written to the display before it can be read by the program with the INZRCD keyword. The system does this the same way an application program performs an output operation with the exception of the following:

- For an output-only field, no user data is available so the field is initialized to blanks. If the field is edited, the editing is ignored. If the BLKFOLD keyword is specified, it is ignored.
- For an output/input field, no user data is available so the field is initialized to blanks. If the field is edited, the editing is ignored. The field actually contains null characters (hexadecimal zeros), which appear as blanks.
- For a constant or input-only field, the data does not normally come from the output buffer so the field appears the same as when the program displays it using a write operation.
- For a hidden field, the field is returned on a read operation as blanks (hex 40) if the field is a character field or zeros (hex F0) if the field is a numeric field.
- For a message, there is no message data so the field is ignored.
- The LOGOUT keyword is ignored.
- The ERRMSG and ERRMSGID keywords are ignored because the record is not already on the display.
- The SFLMSG and SFLMSGID keywords are ignored.

All other fields or keywords are processed as if they were selected on an output operation.

Unlocking the Keyboard while the Program Is Processing Data

The keyboard can be unlocked so that data can be entered into input fields while the program is processing previously entered input data with the UNLOCK keyword.

Normally, input fields are not erased until after the keyboard is unlocked. On a read operation, input fields are erased after the keyboard is unlocked only if the UNLOCK keyword is specified and the GETRETAIN keyword is not specified.

For the 5250 display station, the read operation with the UNLOCK keyword in effect results in the following:

1. The 5250 display station does a hardware validity check on the fields. If no errors are found, the following is done:
 - a. If the UNLOCK keyword is specified without the GETRETAIN keyword or if the UNLOCK(*ERASE) keyword is specified, all input-capable fields that are changed are cleared.
 - b. If the UNLOCK keyword is specified with the GETRETAIN keyword or if the UNLOCK(*MDTOFF) keyword is specified, all modified data tags (MDTs) are reset.
 - c. If the UNLOCK(*ERASE *MDTOFF) keyword is specified, all input-capable fields that are changed are cleared and their MDTs are reset.
 - d. The cursor is repositioned to the field where the user can enter the next record.
 - e. The keyboard is unlocked.
2. The system validity checks all the fields for all records on the display. If errors are detected, normal error retry is performed. A user could be typing into the next record when an error message is displayed.

Note: The error message could refer to data that is no longer on the display because the data was erased.

3. Control returns to the program.

Notes:

1. If an application program detects input errors and sends error messages to the display, the messages may refer to input that has been typed over.
2. If the CHANGE keyword is specified and either the UNLOCK keyword is specified without the GETRETAIN keyword or with the UNLOCK(*ERASE) keyword is specified, the associated response indicator is set on for the next input record.
3. When a read operation with the UNLOCK keyword (and without the GETRETAIN keyword) or the UNLOCK(*ERASE) keyword is used for a record while a subfile is on the screen, subfile records may be returned to the program on a subsequent get-next-changed operation to the subfile even though the user did not enter data into the subfile record. It is recommended that you use the UNLOCK(*ERASE *MDTOFF) keyword instead of the UNLOCK keyword (without the GETRETAIN keyword) or the UNLOCK(*ERASE) keyword. If you must use either of the latter, you should make sure that your high-level language program compares for blanks to handle the possibility that an unmodified field containing all blanks is returned to the program.

Keeping Input Data


Input data on a display can be kept after the user presses the Enter key with the GETRETAIN keyword. The GETRETAIN keyword can only be used with the UNLOCK keyword.

Setting an Indicator When Data Is Changed

A response indicator can be set on when data is entered into an input field or when data is changed in an output/input field with the CHANGE keyword.

Initializing Records and Unlocking the Keyboard—Diagram

The following diagram shows the effect of INZRCD and UNLOCK keywords on an input operation:



Note: Record formats A, D, and E occupy the same lines.

- 1** Record formats B, D, and C are erased if the OVERLAY keyword is not specified for record format A. Record format A is displayed with constants and initialized input fields. The keyboard is unlocked. The keyboard is locked after the user satisfies the get operation.
- 2** Record formats B, D, and C are erased if the OVERLAY keyword is not specified for record format E. Record format E is displayed with constants and initialized input fields. The keyboard is unlocked. After the user satisfies the read operation, the contents of the input fields are erased and the keyboard is unlocked again.

Note: Even though the UNLOCK keyword is specified, field validity checking, if specified, and command key verification are performed. Therefore, a user could be typing into the next record when an error message is sent to the display.

Specifying Validity-Checking Functions

Two methods can be used to check the validity of data entered by the user:

- Have the system check the data before it is passed to the application program.
- Have all the input data passed to the application program, which checks the validity of the data.

In either case, if errors are detected, a message is displayed informing the user of the error so that it can be corrected. If you choose the second method for detecting errors, see “Creating and Displaying Your Own Messages” on page 8-1 for information on how your program can display error messages. The rest of this section gives more information on the first method, when the system detects the errors before passing the data to your program.

The validity-checking functions you can specify in DDS are:

- Detecting fields in which at least one character must be entered (CHECK(ME) keyword). Blanks are valid characters. This is referred to as *mandatory enter*.
- Detecting fields in which every position must contain a character (CHECK(MF) keyword). Blanks are valid characters. This is referred to as *mandatory fill*.
- Detecting incorrect data types where character, numeric, or signed numeric data is required.
- Detecting data that is not in the range specified for the field (RANGE keyword).
- Performing comparison checking between data entered and specified constant value (COMP keyword).
- Comparing the data entered to a specific list of valid entries (VALUES keyword).
- Detecting if a valid field or record name was entered in a character field (CHECK(VN) keyword).
- Detecting if a valid object name was entered in a character field (CHECK(VNE) keyword).
- Performing modulus 10 or 11 check digit verification (CHECK(M10) or CHECK(M11) keyword). (Only one can be specified.)
- Allowing blank-key entries to be processed as if no entry had been made (CHECK(AB) keyword). CHECK(AB)—Allow Blanks—is ignored if the subfile keyword SFLROLVAL or SFLRCDNBR is also specified for the field.

The ERRSFL keyword can be used in addition to the validity checking keywords CHECK(M10 M11 VN VNE), COMP, RANGE, and VALUES to allow more than one of the error messages associated with the keywords to be displayed at one time.

When you specify the RANGE, COMP/CMP, VALUES, CHECK(VN), CHECK(VNE), CHECK(M10), or CHECK(M11) keyword for validity checking and an error is detected by one of these validity checking functions, the following happens:

1. The keyboard is locked.
2. All fields in error are displayed in reverse image. If a field in error has both the underline (UL) display attribute and the highlight attribute (HI), its image is not reversed, as this combination of attributes has the same effect as DSPATR(ND).
3. The cursor is positioned at the beginning of the first field in error.
4. A system-supplied error message for the first field in error is displayed on the error line,

or,

If you have chosen to provide your own error message for a field using the CHKMSGID keyword and this is the first field in error, then your error message is displayed on the error line.

If your controller is installed with the self-check feature (see the *5250 Functions Reference*), the controller performs validity checking for the CHECK(M10F) and CHECK(M11F) keywords. Errors are detected when you attempt to move the cursor from the input field rather than when you press the Enter key or a Command Attention key. The Operator Error Code 00115, rather than a system-supplied or user-specified message, is displayed in the lower left corner of the display. If the USRDSPMGT keyword is also specified, CHECK(M10) and CHECK(M11) function as CHECK(M10F) and CHECK(M11F).

If the RANGE, COMP, VALUES, CHECK(VN), or CHECK(VNE) keyword is specified for a field, and data is entered into that field, the field indicates that it has been changed regardless of attempts by the user to restore the field after an error. If blanks (for character fields) or zeros (for numeric fields) will fail the validity checking function, use the CHECK(AB) keyword. This will satisfy the validity checking function.

When you specify validity checking for records that are part of a subfile, each field in the record is validity checked before it is placed in the subfile from the display. You cannot roll the records until all fields in error are corrected.

The system only performs validity checking on a field if the field is changed by the user or if its modified data tag (MDT) is set on using DSPATR(MDT).

Notes:

1. If the user presses the Dup key, any validity checking for a field is ignored. The DUP keyword lets the user use the Dup key.
2. The value for a numeric field for which the COMP, VALUES, or RANGE keyword is specified is aligned based on the decimal positions specified for the field and filled with zeros where necessary. If decimal positions were not entered for the field, the decimal point is assumed to be to the right of the digit to the extreme right in the value. For example, for a numeric field with length of 5 and decimal positions of 2, the value 1.2 is interpreted as 001.20 and the value 100 is interpreted as 100.00.
3. When you use the RANGE keyword for validity checking an input field and blanks are entered in the input field, the value for the input field may not meet

the range requirements. Blanks are converted to zeros for numeric fields and are passed as blanks for character fields. Use the field level keyword BLANKS to determine when a field is displayed as all blanks. The response indicator on the BLANKS keyword is set on if the user enters blanks.

Understanding the Limitations on the Number of Input-Capable Fields

For a remote 5250 display station (a display station attached through a remote controller), you can specify as many as 126 or 256 input fields on one display, depending on the controller model. (The 5294 controller supports 126 input fields; the 5394 controller supports 256 input fields.) Additionally, if either DSPATR(OID) or DSPATR(SP) is specified, this maximum is reduced by 1 for each three instances of these keywords. If fewer than three instances occur, it is still reduced by one.

For a local 5250 display station (a display station attached through the local display station controller), you can specify as many as 256 input fields. Also, if either DSPATR(OID) or DSPATR(SP) is specified, this maximum is reduced by 1 for each three instances of these keywords. In addition, any use of the magnetic stripe reader on a local 5250 display station also reduces the maximum number of fields. The maximum number of fields is calculated as follows:

$$256 - \left[\frac{3+B}{6} + \frac{A}{3} \right] \text{ rounded up to the next whole number}$$

RSLH131-2

A is the number of DSPATR(OID) and DSPATR(SP) fields on the display and B is the length of the longest expected magnetic stripe input where 125 data characters is the maximum allowed. Magnetic stripe data not specified as DSPATR(OID) can be entered into any input field.

If the maximum number of input fields is exceeded in any of the preceding cases, message CPF5192 is issued to the using program.

No maximum-number-of-fields diagnostic is provided during display file creation because the number of fields and record formats is not known until the program is run.

When a subfile record is displayed, the actual number of input-capable fields sent to the display is the number defined in the record multiplied by the number of subfile records that are displayed.

For remotely attached 3270 displays, the limitation is 126 input fields.

For ASCII displays attached through a protocol converter, the limitations are the same as the controller to which they are attached.

Handling Negative Numeric Input Data

The negative sign in numeric input data can appear in three forms:

- Hex 60 if the sign is entered using the - (minus) key
- Hex D if the sign is entered using the Field Minus key
- Hex Dn if the sign is entered as an alphanumeric character with a D zone

The hex 60 is treated as a true minus sign if it is to the right of the least significant digit.

The hex D zone is treated as a minus sign if it is the least significant digit. In addition, it is treated as a significant digit with a value equal to the numeric portion.

Imbedded blanks (between significant digits) are changed to zeros before decimal alignment.

Understanding How the System Reads Input from the Display

When a read operation is issued, the system reads all the records on a display. However, only one record is passed to the program for each read operation. The system saves all the other records in anticipation of more read operations.

If each read operation refers to a different record on the display, no action is required of the user. However, if each read refers not to a different record on the display but to the same record and if the RTNDTA keyword is not specified, the user must perform an action such as pressing the Enter key or a CFnn key to start the next read operation because each record entered is passed to the program only once. If the RTNDTA keyword is specified, the user does not have to perform any action because the same input buffer that was returned to the program on the previous read operation for the record is returned again.

The system saves the contents of input-capable fields for records that are active on the display. This saved data is passed to the user program and can be altered by:

- Initializing the data with a constant on a write operation. A field can be initialized with the value specified in a DFT keyword.
- Entering data through directly typing the data in or using a light pen to select data. (The MDT for a field can be set on to simulate user input.)
- Entering data from a program on a write operation. This applies to output/input fields (and output-only fields for subfiles).
- Initializing the data with blanks (character fields) or zeros (numeric fields) on an output operation for the same record unless the PUTRETAIN keyword is specified. This applies to input-only fields.

Writing Output and Reading Input at the Same Time

The write-read operation is a combination of a write operation and a read operation to the same record format in one high-level language statement like the SNDRCVF command in a CL program. It behaves as if you had specified a read operation immediately following a write operation.

Some high-level languages have a write-read operation which writes information on the display and reads the user response in one statement. For example, RPG has the execute format (EXFMT) operation. This kind of operation is useful if you need to both present new information on the display and request information from the user at the same time. You can also use a write operation followed by a read operation to the same record format to simulate this operation in languages that do not support a combined write-read operation.

When this operation is performed, the following happens:

1. The program calls the system display support giving it the data to show on the display and the record format to use when writing and reading that data.

2. The system combines that data with the information it finds in the record format and constructs the data stream to be sent to the display.
3. The data stream is then sent to the display and the keyboard is unlocked.
4. The user types the data in the fields which allow input and presses the Enter key or some other function key.
5. The data is then sent from the display to the system. The system decodes it and extracts only the information that the application program needs to know and returns that data to the application program.

When you work with only one record format, this write-read style of working with it is the most common. On the write portion of the operation, you provide the data that the user will see. On the read portion, you receive data back that the user has entered or changed.

Canceling Input That Was Not Waited For

The cancel-invite operation is used to cancel the input request issued to a display station that was previously invited through the invite operation. The input request is canceled by performing a write operation to the invited display station. One of the following occurs:

- If the write request is received before the user responds to the input request from the invite operation, the input request is canceled and the record format specified on the write operation is sent to the display station. If the record format has the option indicator set on for the DDS keyword INVITE, the display station is invited again.
- If the write request is received after the user responds to the input request from the invite operation, the input request is not canceled and the write operation fails. The read-from-invited-devices operation or a read(wait) operation must be issued to receive the available data.

Releasing a display station also implicitly cancels any input requests directed to the display station. If the display station has data available, the data is lost.

Locking the Keyboard and Positioning the Cursor During I/O Operations

The following lists what happens to the keyboard when a write, write-read, or read operation is run:

Operation	Keyboard
Write	The keyboard is unlocked by default. If the LOCK keyword is specified, the keyboard is not unlocked.
Write-Read	The keyboard is unlocked.
Read	The keyboard is unlocked (if locked) before display station user action. After user action, the keyboard is locked by default. If the UNLOCK keyword is specified, the keyboard is left unlocked.

Every time the keyboard is unlocked, the cursor is repositioned. In some cases, many write operations between read operations can cause erratic cursor movement. If the user starts typing before the last write operation, the cursor is repositioned when the keyboard is unlocked and this can cause confusion for the user.

You can prevent this by using the LOCK keyword. By using the LOCK keyword on each write operation but the last, the keyboard remains locked until the last write operation. This avoids erratic cursor movement, but prevents the user from starting to type data.

Normally, a user action, such as pressing a valid command key, locks the keyboard.

To specify that the system unlock of the keyboard on the next input operation should not occur, specify the retain lock status (RETLCKSTS) keyword. This keyword prevents the loss of data when the input operation is started and data is already being transmitted from the keyboard.

Note: Use the RETLCKSTS keyword only when the keyboard is already unlocked.

To position the cursor with the DSPATR(PC), CSRLOC, or SFLRCDNBR(CURSOR) keyword, the keyboard must be locked. Only the following conditions on an output operation cause the keyboard to be locked and must be present for the display station to position the cursor. (An output operation normally unlocks the keyboard before it ends unless the LOCK keyword is specified so these conditions lock the keyboard only momentarily.)

- Input-capable fields are erased (ERASEINP keyword).
- Modified data tags are reset (MDTOFF keyword).
- Any input-capable field is written to the display.
- The complete display is erased (a write operation without an OVERLAY keyword).
- The 5250 format buffer is reset, which can be the result of:
 - A record format with an input-capable field is overlaid or erased.
 - A record format with a cursor location specification is overlaid or erased.
 - The PROTECT keyword is specified on the record being written.

For the cursor positioning keyword to take effect, the keyboard must go from the lock condition to an unlocked condition. That is, if the keyboard is unlocked prior to the write operation, the cursor positioning keyword does not take effect immediately on the write operation. However, there is one exception. If the keyboard is temporarily locked during an output operation, the cursor positioning keyword will be in effect if the output operation unlocked the keyboard at the end.

In addition, if any of the preceding conditions happens on a write operation, the keyboard must be unlocked before any user action either by the same operation or by a following operation (it should be the last write operation).

A write operation to a subfile never unlocks the keyboard because no input or output is sent to the display station.


Saving Previously Displayed Information

A display file may be opened to a display station even when another display file is already using that display station. When an I/O operation is performed to the second display file, the first display file is *suspended*.

When a display file is suspended, the information on the display can be saved automatically by the system if you specify *YES for the RSTDSP parameter on the Create Display File (CRTDSPF) or Change Display File (CHGDSPF) command. The contents of a display file can then be restored when an I/O operation is later

performed to that display file. If *NO is specified for the RSTDSP parameter, the application program needs to rewrite the display to show it again.

The RSTDSP parameter lets you overlap a program call, keyboard input, and file I/O processing, as shown in the following example:



- 1** Program 1 issues a write operation to record format RCD Y1 in display file DSPFILY, which activates display file DSPFILY.
- 2** Program 1 issues a write operation to record format RCD X1 in display file DSPFILX, which suspends display file DSPFILY and activates display file DSPFILX. If RSTDSP(*YES) is specified for display file DSPFILY, the data displayed on the display station is saved. If RSTDSP(*NO) is specified instead, the data is lost and the program needs to write the information in RCD Y1 again to show it.
- 3** Program 1 issues a read operation to record format RCD Y1, which suspends display file DSPFILX and restores display file DSPFILY. If the RSTDSP(*YES) parameter is specified for DSPFILY, then the data displayed on the display station when DSPFILY is suspended can be restored.

When RSTDSP(*YES) is specified for a display file, and you are suspending and restoring that display file because of operations to another display file, some displays may appear to flash on the screen briefly. If a display file has a record on the display and an I/O operation is done to a second display file, the first file is suspended and its screen contents are saved. When returning to the first display file, the display file and its screen contents are restored. If a write operation is done to a different record format in the display file, the restored display will flash briefly before the output operation is complete. If you are going to completely rewrite the display contents from your program when going back to the first file, use RSTDSP(*NO).

You should specify *YES for the RSTDSP parameter in the following situations:

- When you are writing a record that has the following keywords in effect:
 - CLRL
 - OVERLAY

- PUTOVR
- PUTRETAIN
- ERRMSG
- ERRMSGID

You must ensure that the records that are on the display are the records that these keywords apply to. If the display file is suspended, the data must be restored to the screen so that the write operations to the record formats that use these keywords are valid.

- When you perform multiple read operations to a record format on the display without intervening write operations. If you should call a program while processing the data that has been read and that program presents a display of its own, the subsequent read operation done by your program restores the display properly.

Saving and displaying data again requires significant system and data transmission overhead. For a 1920-character 5250 display station, approximately 3000 characters are transmitted each time the display data is saved displayed again. To avoid this overhead, write your application programs to do the following:

- Make the programs in the application share the same copy of the display file among themselves by specifying SHARE(*YES) on the display file.
- Perform complete display rewrites each time the programs in the application write to the display. A complete display rewrite occurs when a record is written to the screen and the OVERLAY keyword is not used or implied.

Note: If complete display rewrites are not performed and if new input fields, occupying positions on the screen above the currently displayed fields, are sent to the display, the program receives a message (CPF5192). This occurs because the 5250 display station requires that new input fields sent to the display appear in lower positions than input fields currently on the display. In normal operations, data management performs field processing to satisfy the 5250 requirement. See “Avoiding Record Format Problems on the 5250 Display Station” on page 3-45.

When one program that uses a display file with the SHARE(*YES) parameter specified calls another program that uses the same display file, the display file is not suspended even though both programs have opened the file. If the display file is not shared, the system maintains separate copies of the display file for each program and suspends and restores the display files separately.

Since system programs do not specify file sharing, you should specify RSTDSP(*YES) on the CRTDSPF or CHGDSPF command if your program contains a display file and calls system functions that present displays. System functions that break into the normal path of an application, however, such as the System Request Menu or the presentation of break messages, restore the display without RSTDSP(*YES) specified.

To display saved display data again after a close operation is issued to a suspended file, specify the KEEP keyword for a record format in the saved display data.

Understanding the Effects of I/O Operations on Command Keys

Read and write operations may or may not affect how the function keys work:

- A write or write-read operation for which no input or output is sent to the display does not affect which keys are valid. Examples of such operations are a write operation or an update operation to a subfile record format.
- If a write or write-read operation displays a message by selecting either the ERRMSG or ERRMSGID keyword, the command keys in effect on that output operation are valid. Therefore, you can specify a different set of command keys to be valid if an error occurs.
- If only one subfile record format is displayed and the subfile control record format specifies a CAnn or CFnn key for the SFLDROP keyword, that key remains valid for that function as long as the subfile is still on the display. In addition, the key specified for the SFLENTER keyword remains valid until another write or write-read operation is done. At the next output operation, the specifications for that record apply.
- If two subfile record formats are displayed and both specify the SFLDROP keyword, only the last SFLDROP keyword is used. There can only be one drop key at a time.

Avoiding Record Format Problems on the 5250 Display Station

Because of the characteristics of the 5250 display stations, certain record format positioning and operational combinations can produce undesirable results. The following example illustrates a combination that can cause undesirable results and explains how to avoid these results.

The displays produced and the DDS for the record formats follow:

Enter all information regarding the subscriber:

Last name: _____ First name: _____ MI: _____

Street: _____ Apt: _____

City: _____ State: _____ ZIP: _____ - _____

CA1-Display state table, CA2-Display subscription table

DETAIL
record
format

RSLH166-0

Alabama AL Alaska AS Arkansas AK Arizona AK
 California CA Delaware DE DST Columbia DC Florida DC
 Y-More state names, N-No more state names
 Enter all information regarding the subscriber:
 Last name: Doe First name: John MI: E
 Street: 112 Elm Apt: 3A
 City: Anytown State: ZIP: -

STATES
record
format

DETAIL
record
format

CA1-Display state table, CA2-Display subscription table

RV2W047-0

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R RCDA
A          FLD1          1  I  2  4DSPATR(PC)
A* STATES record format follows
A          R STATES          OVERLAY
A          SNAME1          12  0  1  2
A          SCODE1          2  0  1 15
A          SNAME2          12  0  1 18
A          SCODE2          2  0  1 31
A          SNAME3          12  0  1 34
A          SCODE3          2  0  1 47
A          SNAME4          12  0  1 50
A          SCODE4          2  0  1 63
A          .
A          .
A          .
A          SNAME8          12  0  2 50
A          SCODE8          2  0  2 63
A          3  2'Y-More state names, N-No more +
A          state names'
A          MORESNAM          1  I  3 48VALUES('Y' 'N')
A* DETAIL record format follows
A          R DETAIL          OVERLAY CA01(11) CA02(12)
A          4  2'Enter all information regarding +
A          the subscriber:'
A          5  1'Last name:' DSPATR(HI)
A          NAMEL          20  I  5 12
A          5 33'First name:' DSPATR(HI)
A          NAMEF          13  I  5 45
A          5 59'MI:' DSPATR(HI)
A          MI          1  I  5 63
A          6  1'Street:' DSPATR(HI)
A          STREET          45  I  6  9
A          6 55'Apt:' DSPATR(HI)
A          APT          4  I  6 60
A          7  1'City:' DSPATR(HI)
A          CITY          15  I  7  7
A          7 23'State:' DSPATR(HI)
A          SCODE          2  I  7 30
A          7 33'Zip:' DSPATR(HI)
A          ZIP1          5  I  7 38
A          7 44'- '
A          ZIP2          4  I  7 46
A          .
A          .
A          .
A          10  1'CA1-Display state table, +
A          CA2-Display subscription table'

```

Figure 3-12. Sample DDS to Show Record Format Problems

Assume that the DETAIL record format is on the screen, and the user is entering data for a subscriber. Because the user does not know the state code for the state to be entered, he or she presses the CA01 key.

Because CA01 is defined as a CAnn key, no data is transmitted to the system when the CA01 key is pressed. The data, however, remains on the screen. The program detects that the CAnn key was pressed because response indicator 11 is set on. The program then displays the STATES record format.

Because the STATES record format is physically above the DETAIL record format, the system must resend the field formats for the input fields in the DETAIL record format. (The system would also resend the field formats if the STATES record format contained only output-only fields and was replacing the RCDA record format. In this case, the field formats are resent because a record format (RCDA) with a specific cursor location is being removed.)

The following problems occur because the system resends the field formats for the DETAIL record format:

- All the input fields in the DETAIL record format lose their modified data tags (MDTs). When the program does the next read to the DETAIL record format (for example, when the user presses the Enter key), none of the fields typed in before the user pressed the CA01 key are returned to the program. The program cannot retrieve that typed data even though the data still remains on the screen.

To avoid this problem:

- Avoid using a CAnn key.
 - If you must use a CAnn key, avoid writing the format containing the CAnn key to the screen and then writing another format that is physically placed above the first format if both formats contain input-capable fields.
 - Avoid writing a format to the screen that causes the removal of a format containing a cursor location specification.
- The highlight attribute for the constant fields (except Last name) is lost. The system does not resend the field format for output-only fields. However, if an output-only field immediately follows an input-capable field so that the leading attribute character for the output field is in the same position as the ending attribute character for the input-capable field, the attribute of the output field reverts to normal.

To avoid this problem:

- Do not specify an output-only field with special display attributes immediately following an input-capable field.
- If you must specify an output-only field with special display attributes immediately following an input-capable field, avoid writing that format to the screen and then writing another format that is physically placed above the first format if both formats contain input-capable fields.
- Avoid writing a format to the screen that causes the removal of a format containing a cursor location specification.

Note: The system needs to resend the attributes for the input-capable fields when a subfile is rolled from a full page to a partial page, a partial page to a full page, or a partial page to a partial page. The two problems mentioned above may also occur when resending the field attributes.

Releasing an Acquired Display Station from I/O Operations

The **release operation** makes a display station ineligible for any further I/O operations through a file. This operation is used in multiple display file applications or if you are performing error recovery in your program. If the display station being released is invited, the invite is ended. If the invited display station had data available, the data is lost. The release operation can only be performed on display stations that are currently acquired to the file.

The release operation can also be used to recover from errors from acquire, I/O, and release operations. After a display station is released, it must be acquired again with another acquire operation before any I/O operations can be directed to it. If a program is written to recover from errors by releasing a display station and then acquiring it again, a value other than *IMMED should be specified on the WAITFILE keyword. This is because it takes the system a short time to transfer the allocation of a display station description from a job, to the subsystem, and back again.

Closing Display Files

The **close operation** makes the display file ineligible for any further I/O operations between the program and the system. Refer to the appropriate high-level language manual for information on how to start the close operation.

If the display file is not being shared, the close operation also implicitly releases all the display stations acquired to the file and deallocates any file resources allocated by the open operation or the acquire operation.

If the close operation is successful, the only valid operation to the file is open. If the close operation fails, the program should issue the close operation a second time.

Mapping Display Operations to High-Level Language Operations

The following shows the I/O requests supported by the operating system and the equivalent high-level language operations:

Table 3-6 (Page 1 of 2). Display File Operations Supported by the Operating System and the Equivalent High-Level Language Commands

Operation	BASIC Statements	C/400 Functions	CL Commands	COBOL/400 Statements	FORTRAN/400* Statements	RPG/400 Operations
Open	OPEN	fopen, _Ropen		OPEN	OPEN	OPEN
Acquire		QXXACQUIRE, _Racquire		ACQUIRE		ACQ
Release		QXXRELEASE, _Rrelease		DROP		REL
Get Attributes		QXXDEVATR _Rdevatr		ACCEPT		POST
Write	WRITE	fwrite, QXXPGMDEV, QXXFORMAT, _Rformat, _Rpgmdev, _Rwrite	SNDF	WRITE	WRITE	WRITE, output specifications

Table 3-6 (Page 2 of 2). Display File Operations Supported by the Operating System and the Equivalent High-Level Language Commands

Operation	BASIC Statements	C/400 Functions	CL Commands	COBOL/400 Statements	FORTRAN/400* Statements	RPG/400 Operations
Read(wait)	READ	fread, QXXPGMDEV, QXXFORMAT, _Rformat, _Rpgmdev, _Readn	RCVF WAIT(*YES)	READ	READ	Primary or secondary file input, READ
Read	READ		RCVF WAIT(*NO)	READ		
Cancel Read			ENDRCV			
Wait			WAIT			
Invite		fwrite ¹ , QXXPGMDEV, QXXFORMAT, _Rformat, _Rpgmdev, _Rwrite ¹	SNDF ¹	WRITE ¹		WRITE ¹
Read from Invited Device		QXXREADINVDEV, _Rreadindv		READ		READ
Cancel Invite		fwrite, QXXPGMDEV, QXXFORMAT, _Rformat, _Rpgmdev, _Rwrite	SNDF	WRITE		WRITE
Write-Read(wait)		_Rwriterd, _Rformat, _Rpgmdev	SNDRCVF WAIT(*YES)			EXFMT
Write-Read(no-wait)			SNDRCVF WAIT(*NO)			
Close	CLOSE, END	fclose, _Rclose	RETURN, RCLRSC	CLOSE, CANCEL, STOP RUN	CLOSE	CLOSE, RETRN

¹ This is the write operation of a record format with the INVITE DDS keyword selected.

If an error occurs during an I/O operation to a display file, the major/minor return code field in the file dependent I/O feedback area may be used to help diagnose the error and determine the error recovery action needed.

Sharing Display Files in the Same Job

By specifying the SHARE parameter on the CRTDSPF, CHGDSPF, and OVRDSPF commands, you can specify that more than one program share the same path to the data or the display station. Using the SHARE parameter allows more than one program to share the file status, positions, and storage area, and can improve performance by reducing the amount of main storage the job needs and by reducing the time it takes to open and close the file.

Using the SHARE(*YES) parameter lets an open data path (ODP) be shared between two or more programs running in the same job. An **open data path** is the path through which all input/output operations for the file are performed. It connects the program to a file. If not specified otherwise, every time a file is opened a new open data path is built. You can specify that if a file is opened more than once and an open data path is still active for it in the same job, the active ODP for the file can be used with the current open of the file, and a new open data path does not have to be created. This reduces the amount of time required to open the file after the first open, and the amount of main storage required by the job. SHARE(*YES) must be specified for the first open and other opens of the same file for the open data path to be shared. Specifying SHARE(*YES) for other files depends on the application.

Note: Most high-level language programs process an open or a close operation independent of whether or not the file is being shared. You do not specify that the file is being shared in the high-level language program. You indicate that the file is being shared in the same job through the SHARE parameter. The SHARE parameter is specified only on the create, change, and override file commands. Refer to your appropriate language manual for more information.

Understanding the Open Operation for Files Shared in a Job

The following items should be considered when opening a file that is shared in the same job by specifying SHARE(*YES).

- You must make sure that when the shared file is opened for the first time in a job, all the open options that are needed for subsequent opens of the file are specified. If the open options specified for subsequent opens of a shared file do not match those specified for the first open of a shared file, an error message is sent to the program. (You can correct this by making changes to your program to remove any incompatible options.)

For example, PGMA is the first program to open FILE1 in the job and PGMA only needs to read the file. However, PGMA calls PGMB which will delete records from the same shared file. Because PGMB will delete records from the shared file, PGMA will have to open the file as if it, PGMA, is also going to delete records. You can accomplish this by using the correct specifications in the high-level language. (In order to accomplish this in some high-level languages, you may have to use file operation statements that are never run.) For more details, see your appropriate language manual.

- If you did not specify a library name in the program or the override command (*LIBL is used), the system assumes that the library list has not changed since the last open of the same shared file with *LIBL specified. If the library list has changed, you should specify the library name on the override command to ensure that the correct file is opened.
- Overrides and program specifications specified on the first open of the shared file are processed. Overrides and program specifications specified on subsequent opens, other than those that change the file name or the value specified on the SHARE or LVLCHK parameters on the override command, are ignored.

Understanding the Input/Output Operation for Files Shared in a Job

The system uses the same input/output area for all programs sharing the file, so the order of the operations is sequential regardless of which program does the operation. For example, if Program A is reading records sequentially from a file and it reads record 1 just before calling Program B, and Program B also reads the file sequentially, Program B reads record 2 with the first read operation. If Program B then ends and Program A reads the next record, it receives record 3. If the file was not being shared, Program A would read record 1 and record 2, and Program B would read record 1.

For display files, the display station remains in the same state as the last I/O operation.

For display and ICF files, programs other than the first program that opens the file may acquire more display or program display stations or release display or program display stations already acquired to the open data path. All programs sharing the

file have access to the newly acquired display stations, and do not have access to any released display stations.

Understanding the Close Operation for Files Shared in a Job

The processing done when a program closes a shared file depends on whether there are other programs currently sharing the open data path. If there are other programs, the main function that is performed is to detach the program requesting the close from the file. All other programs sharing the file are still attached to the ODP and can perform I/O operations.

If the program closing the file is the last program sharing the file, then the close operation performs all the functions it would if the file had not been opened with the share option. This includes releasing any allocated resources for the file and destroying the open data path.

The function provided by this last close operation is the function that is required for recovering from certain run-time errors. If your application is written to recover from such errors and it uses a shared file, this means that all programs that are attached to the file when the error occurs will have to close the file. This may require returning to previous programs in the program stack and closing the file in each one of those programs.

Chapter 4. Displaying Groups of Records Using Subfiles

A subfile is a group of records that have the same record format and are read from and written to a display station in one operation. The following sample display shows an example of a subfile:

CUSTOMER NAME SEARCH				
Search code: 41401				
NUMBER	NAME	ADDRESS	CITY	STATE
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
41403	Advanced Electronics	809 8th Street	St Paul	MN
41404	Riteway Repair	443 Western Lane	New York	NY
41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL
41406	Hall's Electric	200 Main Street	St Paul	MN

RV2W049-0

Information about DDS keywords

This chapter uses DDS keywords to describe subfiles. For more information about specific DDS keywords, see the *DDS Reference*.

Recognizing Subfile Uses

Subfiles are useful when multiple records that are alike must be displayed. You can describe a subfile so that the number of records to be displayed fits on one display or exceeds the number of lines available on the display.

You can use subfiles for the following purposes:

- Display only, which allows the user to review the subfile records on the display (for example, all the line items for a particular order number, or a group of records containing customer names and addresses as shown on the previous sample display).
- Display with selection, which allows the user to request more information about one of the items on the display. On the first sample display of the following example, the user can request the records for a particular customer by entering the record number in the record number field. In the second sample display, the user can request the records for a particular customer by placing an X in the select number field.

Enter customer number: 41401
 Enter record number: _____

RECORD	NUMBER	NAME	ADDRESS	CITY	STATE
01	41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
02	41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
03	41403	Advanced Electronics	809 8th Street	St Paul	MN
04	41404	Riteway Repair	443 Western Lane	New York	NY
05	41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL
06	41406	Hall's Electric	200 Main Street	St Paul	MN

Enter customer number: 41401

SELECT

RECORD	NUMBER	NAME	ADDRESS	CITY	STATE
-	41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
-	41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
-	41403	Advanced Electronics	809 8th Street	St Paul	MN
-	41404	Riteway Repair	443 Western Lane	New York	NY
-	41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL
-	41406	Hall's Electronic	200 Main Street	St Paul	MN

- Changing information, which allows the user to change one or more of the records in the subfile. The following sample display allows the user to change the *QTY* and *SHIP* values:

UPDATE SHIP QUANTITY ON ORDERS

Order: 11589 Customer number: 11111 Customer name: Al'Supply

ITEM	DESCRIPTION	QTY	SHIP	LOCATION
25764	Pliers	10	10	RST
33624	Hammer	500	250	RST
49821	Pliers	200	200	RST
26837	Wire Cutters	50	25	RST

- Input only without validity checking, which allows the user to enter data as fast as possible; or input only with validity checking, which allows the user to enter data that is validity checked by the system or by the program for valid entries. The following sample display shows subfiles for input only:

Enter order number: XXXXX

ITEM NUMBER	QUANTITY
XXXXX	XXX
XXXXX	XXX
XXXXX	XXX
XXXXX	XXX
XXXXX	XXX
XXXXX	XXX
XXXXX	XXX

- Combination of tasks, which can, for example, allow the user to change data as well as to enter new records. In the following example, the user can change existing names and addresses or enter new records.

CUSTOMER NAME SEARCH				
Search code: 41401				
NUMBER	NAME	ADDRESS	CITY	STATE
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
41403	Advanced Electronics	809 8th Street	St Paul	MN
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____
_____	_____	_____	_____	_____

Describing Subfiles in Your DDS Source

Each subfile you describe in your DDS source requires two types of record formats: a subfile record format and a subfile control record format.

- The **subfile record format** defines the fields in one row of the subfile.

The high-level language program uses the subfile record format to read a subfile, write new records to a subfile, and update the subfile. Operations to the subfile record format are performed between the subfile and the high-level language program; the display is not changed on operations to a subfile record format.

The subfile (SFL) keyword is required on the subfile record format.

- The **subfile control record format** contains heading information and controls subfile functions such as size, initialization, and clearing.

The high-level language program performs operations on the subfile control record format to write the subfile to the display and to read the subfile from the display.

The following DDS keywords are required on a subfile control record format:

- Subfile control (SFLCTL) keyword, which identifies the subfile control record format for the subfile record format that immediately precedes it
- Subfile size (SFLSIZ) keyword, which specifies the size of the subfile
- Subfile page (SFLPAG) keyword, which specifies the size of the subfile page
- Subfile display (SFLDSP) keyword, which specifies when to begin displaying records in a subfile

The DDS for the subfile record format must precede the DDS for the subfile control record format.

Each subfile has two types of records:

- An **active subfile record** is a record that has been:
 - Added to a subfile by a write operation.
 - Initialized as active by the subfile initialize (SFLINZ) keyword.
 - Changed when a write or update operation with the subfile next changed (SFLNXTCHG) keyword in effect was issued to the record.
 - Changed by the user.
- An **inactive subfile record** is a record that was:
 - Not added to a subfile by the write operation.

- Initialized as inactive by the SFLINZ keyword and the subfile records not active (SFLRNA) keyword.

You can also perform the following functions on subfiles:

Table 4-1 (Page 1 of 3). Optional Functions for Subfiles

Function	DDS keyword	Additional information
Allow a subfile to contain messages from a program message queue	Subfile message key (SFLMSGKEY), subfile message record (SFLMSGRCD), and subfile program message queue (SFLPGMQ)	See the <i>DDS Reference</i> for more information about the subfile message keywords.
Clear the subfile of all records before new records are written	Subfile clear (SFLCLR)	The subfile is not erased from the display, however, until the SFLDSP keyword is in effect on the subfile control record. If the SFLCLR keyword is specified for a subfile with no records, it is ignored.
Control when to display a subfile control record	Subfile Display Control (SFLDSPCTL) or SFLDSP	The SFLDSP and SFLDSPCTL keywords are the only keywords that cause the contents of the display to change. The SFLDSPCTL keyword must be in effect if an input operation is done to retrieve the status of a CFnn or CAnn key even if no fields are displayed.
Delete the subfile to allow another subfile to be used or to continue processing the display file with no subfile used	Subfile delete (SFLDLT)	Normally, subfiles should not be deleted by the program. When the file containing the subfile is closed, the subfile is deleted automatically by the system. However, if the file is shared and is still open by another program, the subfile is not deleted, and you must delete it in your program. You should only delete a subfile if the maximum number of subfiles are already being used and you need to use another one. The SFLDLT keyword is ignored if the subfile does not exist.
Display a page of a subfile by a record number	Subfile record number (SFLRCDNBR)	If CURSOR is specified for the SFLRCDNBR keyword, the cursor is placed in the subfile record whose relative record number is identified by the contents of this field. The cursor is positioned at the first input-capable field in the subfile record. If there is no input-capable field, the cursor is positioned at the first output-only or constant field.
Display a plus sign (+) in the lower corner at the extreme right of the subfile display area (page) when there are more records than fit on the display.	Subfile end (SFLEND) or (SFLEND(*PLUS))	The plus sign is replaced by a blank when the last record is displayed. An option indicator must be specified with the SFLEND or SFLEND(*PLUS) keyword.
Display the word 'More...' on the line following the subfile display area (page) when there are more records than fit on the display.	Subfile end SFLEND(*MORE)	The word 'More...' is replaced by the word 'Bottom' when the last record is displayed. An option indicator must be specified with the SFLEND(*MORE) keyword.

Table 4-1 (Page 2 of 3). Optional Functions for Subfiles

Function	DDS keyword	Additional information
Enable a command key to fold or truncate records in a subfile	Subfile fold (SFLFOLD) or subfile drop (SFLDROP)	<p>If the SFLFOLD keyword is specified, the initial display of the records is folded. If the SFLDROP keyword is specified, the initial display of the records is automatically truncated. Then the user can press the command key to display the truncated or folded version, respectively, of the subfile record. If the page size equals the subfile size or the subfile fits on one display line, the specified keyword (SFLFOLD or SFLDROP) is ignored.</p> <p>Both SFLFOLD and SFLDROP can be used on the same subfile. Optional indicators can be used on these keywords. The optional indicators are used to determine which mode the subfiles are initially displayed in. If both keywords are optioned on or optioned off, then the subfile is initially displayed in folded mode. If the keyword is optioned off, the command key can still be used to display the truncated or folded version.</p>
Enable the Enter key as the Roll Up key and enable a command key to return to the high-level language program	Subfile enter (SFLENTER)	<p>If more than one subfile using SFLENTER is displayed at the same time, the only CAnn or CFnn key in effect as an Enter key is the CAnn or CFnn key specified for SFLENTER on the most recently displayed subfile. The cursor position at the time the Enter key is pressed determines which subfile is affected.</p>
Initialize a subfile with no active records even though the subfile is active	SFLINZ and subfile records not active (SFLRNA)	<p>A record becomes active when one of the following happens:</p> <ul style="list-style-type: none"> • An output operation is issued to the subfile for a specific record. The record is not considered changed unless the SFLNXTCHG keyword is used. • A user enters data into a displayed record. The record is considered active and changed. <p>The records are displayed if the SFLDSP keyword is in effect. If default values were specified for fields in the records, they are included in the display.</p>
Initialize all records by the field descriptions in the subfile record format in the display file	SFLINZ	<p>When the SFLINZ keyword is in effect on an output operation to the subfile control record (SFLCTL), the system assumes that all option indicators on the subfile record are off; therefore, only those option indicators that are preceded by N are in effect. The subfile records are displayed if SFLDSP is in effect on an output operation. When the SFLINZ keyword is in effect on an output operation, the contents of input-capable fields without a default value are handled as follows:</p> <ul style="list-style-type: none"> • Numeric fields are initialized to zeros. • Character fields are initialized to blanks. • Floating point fields are initialized to nulls.
Return a record to the program when a get-next-changed operation is performed	Subfile next changed (SFLNXTCHG)	<p>The record is returned even if the record was not changed by the user</p>
Roll by a specified number of records instead of by page	Subfile roll value (SFLROLVAL)	<p>This field must have the keyboard shift attribute of signed numeric with zero decimal positions. It can be up to 4 digits long and must be defined as an output/input or input-only field.</p>

Table 4-1 (Page 3 of 3). Optional Functions for Subfiles

Function	DDS keyword	Additional information
Specify the number of spaces between each record on a line when more than one record is displayed on a line	Subfile line (SFLLIN)	This keyword is used for a horizontally displayed subfile. If the display file supports more than one screen size and the SFLLIN keyword is to apply to the secondary screen size in addition to the default (or primary) screen size, screen size condition names must be specified.
Write a message to the message line on the display when your program does an output operation to the subfile control record	Subfile message (SFLMSG) and subfile message ID (SFLMSGID)	See the <i>DDS Reference</i> for more information about the message keywords.
Determines where the cursor is located in a subfile	Subfile cursor relative record number (SFLCSRRRN)	The relative record number on which the cursor is positioned is returned in the hidden field specified as the parameter on the keyword.
Determines whether the subfile was in folded or truncated mode	Subfile mode (SFLMODE)	This is a required parameter and is only valid for subfile control records and the SFLCTL keyword must be specified.

The DDS keywords can be specified in any order; however, the subfile record format (SFL) must precede the subfile control record format (SFLCTL).

You can use option indicators to condition many of the DDS subfile keywords.

You can specify a maximum of 512 subfiles in a display file, since the maximum number of record formats allowed in a display file is 1024. No more than 12 subfiles can be active at the same time to the same display station. One or more active subfiles can be displayed at the same time on the display station. A subfile must contain at least one field that can be displayed, and the subfile record format must not overlap the subfile control record format. If these records overlap, the display file cannot be created.


All named fields in a subfile record, including fields that are *not* input-capable, are returned to the program.

If any input data validity checking is specified for the subfile record, the validity checking is performed before any roll function is performed. If the data fails validity checking, the roll function is not performed.

When the relative record number of the record written to the subfile equals the subfile size, the system sends the program a CPF5003 message indicating that the subfile is full. (Not all records need to be active; that is, this message is sent even if the only record written to the subfile was the last record in the subfile.) If the subfile size does not equal the page size and the program then writes more records to the subfile, the system automatically extends the subfile as additional records are added. The program is not notified that the subfile has been extended. (A subfile cannot be extended past 9999 records.) Also, if the subfile size equals the page size, the program is not notified that the subfile is full unless the last record written to the subfile occupies the last line available on the subfile display area.

Processing of an extended subfile is less efficient because the extended space is not connected with the subfile. You can avoid extension by specifying a larger subfile size, but you will be wasting space if the extended space is used very seldom or never.

Figure 4-1 illustrates the order in which some of the DDS keywords used for subfile control are processed at run time:




RSLH181-0

Figure 4-1. DDS Keyword Processing Order for Subfile Control


Using a Subfile in a Program

To use a subfile, you perform the following basic operations in your high-level language program:


1. Initialize the subfile. One way to initialize the subfile is to read records from a database file and write them to the subfile. Place the records in the subfile one at a time until the subfile is full or until there are no more records.



2. Send the subfile to the display in one output operation using the subfile control record format.
3. After the user reviews the records, changes them, or enters new records (depending on the function of the subfile), read the subfile control record format.



4. Process each record in the subfile individually, updating the database file or writing new records to the database file as required. If the function of the subfile is to update records, the program need only process the changed records by using the READC operation in RPG/400* or the Read Subfile Next Modified verb in COBOL/400*.



A display file that uses subfiles may display only a portion of a subfile at a time. The portion that is displayed is called a **subfile page**. The data entered into an input-only field on a subfile display goes to the subfile when a function key (such as a Roll key) is pressed. The field then displays a value in the subfile, and what happens when the Enter key is pressed depends on the application code.

Note: In a READC operation in RPG, the data is moved from the subfile to the program. It does not remove it from the subfile, and it will continue to be displayed in the input-only field as if the fields were initialized to that value. Otherwise, it would appear that the subfile was empty when the data was actually there.

If the subfile is processed (for example, by an UPDAT operation in RPG), then the data is removed from the subfile, and the input-only fields are blanked out, reflecting the true condition of empty fields. This should be done after the READC operation moves the data to the program.

Requesting I/O Operations for a Subfile

An I/O request by a calling program to a subfile record format either writes a record to a subfile or reads a record from a subfile but never causes actual I/O to the display. To write subfile records to a display, the program must issue a request to the subfile control record format.

The valid requests that can be made to a subfile depend on whether the request is made to the subfile record format or the subfile control record format.

Requesting I/O Operations for a Subfile Record Format

By requesting the correct I/O operation for a *subfile record format*, you can do the following:

- Add a record (passed from a program) to a specified location in a subfile
- Update an active record that already exists in the subfile
- Read an active record at a specified location in the subfile
- Read the next changed record in the subfile that is greater than the relative record number previously read with a get-relative or get-next-changed operation

Adding a Record at a Specified Location in a Subfile

The **put-relative operation** adds a record (passed from a program) at a specified location in a subfile.

The location must be a valid relative record number in the subfile. The minimum relative record number is always 1. If the subfile size equals the subfile page, the maximum relative record number value is the subfile size value. If the subfile size is greater than the subfile page, the maximum relative record number value is 9999 because the system automatically extends the subfile as required. In addition, the relative record number cannot be the number of an active record already in the subfile. The relative record number is ignored when field selection is specified for the subfile record.

When a put-relative operation adds a record at the last record location (the subfile size value) in the subfile, a subfile-full condition occurs (message CPF5003). Both RPG/400 and COBOL/400 have special support for notifying the application program of this condition. See the appropriate high-level language manual.

The contents of input-capable fields without a default value specified are handled as follows:

- Numeric fields are initialized to zeros
- Character fields are initialized to blanks
- Floating point fields are initialized to nulls

Updating an Active Record in the Subfile

The **update operation** updates an active record that already exists in the subfile.

The active record must have been read before the update operation by a get request (either get relative or get-next-changed). No other I/O operations may be performed on the subfile to be updated between the read and the update. In addition, the subfile being updated may not be displayed again between the read and the update (for example, using subfile roll or SFLDROP processing).

Notes:

1. Some high-level languages do not allow I/O to any format in the display file between the read and the update of a single subfile record in the display file. Refer to the documentation for the high-level language you are using for more information.
2. If field selection is specified for the subfile record, only the fields that were selected when the record was placed in the subfile can be updated. Selecting different fields will cause results that cannot be predicted.

Reading an Active Record at a Specified Location in the Subfile

The **get-relative operation** reads an active record at a specified location in the subfile.

The location must be a valid relative record number in the subfile. The entire record, including response indicators (defined at the file level and on fields in a subfile record), input, output, output/input, and hidden fields, is passed to the program, the relative record number is placed in the input/output feedback area, and the record is no longer identified as a changed record. Response indicators defined at the file level are always returned as off. Response indicators defined on fields in a subfile record, such as the BLANKS or CHANGE keywords, are returned as on or off depending on the information in the field at the time the get operation was done.

If the record specified on the get-relative operation is not active, a not valid record number condition occurs (message CPF5020). This condition becomes a record-not-found condition in some high-level languages. See the appropriate high-level language manual.

Note: The get-relative operation and get-next-changed operation both update the relative record number in the input/output feedback area. Subsequent get-next-changed-record requests retrieve sequentially changed records greater than this relative record number.

Reading the Next Changed Record in a Subfile

The **get-next-changed operation** reads the next changed record in the subfile that is greater than the relative record number previously read with a get-relative or get-next-changed operation.

If the get-next-changed operation is used as the first read operation, the first changed record in the subfile is read. The entire record, including response indicators (defined at the file level and on fields in a subfile record), input, output, output/input, and hidden fields, is passed to the program, the relative record number is placed in the data management feedback area, and the record is reset to a *not changed* record. Response indicators defined at the file level are always

returned as off. Response indicators defined on fields in a subfile record, such as the BLANKS or CHANGE keywords, are returned as on or off depending on the information in the fields at the time the get operation was done.

If there are no more changed records in the subfile, a message (CPF5037) indicating that the last changed record has already been retrieved, is sent to the program. See the appropriate high-level language manual for a description of how this condition is reported to your program.

If a record retrieved by a get-next-changed operation is updated and the SFLNXTCHG keyword is specified for an updated record, the updated record is set again as a changed record. This allows the program to ensure that the user has changed the record. For example, if the program detects an error in a record, it is advantageous to require the user to correct the error. The use of the SFLNXTCHG keyword allows the program to read that record again on a get-next-changed operation so it can continue to reject the record until the error has been corrected. The next get-next-changed operation does not retrieve this updated record. The record cannot be retrieved again with a get-next-changed operation until all the changed records following it in the subfile have been processed. This is because the changed records are accessed sequentially and the sequence does not start at the beginning until after the message indicating that there are no more changed records in the subfile has been sent to the program. A get-next-changed operation following this message gets the first changed record in the subfile. Because no I/O operation has been issued to the display, any changed record would be a record that was processed using the SFLNXTCHG keyword.

Note: The get-relative operation and get-next-changed operation both update the relative record number in the input/output feedback area. Subsequent get-next-changed-record requests retrieve sequentially changed records greater than this relative record number.

Requesting I/O Operations for a Subfile Control Record Format

By requesting the correct I/O operation for a *subfile control record format*, you can do the following:

- Display subfile records
- Place the subfile records on the display into the subfile for processing by the program
- Display and process subfile records at the same time

Displaying Subfile Records

You can display subfile records by issuing a **write operation** to the subfile control record format.

You can control the write operation using the following DDS keywords:

SFLDSP	Display the subfile.
SFLDSPCTL	Display the subfile control record.
SFLCLR	Clear the subfile of active records.
SFLDLT	Delete the subfile.
SFLINZ	Initialize the subfile with active records, or if the SFLRNA keyword is specified, with inactive records. When the subfile is initialized, all option indicators in the subfile record are assumed to be off.
SFLEND	Notify the user when the last available record is displayed.
SFLRCDNBR	Display the specified page of the subfile.

Note: These keywords are described under “Describing Subfiles in Your DDS Source” on page 4-3.

Placing Subfile Records on the Display for Processing

A **read operation** must be issued to a displayed record format in order for the subfile records on the display to be placed into the subfile for processing by the program. The subfile records from the display are placed in their corresponding record positions in the subfile.

Displaying and Processing Subfile Records at the Same Time

The **write-read operation** is a single operation that combines the write and read operations and is more efficient than a single write operation followed by a single read operation.

Recognizing Subfile I/O Requests in High-Level Languages

Table 4-2 shows the I/O requests supported by the system and the equivalent high-level language operations:

Table 4-2. Subfile Operations Supported by the System and Equivalent HLL Commands

Operation	C/400 Function	RPG/400 Operation	COBOL/400 Statement	BASIC Statement
Put Relative	_Rwrited	WRITE, output specifications	WRITE SUBFILE	WRITE REC =
Update	_Rupdate	UPDAT	REWRITE SUBFILE	REWRITE REC =
Get Relative	_Rreadd	CHAIN	READ SUBFILE	READ REC =
Get Next Changed	_Rreadnc	READC	READ SUBFILE NEXT MODIFIED	READ MODIFIED
Write	_Rwrite	WRITE	WRITE	WRITE
Read	_Rread	READ	READ	READ
Write-Read	_Rwriterd, _Rformat, _Rpgmdev	EXFMT		

Controlling the Appearance of Subfiles

Records in a subfile can be displayed either vertically or horizontally. In a vertically displayed subfile, a record is displayed on one or more lines, with each record beginning a new line (see Figure 4-2 on page 4-13). In a horizontally displayed subfile, a record is complete on one line, and more than one record is displayed on a line (see Figure 4-3 on page 4-13). You can specify that a subfile is to be displayed horizontally by using the SFULLIN keyword to define the number of spaces between each subfile record on a display line. Figure 4-4 on page 4-13 shows an example of a vertical subfile and a horizontal subfile being displayed at the same time.




Figure 4-2. Vertically Displayed Subfile




Figure 4-3. Horizontally Displayed Subfile




Figure 4-4. Horizontally and Vertically Displayed Subfiles Displayed at the Same Time

If a subfile is larger than the space allowed for the subfile on the screen, the user can roll the display from one group of records in the subfile to another. Each group of records displayed at the same time is called a page. When you create a display file with a subfile, you must specify the size of the page for a subfile by specifying the number of records in the page (SFLPAG keyword). Usually page size is based on the number of lines available on the display. You must also specify the size of the subfile by specifying the number of records in the subfile (SFLSIZ keyword).

Page size and subfile size can be the same; that is, all records in the subfile fit on one page. When page size equals subfile size, variable-length subfile records are supported. One record can take up only a single line while another record can take up more than one display line. Each record is placed in the first record position available in the subfile; this position is always a new line. In addition, the SFLDROP and SFLROLVAL keywords are ignored by display station support when page size equals subfile size.

For more information on page size and subfile size, see “Specifying Subfile Size Equal to Page Size” on page 4-15 and “Specifying Subfile Size Not Equal to Page Size” on page 4-17.

Note: For the initial display of a subfile, the more records placed in a subfile before it is displayed, the slower the response time.

You can use the display mode (DSPMOD) keyword to specify which of the two **modes** (or display sizes), 24x80 or 27x132, you want to use for your display station.

The following example shows how to specify DSPMOD with subfiles:

	1	2	3	4	5	6	7
A						DSPSIZ(*DS4 *DS3)	
A	R	SFLR				SFL	
A		FLD1	8	0	1	5	
A		FLD2	7	I	1	16	
A		FLD3	7	B	1	24	
A	R	SFLCTLR				SFLCTL(SFLR)	
A						SFLDSP	
A						SFLDSPCTL	
A						SFLSIZ(60)	
A						SFLPAG(12)	
A						SFLLIN(4)	
A	*DS3					SFLIN(6)	
A	02					SFLEND	
A	10					DSPMOD(*DS3)	
A							
A							

In the previous example, if the user's program turns indicator 10 off and issues a write-read operation to the subfile control record format (SFLCTLR), the subfile is displayed as follows:

- #### 4-14 AS/400 Guide to Programming Displays

The following example shows the subfile displayed in *DS4 mode.

RECORD 1	RECORD 4	RECORD 7	RECORD 10
RECORD 2	RECORD 5	RECORD 8	RECORD 11
RECORD 3	RECORD 6	RECORD 9	RECORD 12

If the user presses the Enter key, control is returned to the user's program. If the user's program turns on indicator 10 and then issues another write-read operation to the subfile control record format (SFLCTLR), the subfile is displayed as follows:

- *In 24 by 80 (*DS3) mode*, because indicator 10 for the DSPMOD keyword is on.
- *Horizontally*, because SFLLIN is specified for the *DS3 mode. If SFLLIN was not specified for the *DS3 mode, the subfile would have been displayed vertically. If the SFLLIN keyword is to be used for more than one screen size, a screen size condition name for each secondary screen size is required. Because each record is 30 bytes long and the space between each record is 6 bytes long, two records can be displayed on one horizontal line, $(2 \times 30) + 6 = 66$ bytes). The subfile is displayed on six lines because SFLPAG(12) is specified. To ensure other records are not erased, the SFLPAG may need to be specified for the secondary screen size.

The following example shows the subfile displayed in *DS3 mode.

RECORD 1	RECORD 7
RECORD 2	RECORD 8
RECORD 3	RECORD 9
RECORD 4	RECORD 10
RECORD 5	RECORD 11
RECORD 6	RECORD 12

Specifying Subfile Size Equal to Page Size

You must specify the size of the subfile and the number of subfile records to be displayed at one time with the SFLSIZ and SFLPAG keywords. The use of subfile size equals page size is recommended when the number of subfile records to be displayed will fit on one page or when the number of records to be placed in the subfile is unknown and large. It is not an efficient use of resources to retrieve many database records to fill a large subfile if the user normally finds the needed information on the first page.

When subfile size equals page size, the system does not automatically support the use of the Roll Up and Roll Down keys. If you want the user to roll through the

subfile using these keys, you must specify the ROLLUP or ROLLDOWN keyword in the subfile control record, and your program must handle the roll up or roll down function.

For example, if a subfile is used to allow the user to search through a long list, you can specify SFLSIZ equals SFLPAG and ROLLUP on the subfile control record:

...+....1....+....2....+....3....+....4....+....5....+....6....+....7...	
A	R SFLCTLR
A	SFLCTL(SFLRCD)
A	SFLSIZ(16)
A	SFLPAG(16)
A	ROLLUP(20 'Roll Up')

Figure 4-6. Sample DDS Using SFLSIZ, SFLPAG, and ROLLUP Keywords

When the user presses the Roll Up key, indicator 20 is set on and control returns to the program. In your program, you would:

- Clear the subfile (a write operation to the subfile control record with the SFLCLR keyword in effect).
- Use the indicator to control a return to the logic that fills the subfile with another page of records.
- Display the new subfile page.

You could also allow the display station user to press a CFnn key to return to the start of the search. When the user presses the CFnn key, the associated indicator is set on and control returns to the program. In your program, you would:

- Clear the subfile.
- Use the indicator to control a return to the logic that built the first subfile page based on the search code entered. (The program needs to keep the original search code in order to do this.)

Using the ROLLDOWN keyword when subfile size equals page size requires more lines of code in the program because the program must keep track of the record position in the subfile and in the database file.

When the subfile size equals page size, you can use field selection and variable-length records in the subfile. If you use field selection, consider the following:

- If the fields are selected through the use of option indicators, the relative record number is ignored and each record is placed in the first available record position in the subfile.
- If a record is being updated, the field selection that does not match that on the original output is ignored. For example, assume that FIELD1 and FIELD2 are selected when the record is placed in the subfile. If the update selects FIELD2 and FIELD3, fields would overlay the original FIELD1 and FIELD2 fields, and the results could not be predicted.
- If field selection is specified on the subfile record, the number of records that can be displayed on the screen depends on the number of fields selected. When field selection is specified, the SFLPAG(value) keyword specifies the number of screen lines available to display the subfile record. In other cases, the SFLPAG(value) keyword specifies the number of subfile records that can be displayed at one time.

- The SFLFOLD, SFLDROP, and SFLROLVAL keywords are ignored.

When variable-length records are used, each record in the subfile is displayed beginning on the first available line on the page. If you use field selection for variable-length records, each record can take up a different number of lines on the display. Therefore, the number of records that actually fit in the subfile depends on the field selection of each record written to the subfile. The following shows an example of the DDS for a variable-length record:

```
|....+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R SFLRCD                      SFL
A          ITMNR 8Y 0 6 2
A          ITMDSC 15 6 11
A          QTYOH 4 0 6 28
A          LSTPC 7 2 6 39
A          ALLOH 8Y 0 6 49
A          SLSMO 10 2 6 63
A N80      SLSYR 12 2 7 7
A N80      CSTYR 12 2 +3
```

Figure 4-7. Sample DDS for a Variable-Length Record

When indicator 80 is on, each record in the subfile fits on one line. However, when indicator 80 is off, each record uses two lines on the display.

Another typical use of variable-length records is where two or more entirely different formats are used to make up one format. In this case, each field would be separately conditioned by option indicators so that one record format might use multiple lines while another format uses only one line.

Specifying Subfile Size Not Equal to Page Size

Subfile size not equal to page size should be used when a finite number of records can be placed in the subfile and that number is small (for example, 50). The SFLSIZ keyword specifies the subfile size. The system allocates space to contain the subfile records based on the value specified for SFLSIZ. You should specify a value equal to the number of records that you normally have in the subfile. If your program places a record with a relative record number larger than the SFLSIZ value into the subfile, the system extends the subfile to contain it (up to a maximum of 9999 records).

When the subfile size is not equal to the page size, the use of the Roll Up and Roll Down keys is automatically supported.

To inform the user that there are more records in the subfile, use the SFLEND keyword on the subfile control record. When SFLEND is in effect (for example, the option indicator is on), a + (plus sign) is placed in the lower position to the extreme right of the screen on each page except the last page. On the last subfile page, the + is replaced with a blank.

When the subfile size is not equal to page size, you can use the SFLROLVAL keyword to allow the user to enter a value to specify how many records should be rolled up or down when the appropriate key is pressed. If the SFLROLVAL keyword is not used, the subfile is rolled by the SFLPAG value except for subfiles

using SFLFOLD or SFLDROP. If the SFLFOLD or SFLDROP keyword is used, more records are displayed than the SFLPAG value when records are displayed in the truncated format. For truncated records, the display rolls by the number of records displayed in the truncated format. When the SFLROLVAL keyword is used and the Roll Up key is pressed, the uppermost record number in the displayed subfile is added to the roll value to determine the new uppermost record number. If this value is greater than the last record in the subfile, the last full page of records is displayed. If the Roll Up key is pressed when the last subfile page is displayed and the roll value is not less than the page size value, an error message is issued. If the roll value is less than the page size value, the roll function is performed.

Variable-length records and field selection cannot be used when the subfile size is not equal to the page size.

A technique to improve performance when you are using a multiple page subfile is to write only one page of subfile records at a time but use the OS/400 support to roll through the subfile. To do this, you need to define the ROLLUP keyword in DDS with a response indicator and also use the SFLRCDNBR keyword. In your program, you would write the records needed to fill one subfile page and then display that page. When the user wants to see more records, he or she presses the Roll Up key. The program then writes another page of records to the subfile, places the relative record number of a record from the second page into the SFLRCDNBR field, and displays the record.

The second page of subfile records is now displayed, and if the user presses the Roll Down key, the roll down is handled by the system. If the user presses the Roll Up key while the first page is displayed, the system will also handle the roll up. The program is notified only when the user attempts to roll up beyond the records currently in the subfile. The program would then handle any additional roll up requests in the same manner as for the second page. When you use this technique, the subfile appears to be more than one page because of the use of the roll keys. Yet, you can maintain good response time because the program only fills one subfile page before writing it to the display.

Checking Validity on Subfile Data

In addition to the DDS validity checking keywords (CHECK, COMP/CMP, RANGE, and VALUES), you can also do validity checking on subfile data in your program and require the user to correct the error.

For example, assume that you are using a subfile for an order entry program and you want to check the item number field to be sure it is a valid order number. You also want to check the quantity ordered field to ensure there are enough items on hand to fill the order. To do this, you can use the SFLNXTCHG keyword on the subfile record (SFL) to allow your program to diagnose the errors and require the user to correct them. The following DDS shows an example of using the SFLNXTCHG keyword:

```

|...+...1....+...2....+...3....+...4....+...5....+...6....+...7...
A          R ORDENTD
A
A          1 30'ORDER ENTRY DISPLAY'
A          3 2'Enter customer number:'
A          CUST          5          3 25
A          R SFLRCD          SFL
A 61          SFLNXTCHG
A          LINNBR          2          7 4
A          ITMNB          5  B 7 9
A 40          DSPATR(RI PC)
A          QTYORD          4  B 7 20
A 35          DSPATR(RI PC)
A          R SFLCTL          SFLCTL(SFLRCD)
A          SFLSIZ(5)
A          SFLPAG(5)
A 55          SFLDSP
A 50          SFLDSPCTL
A 30          SFLCLR
A 10          SFLINZ
A 40          SFLMSG('Item number not valid' 40)
A 35          SFLMSG('Qty not available' 35)

```

Figure 4-8. Sample DDS Using the SFLNXTCHG Keyword

When the program detects an error, it sets on the indicator that conditions the SFLNXTCHG keyword and issues a write operation to the subfile control record with the SFLDSP keyword in effect. The field in error is displayed in reverse image, and the cursor is positioned at that field. The associated error message is also displayed. The user then corrects the error.

A decision you must make when using the SFLNXTCHG keyword is whether to allow the user to change the subfile fields that were not in error. If you do not want the display station user to change those fields you can protect them with the DSPATR(PR) keyword. For those fields you do not want changed, the DSPATR(PR) keyword must be in effect only when the SFLNXTCHG keyword is in effect. If you allow the user to change the fields, you can:

- Define hidden fields for those fields that are to be checked.
- Move the data originally entered by the user into the hidden fields when an error occurs on a subfile.
- Compare the data in the hidden fields to the fields just read to identify which fields have been changed so you can update the records that have already been processed when the user makes the changes.

Displaying Error Messages from Subfiles

You can use a subfile to display messages for multiple errors. The messages to be placed in the subfile are on a program message queue. Each message written to the subfile is displayed on a separate line and is truncated, if necessary. Each message line contains an attribute character in position 1 that is displayed as a blank, followed by the message text. For the 24 by 80 display mode, 76 characters are displayed. For the 27 by 132 display mode, 128 characters are displayed. Because both the message identifier and the message data are available from the program message queue, message help and substitution text are supported for the

messages placed in a message subfile. If the SFLMSGRCDD keyword is specified, the SFLPGMQ and SFLMSGKEY keywords must also be specified.

The following shows an example of the DDS for a message subfile:

	1	2	3	4	5	6	7
A	R	MSGSFL			SFL		
A					SFLMSGRCDD(14)		
A		MSGKEY			SFLMSGKEY		
A		PGMQ			SFLPGMQ		
A	R	MSGCTL			SFLCTL(MSGSFL)		
A					SFLSIZ(8)		
A					SFLPAG(8)		
A	50				SFLDSP		
A	55				SFLDSPCTL		
A	60				SFLINZ		
A		PGMQ			SFLPGMQ		
A		NBR	4	0H	SFLRCDNBR(CURS)		
A							

Figure 4-9. Sample DDS for a Message Subfile

The SFLRCDNBR(CURS) keyword is used to position the cursor at the first displayed character in the message subfile that is specified in the SFLRCDNBR field so the Roll Up and Roll Down keys will apply to the message subfile.

For information on sending and receiving messages and on the program message queue, see the *CL Programmer's Guide*. Message subfiles are the only kind of subfiles supported for CL programs and for C/400 programs.

Positioning the Cursor on the Displayed Subfile

The DSPATR(PC) keyword lets you position the cursor for each page of the subfile record that is displayed. Write and update operations can be used to control DSPATR(PC) for:

- The initial display of subfile records. (A write or write-read operation to the subfile control record when the SFLDSP and SFLDSPCTL keywords are used.)
- Subfile records displayed using a roll key or a fold or truncate key (SFLDROP or SFLFOLD keywords).

Positioning the Cursor Initially

The cursor is positioned by the first of the following conditions that applies:

- The CSRLOC keyword on the subfile control record.
- The DSPATR(PC) keyword within the records being displayed.
- The DSPATR(PC) keyword within a field in the subfile control record.
- The SFLRCDNBR(CURS) keyword within the subfile control record.
- If nothing is specified, the cursor is positioned at the first input-capable field on the display.

Note: If the keyboard is unlocked prior to the output operation that displays the subfile, explicit cursor positioning is not performed.

Use the keywords in the following order:

- The CSRLOC keyword can be used to position the cursor anywhere on the screen.
- The DSPATR(PC) keyword can be used to position the cursor at any field in the first record displayed when the output operation specifies the SFLDSP keyword.
- The DSPATR(PC) keyword can be used to position the cursor at any field of the subfile control record.
- The SFLRCDNBR(CURS) keyword can be used to position the cursor at the first input-capable field of the record whose record number is used to select which page is to be displayed first. If no input fields exist, the cursor is positioned at the first selected output field in that record.
- If neither the DSPATR(PC) nor SFLRCDNBR(CURS) keyword is used, the cursor is positioned at the first input-capable field on the display.

Positioning the Cursor When a Roll Key Is Used

The positioning of the cursor when a roll key is used depends on whether the DSPATR(PC) keyword is used:

- If the DSPATR(PC) keyword is not used, the cursor is positioned at the same location as when the roll key was pressed.
- If the DSPATR(PC) keyword is used, the cursor is positioned at the first field in the displayed subfile records with the DSPATR(PC) keyword in effect.

The following example illustrates both and shows part of the DDS for a subfile in which records are displayed vertically. Customer number, name, address, city, and state are displayed. A user can change customer name, address, city, and state. Customer number cannot be changed; it is an output field only. The DSPATR(PC) keyword has been specified for the customer number field (CUST). Subfile size is 21 and page size is 7.

```

|...+...1....+...2....+...3....+...4....+...5....+...6....+...7...
A          R SUBFIL1                      SFL
A          TEXT('Subfile record')
A          CUST          5      4  3DSPATR(PC)
A          NAME          20    B  4 10CHECK(LC)
A          ADDR          20    B  4 32CHECK(LC)
A          CITY          20    B  4 54CHECK(LC)
A          STATE         2     B  4 76
A          R FILCTL1                      SFLCTL(SUBFIL1)
A 50                      SFLDSPCTL
A 55                      SFLDSP
A                      SFLSIZ(21)
A                      SFLPAG(7)
A 60                      SFLCLR
A                      TEXT('Subfile control record')
A                      OVERLAY
A                      PROTECT
A                      CA03(98 'End of program')
A                      2  2'NUMBER'
A                      2 10'NAME'
A                      2 32'ADDRESS'
A                      2 54'CITY'
A                      2 76'STATE'

```

Figure 4-10. Sample DDS Using the DSPATR(PC) Keyword

The initial display looks like this:

Cursor

NUMBER	NAME	ADDRESS	CITY	STATE
41394	Sorensen and Walton	500 5th Avenue	New York	NY
41395	Charland, Inc.	200 Madison Avenue	New York	NY
41316	Anderson's Electric	950 2nd Avenue	Atlanta	GA
41397	Morem Motors	1300 Pine Street	Atlanta	GA
41398	Polt Electronics	240 Walters Place	Chicago	IL
41399	Clark's TV	560 3rd Street	Chicago	IL
41400	Jim's Repair	700 4th Avenue	Chicago	IL

RSLH709-0

The first seven records in the subfile are displayed and the cursor is positioned under the customer number in the first record. The user moves the cursor to the third record, updates the address for that customer, and moves the cursor to the customer number of the fourth record:

Cursor

Changed Field

NUMBER	NAME	ADDRESS	CITY	STATE
41394	Sorensen and Walton	500 5th Avenue	New York	NY
41395	Charland, Inc.	200 Madison Avenue	New York	NY
41316	Anderson's Electric	950 2nd Avenue	Atlanta	GA
41397	Morem Motors	1300 Pine Street	Atlanta	GA
41398	Polt Electronics	240 Walters Place	Chicago	IL
41399	Clark's TV	560 3rd Street	Chicago	IL
41400	Jim's Repair	700 4th Avenue	Chicago	IL

RSLH183-0

Now the user presses the Roll Up key to display the next seven records. The cursor is positioned under the customer number in the first record:

Cursor

NUMBER	NAME	ADDRESS	CITY	STATE
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
41403	Advanced Electronics	809 8th Street	St Paul	MN
41404	Riteway Repair	443 Western Lane	New York	NY
41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL
41406	Hall's Electric	200 Main Street	St Paul	MN
41407	Electric House	903 East Place	Atlanta	GA

RSLH184-0

If the DSPATR(PC) keyword had not been specified and the user pressed the Roll Up key, the cursor would have been positioned at the fourth record under customer number:

Cursor

NUMBER	NAME	ADDRESS	CITY	STATE
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN
41403	Advanced Electronics	809 8th Street	St Paul	MN
41404	Riteway Repair	443 Western Lane	New York	NY
41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL
41406	Hall's Electric	200 Main Street	St Paul	MN
41407	Electric House	903 East Place	Atlanta	GA

RSLH185-0

Positioning the Cursor When a Fold or Truncate Key Is Used

When you use the SFLFOLD or SFLDROP keyword to assign a CFnn or CAnn key, cursor positioning is handled the same way as described under “Positioning the Cursor When a Roll Key Is Used” on page 4-21. The cursor is positioned as specified for all displayed records, including those folded. When you use the SFLFOLD or SFLDROP keyword to assign a CFnn or CAnn key, the cursor is positioned only for those fields displayed. Cursor positioning specifications for fields in the folded portion of the record are ignored.

Positioning the Cursor and Rolling When Two or More Records Are Displayed

When you display two or more records at the same time, the position of the cursor determines the action taken when the user presses a roll key, regardless of which record was written to the display last.

The cursor can be positioned in the *roll-enabled area* of the display or in the area that is *not roll-enabled* of the display. A *roll-enabled area* is:

- A record without subfiles and with the ROLLUP/ROLLDOWN keyword in effect
- A subfile control record with the ROLLUP/ROLLDOWN keyword in effect
- A roll-enabled subfile, which is an active subfile with subfile size greater than page size
- An active subfile with subfile size equal to page size and the ROLLUP/ROLLDOWN keyword in effect for its subfile control record

Based on the location of the cursor, the action taken when the user presses a roll key is as follows:

- If the cursor is positioned in the roll-enabled area at a roll-enabled subfile or at the subfile control record for a roll-enabled subfile, the subfile is rolled. If the subfile is at the end of the subfile and the corresponding ROLLUP/ROLLDOWN keyword is not in effect, the end-of-subfile message is sent to the user. If the ROLLUP/ROLLDOWN keyword is in effect at the end of the subfile, control returns to the program.
- If the cursor is positioned in the roll-enabled area at a record without subfiles with the ROLLUP/ROLLDOWN keyword in effect, at a subfile control record with the ROLLUP/ROLLDOWN keyword in effect, or at an active subfile with subfile size equal to page size and the ROLLUP/ROLLDOWN keyword in effect for the subfile control record, control returns to the program.
- If the cursor is not positioned in the roll-enabled area, the system attempts to find the uppermost roll-enabled area on the display and perform the action indicated, as listed previously. If there is no roll-enabled area on the display, the command-key-not-valid message is sent to the user.

Note: Records that do not occupy display space (record formats with no fields, with hidden, program-to-system, or message fields only, or with the CLRL keyword specified and no input-capable fields; and message subfiles) are assumed to be at line 0. Therefore, these records are considered to be uppermost on the display, and the system attempts to roll them first.

The following examples illustrate what action is taken, based on the location of the cursor, when two records are displayed and the user presses a roll key.

In the following example, control returns to the program if the corresponding ROLLUP/ROLLEDOWN keyword is in effect. This occurs because the cursor is positioned at a record without subfiles and with the ROLLUP/ROLLEDOWN keyword in effect.

NUMBER	NAME	ADDRESS	CITY	STATE	
41394	Sorensen and Walton	500 5th Avenue	New York	NY	
41395	Charland, Inc.	200 Madison Avenue	New York	NY	
41316	Anderson's Electric	950 2nd Avenue	Atlanta	GA	
41397	Morem Motors	1300 Pine Street	Atlanta	GA	
41398	Polft Electronics	240 Walters Place	Chicago	IL	+

Enter next customer number: _____

RV2W050-0

Cursor

Subfile with SFLSIZ> SFLPAG

Nonsubfile Record with ROLLUP/ROLLEDOWN in Effect

In the following example, two subfiles with the subfile size greater than the page size and their control records are displayed. The user positions the cursor in the bottom subfile control record. The bottom subfile is rolled because the cursor is positioned at a roll-enabled subfile in the roll-enabled area of the display.

NUMBER	NAME	ADDRESS	CITY	STATE	
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL	
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN	
41403	Advanced Electronics	809 8th Street	St Paul	MN	
41404	Riteway Repair	443 Western Lane	New York	NY	
41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL	+

NUMBER	ORDER NUMBER	LINE NUMBER	DESCRIPTION	QTY	Price	TOTAL PRICE
41401	35900	1	E35 Motor	10	15.00	150.00
41401	35400	2	F60 Pump	25	20.00	500.00

RV2W051-0

Cursor

Subfile 1 with SFLSIZ> SFLPAG

Subfile 2 with SFLSIZ> SFLPAG

In the following example, a subfile with the subfile size equal to the page size and the ROLLUP/ROLLDOWN keyword in effect is written to the display first. A record without subfiles and without the ROLLUP/ROLLDOWN keyword in effect is then written to the display. If the cursor is positioned at either the subfile record or the second record, control returns to the program.

Cursor

NUMBER	NAME	ADDRESS	CITY	STATE	
41394	Sorensen and Walton	500 5th Avenue	New York	NY	
41395	Charland, Inc.	200 Madison Avenue	New York	NY	
41316	Anderson's Electric	950 2nd Avenue	Atlanta	GA	
41397	Morem Motors	1300 Pine Street	Atlanta	GA	
41398	Polt Electronics	240 Walters Place	Chicago	IL	+

Enter next customer number: _____

RV2W052-0

Subfile with SFLSZ> SFLPAG

Nonsubfile Record without ROLLUP/ROLLDOWN

In the following example, the first subfile has a subfile size greater than the page size but the ROLLUP/ROLLDOWN keyword is not specified. The second subfile has a subfile size equal to the page size but the ROLLUP/ROLLDOWN keyword is not specified. If the cursor is positioned at the second subfile, the first subfile is rolled. In this position, the cursor is not in a roll-enabled area; therefore, the system finds the uppermost roll-enabled area in the display and performs the roll function.

NUMBER	NAME	ADDRESS	CITY	STATE	
41401	Adam's Home Repair	121 Golden Circle	Chicago	IL	
41402	Jane's Radio/TV	135 Ransom Drive	St Paul	MN	
41403	Advanced Electronics	809 8th Street	St Paul	MN	
41404	Riteway Repair	443 Western Lane	New York	NY	
41405	Fixtures, Inc.	607 9th Avenue	Chicago	IL	+

NUMBER	ORDER NUMBER	LINE NUMBER	DESCRIPTION	QTY	Price	TOTAL PRICE
41401	35900	1	E35 Motor	10	15.00	150.00
41401	35400	2	F60 Pump	25	20.00	500.00

Subfile with
SFLSIZ>
SFLPAG
and without
ROLLUP/
ROLLDOWN

Subfile with
SFLSIZ=
SFLPAG
and without
ROLLUP/
ROLLDOWN

Cursor

RV2W053-1

In the following example, the subfile with a subfile size greater than the page size and without ROLLUP/ROLLDOWN keyword is written to the display first. The record without subfiles and with ROLLUP/ROLLDOWN keyword in effect is then written to the display above the subfile. If the cursor is positioned within the subfile record, the subfile is rolled. If the cursor is not positioned within the subfile record, the subfile is not rolled and control returns to the program.

Identifiers Highlight Command Prompt Exit Help

===== Top-of-File =====
RTYP CMGR
===== Bottom-of-File =====

Select a Router identifier and press Enter.

RTYP Type of router.
RTCU common user ID.
RTDN Default system name.
RMTN Name of Remote LU alias.
LCLN Name of Local LU alias.
MODN Mode name information.

Enter Esc=Cancel F1=Help

RSLH054-0

Understanding Subfile DDS and Program Logic–Example

The following shows the DDS that describes the customer name search subfile shown earlier in this section. The DDS is followed by a description of the logic a program would use to process this subfile.

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A** DISPLAY CUS220D  CUSTOMER NAME SEARCH
A                                     CF03(99 'End of Program')
A          R NAMESR                                     OVERLAY
A                                     1 29 'CUSTOMER NAME SEARCH'
A                                     3  2 'Search code'
A          SEARCH          5   I  3 15
A          R SUBFIL1                                     SFL
A          CUST          5       7  2
A          NAME        20    B  7  9
A          ADDR        20    B  7 31
A          CITY        20    B  7 53
A          STATE       2     B  7 75
A          R FILCTL                                     SFLCTL(SUBFIL1)
A 55                                     SFLDSPCTL
A 50                                     SFLDSP
A                                     SFLSIZ(18)
A                                     SFLPAG(6)
A 50                                     SFLEND
A 60                                     SFLCLR
A                                     OVERLAY PROTECT
A          RCDNBR          2  0H  SFLRCDNBR(CURS0R)
A 45                                     5  2 'NUMBER'
A 45                                     5  9 'NAME'
A 45                                     5 31 'ADDRESS'
A 45                                     5 53 'CITY'
A 45                                     5 75 'STATE'
```

Figure 4-11. Sample DDS Showing Customer Name Search Subfile

The following is an example of the logic a user program would use to process the subfile just shown. A write-read operation is a combined input and output operation. A read is an input operation. A write is an output operation. See the appropriate high-level language manual for the operations that can be performed in the high-level language program.

User Program

1. Opens a file and issues a write-read operation to the NAMESR record format to prompt for a search code.

User

2. Enters a zip code in the search code field. The program uses the search code field as a key field to find the first database record in the file with that key field. The program will build the subfile using that record as the first record in the subfile.

User Program

3. Obtains records (read operation) from the database file and places (write operation to SUBFIL1) them in the subfile one record at a time until the subfile is full or there are no more records to place in the subfile.
4. When all records are in the subfile, issues a write-read operation to the subfile control record format (FILCTL) with the following:
 - a. A + (plus sign) is displayed in the lower right corner of the screen when there are more records than fit on one subfile page. Because the indicator for the SFLEND keyword is on, the system replaces the + with a blank when the last subfile page is displayed.
 - b. The indicator for the SFLDSP keyword is on, so the first subfile page is displayed.
 - c. The indicator for the SFLDSPCTL keyword is on, so the subfile control record is displayed.
 - d. The SFLRCDNBR(CURS) keyword is specified for a field. The program placed a value of 1 in this field, so the subfile page that contains relative record number 1 is displayed first and the cursor is positioned at the first input field in that record. (If no input field exists, the cursor is positioned at the first selected output field or constant in that record.)
 - e. The constant field (heading line) indicators are on, so the constants in the subfile control record are displayed.
 - f. The OVERLAY and PROTECT keywords are in effect in the subfile control record so that the prompt (NAMESR) can remain on the display without being changed.

User

5. Updates displayed records, using the roll keys to display different subfile records as needed. Presses the Enter key after completing all updates to the subfile.

User Program

6. Completes the input portion of the write-read operation to the subfile control record format. In this example, the subfile control record does not contain any input fields. The input portion of the write-read operation allows the display station user to enter data into the subfile.
7. Issues the get-next-changed operation to the subfile record to process the first subfile record changed by the user.
8. Uses each changed record to update the corresponding database file record.
9. Repeats steps 7 and 8 until a no-more-modified-records condition exists for step 7. When this condition is detected, step 10 is performed.
10. Issues a write-read operation to the prompt (NAMESR) to determine if the program should end or display another group of database records. The OVERLAY keyword is specified, so that the current display contents for the subfile are left unchanged. If the user presses the CF1 key, which turns on response indicator 99, the program will close the display file and end. If the user enters another search code for another group of records to be displayed, step 11 is performed.
11. Issues a write operation to the subfile control record (FILCTL) with the following:
 - a. The indicator for the SFLCLR keyword is on, so the subfile is cleared of all records (the display is unchanged).

- b. The indicator for the SFLDSP keyword is off, so the contents of the display remains unchanged.
 - c. The indicator for the SFLDSPCTL keyword is off, so the subfile control record is not displayed again.
12. Repeats steps 3 through 10. The subfile was cleared (SFLCLR keyword) in step 11 so that new records can be placed in the subfile. The write operation to the subfile control record in step 4 has the constant field indicator off so that heading information is not sent to the display again. As long as the subfile control record remains on the display (no intervening write operations without the OVERLAY keyword in effect have been performed), the fields do not have to be sent to the display again.

Chapter 5. Defining Windows with Display Files

This chapter explains how to use the specialized DDS window keywords to create windows in your applications. The DDS window keywords provide the simplest, most flexible method of creating windows for a variety of purposes. For example, they allow you to use subfiles to present data in windows, to have the system automatically save and restore the underlying display, and to position data in the window by referring to positions in the window itself instead of positions on the full screen.

Use the DDS window keywords if your windows must use other DDS functions, such as subfiles, display attributes, validity checking, and optioning. Also use the DDS window keywords when the window contains multiple input fields, or if the window location can be varied.

If you have help information defined with DDS and are using the HLPRCD keyword to display it, the WINDOW keyword can be used to easily display the information in a window.

The following sections describe the terminology used for windows, the functions of the window keywords, and how to use the keywords for the following tasks:

- Creating windows
- Defining window borders
- Reading data from windows
- Changing window borders and contents
- Moving and duplicating windows
- Making two windows seem active at one time
- Making one window in a series stand out
- Removing windows
- Improving application performance by bypassing system save and restore operations

For examples on using the window keywords, see “Programming Examples” on page 5-14.

For some applications, you might want to use a different method of creating windows:

- Chapter 20, “Defining Online Help Information” on page 20-1 describes how to create help windows with the user interface manager (UIM). The UIM uses a different language from DDS. However, it automates many help window functions for you and provides a simple way of adding online help information to your existing applications.
- The *IBM WindowTool/400 PRPQ*, SC41-0050-00, describes how to create windows with the WindowTool/400 PRPQ. Consider using this program if you use windows primarily to construct application menus.
- Chapter 6, “Creating a Graphical Look for Displays” describes how to create menu bars, pull-down menus, selection fields, continued-entry fields, and how to use edit masks using DDS keywords.

Window Terminology

A **window** is information that overlays part of the display. The user can view information inside the window and the portion of the display that is not overlaid by the window. However, only the window is active; the user cannot work with the underlying display. When more than one window is displayed, only one window is active at a time.

The **active window** is the window subject to the most recent input or output operation. The active window appears to be the topmost window on the display. It is the only part of the display with which the work station user can interact.

A window remains on the display until your application or the system takes action to remove it. Removing a window and overlaying a window are different operations. When a window is **removed**, it no longer exists on the display, and you can no longer write to or read from it. When a window is **overlayed** by another window, it might not be visible to the work station user; however, it is still available for you to work with.

DDS Window Keywords

Four DDS keywords allow your applications to create and work with windows:

WINDOW (Window)

Creates a window on the display, changes the contents of an existing window, or makes an existing but inactive window active again.

WDWBORDER (Window Border)

Specifies the color, display attributes, and characters of a window border.

RMVWDW (Remove Window)

Removes other windows from the display when a new window is displayed or when an existing window is redisplayed as the active window.

USRRSTDSP (User Restore Display)

Prevents the OS/400 system from automatically saving and restoring the underlying display when windows are displayed and removed. In some situations, save and restore operations are unnecessary; bypassing them speeds up your application. You can also use the USRRSTDSP keyword to make an earlier window in a series pop up and overlay later windows, and to make two windows seem active at the same time.

For detailed reference information about each keyword, see the *Data Description Specifications Reference*, SC41-9620.

Window Representation and Hardware Configuration

Window borders appear differently, depending on the type of display station and work station controller you are using.

For more information on how windows appear on different hardware configurations, see "Hardware Configuration" on page 6-2.

Creating Windows

The record-level keyword `WINDOW` allows a record format to be displayed inside a window. A maximum of 12 windows can be created on a display at one time.

To create a window, write a record that specifies a `WINDOW` keyword. The first window record you write must be a window definition record specifying the window size and its location on the display. The window definition record places the window borders on the display. Then you can write the same window definition record again or use one or more window reference records to complete the specifications for the window.

Window Definition Records

A window definition record is a record containing a `WINDOW` keyword that defines the window size and location. Size and location attributes include the position of the upper left corner of the window border and the number of rows and columns within the window.

A window definition record must be the first record written for each window you display. It is the record that actually creates the window and makes it visible on the display. The record can contain the same types of fields or data found in any typical record. It can also contain a `WDWBORDER` keyword defining the window border. (The `WDWBORDER` keyword can also be used at the file level.)

You can supply all the specifications for the window in the window definition record. You can supply additional specifications by writing the same window definition record again, as you would when displaying an error message in the window. You can also supply additional specifications by writing one or more window reference records after you write the window definition record.

Window Reference Records

Window reference records provide additional data to be placed in the window. They allow you to display more than one record format in a window.


Each window reference record contains a `WINDOW` keyword specifying the name of the window definition record to which it applies. When the window reference record is written, the window definition record being referred to must be on the display. If the referenced record is not on the display, then a notify message stating that the window does not exist is returned to the application.

Window reference records do not contain size and position attributes, and any active `WDWBORDER` keywords are ignored.

You can use as many window reference records as needed to complete the window. However, you do not need to write any window reference records to display a window. You can display a window using only a window definition record.

Window Size and Location

The following diagram shows the parts of a window that is created when a window definition record is displayed:



Key:

- L** Left border attribute
- .** Top and bottom border
- R** Right continuation attribute
- :** Left and right border
- A** Leading window attribute
- w** Window area
- m** Message line
- B** Right border attribute

This window is specified as having a depth of 13 rows (also known as lines) and a width of 19 columns (also known as positions). The usable area inside the window borders is 12 rows deep and 19 columns wide. Row 13 is reserved for messages; it cannot contain fields.

With its border, the window actually takes up additional rows and columns on the display. All windows take up two more rows, one each for the top and bottom borders. Most windows also take up six more columns:

- Two for border attributes
- Two for border characters
- One for the leading window attribute
- One for the continuation attribute on the right.

If a window starts and ends in the first and last columns of the full display, it takes up only four more columns instead of six. If a window row overlays DBCS fields, that row requires the six columns mentioned previously plus up to four more columns for DBCS shift-out and shift-in characters on each side.

The window is positioned by the upper left corner of the border, which has a starting row position equal to the top border row and a starting column position equal to the left border column. Fields that do not fit within the window are diagnosed during file compilation. If the SLNO keyword is used and specifies the starting line number, the DDS compiler flags any fields that do not fit within the window. If *VAR is specified on the SLNO keyword and the run-time starting line number does not allow the entire record to be displayed, an exception occurs.

The DDS compiler diagnoses window location problems when either the upper left window line or upper left window position is specified as a constant. A run-time error occurs if a dynamically positioned window does not fit on the display.

Cursor Position

To position the cursor in a window, use the CSRLOC and DSPATR(PC) keywords in the same way as for a full-screen display. The cursor is positioned with reference to the upper left corner of the usable area of the window.

When the cursor is moved outside the usable area of the active window, only the Print and Home command function (CF) keys are active. If the work station user presses any other command function (CF) key, the alarm sounds and the cursor is moved back to its position for the previous write operation.

Error Messages

When windows exist on a display and *MSGLIN is specified on the WINDOW keyword for the window, any error messages are displayed on the last usable line of the active window. The last usable line in the window is reserved for error messages; no records are displayed there. If the error message is longer than the line, it is truncated to fit. When windows exist on a display and *NOMSGLIN is specified on the WINDOW keyword for the window, any error messages are displayed at the bottom of the display or the location defined by the MSGLOC keyword.

Help is available through the Help key for error messages displayed in windows.

When messages reporting operational and keyboard errors, such as Function key not allowed, are displayed, the keyboard is locked and the user must press the Error Reset key to continue.

An informational message, stating that mismatching shift-out and shift-in characters were sent to the display, is placed in the job log under the following circumstances:

- The base display has a DBCS field that spans more than one line.
- A window is displayed and part of the DBCS field from the base display is on the window message line.
- A function key is pressed that results in an operational or keyboard error.

A few message-related keywords function differently when used for windows:

- The ERRSFL keyword is ignored. Its function is performed only when there are no windows on the display.
- The MSGLOC keyword is ignored if *MSGLIN is specified on the WINDOW keyword. Its function is performed only when there are no windows on the display or when *NOMSGLIN is specified on the WINDOW keyword.

- Messages resulting from the ERRMSGID, ERRMSG, SFLMSG, SFLMSGID, and DDS validity-checking keywords are displayed in the window but do not lock the keyboard. Such messages do lock the keyboard when displayed on full-screen displays.

Subfiles

A maximum of 24 subfiles can be active at any one time. A maximum of 12 subfiles can be displayed on the base display or in a single window at any one time.

If a subfile is displayed in a window and the window is removed from the display, the subfile is not deleted. The subfile remains active until the display file is closed or you explicitly delete the subfile.

DDS Help Records

If a window definition record is written to the display as a DDS help record, the current display is suspended as it normally is for application help, and the application help record is written to the display as a window. To avoid errors when using window records as help records, adhere to these requirements:

- Include the ASSUME keyword in the display file containing the help record. If the ASSUME keyword is not present, the rest of the display is blank while the help window is displayed.
- Use a value of *YES for the Restore Display (RSTDSP) parameter when creating, changing, or overriding the display file. When returning from help, RSTDSP(*YES) restores the suspended display and puts the cursor back where it was when the Help key was pressed.
- Use variable line and position values in your window definition record to allow the operating system to position the help window dynamically, according to cursor position. The system uses the following sequence of rules to position the window:
 1. If the window will fit below the cursor position on the display, it is placed there. The top window border is positioned one row below the cursor. If possible, the left window border is positioned in the same column as the cursor; if not, the window is positioned as far to the left of the cursor as necessary for it to fit on the display.
 2. If the window will fit above the cursor position, it is placed there. The bottom window border is positioned one row above the cursor. The window is positioned horizontally as described in step 1.
 3. If the window will fit to the right of the cursor position, it is placed there. The right window border is positioned in the next-to-last column of the display. If possible, the top window border is positioned in the same row as the cursor; if not, the window is positioned as far above that as necessary for it to fit on the display.
 4. If the window will fit to the left of the cursor position, it is placed there. The right window border is positioned two columns to the left of the cursor. The window is positioned vertically as described in step 3.
 5. If the window cannot be positioned in any of the above areas, it is placed in the bottom right corner of the display.

If the window definition record specifies that only the line value or only the position value is variable, the same rules are followed. However, the constant value is not changed.

Defining Window Borders

You can use the system defaults for your window borders or define them using the WDWBORDER keyword. This keyword specifies three border components: color, display attributes, and characters. More than one WDWBORDER keyword can be specified. You can use option indicators with the WDWBORDER keyword.

You can use the WDWBORDER keyword at the file level, where it applies to each window definition record in the file, or on individual window definition records. If you use it on window reference records, a warning message is issued when the file is created.

The following sections describe window border defaults, how the system handles multiple window border definitions, and how to use the WDWBORDER keyword to define UIM help window borders.

Border Defaults

When you do not use the WDWBORDER keyword, the system defaults are as follows:

Border Element	Default
Color	Blue on color displays. On noncolor display stations, this attribute is ignored.
Display attribute	Normal (that is, no attributes such as highlighting or reverse image)
Top and bottom border character	Period (.)
Left and right border character	Colon (:)
Top left and right corner character	Period (.)
Bottom left and right corner character	Colon (:)

Note: RUMBA/400 work stations and InfoWindow* II display stations attached to a controller that supports an enhanced interface have solid-line window borders. For more information, see Table 6-1 on page 6-2.

Multiple Border Definitions

When the WDWBORDER keyword is specified at the file level and in a window definition record, the parameter values of the keyword at the file and record level are combined. If the parameter values conflict, the record-level parameter value is used. For example, if the following is specified at the file level:

```
WDWBORDER((*COLOR RED) (*DSPATR RI))
```

and the following is specified at the record level:

```
WINDOW(2 5 10 20) +  
WDWBORDER((*COLOR GRN) +  
          (*CHAR '.....'))
```

then the window border consists of green periods in reverse image.

If more than one WDWBORDER keyword is specified at the same level, the parameters for the keywords that are in effect are combined. If different values are specified for the same parameter, the parameter value of the first keyword in effect is used. The values for individual components of the border are determined when a window definition record is written. The border values are determined by the following hierarchy:

1. Start with system defaults.
2. Override the defaults with any file-level border specifications.
3. Override any file-level border specifications with record-level border specifications.

The process is similar when more than one WDWBORDER keyword is in effect at the same level and the keywords specify the same WDWBORDER component (color, attribute, or character). The first component value is used. For example, assume that two WDWBORDER keywords are in effect at the file level:

```
WDWBORDER(*COLOR GRN
          *CHAR '.....')
WDWBORDER(*CHAR '---|||-|')
```

and the following is specified at the record level:

```
WDWBORDER(*COLOR BLU)
```

then the border component values are determined as follows:

1. Start with the defaults for each component.
2. Override the character component and color component defaults with the file-level values. Because the character component is specified more than once, use the first character component value specified.
3. Override the file-level color value with the record-level value.

The window border is constructed using the record-level border color, the first file-level border characters, and the default border display attributes.

If a single WDWBORDER keyword does not specify all three border components, then those not specified use the values from any other WDWBORDER keywords in effect; they do not use the defaults. In the preceding example, this is demonstrated at the record level. Only the color component is specified. However, because the character component is specified at the file level, the file-level value is used instead of the default. Because the display attribute component is not specified at the record or file level, the default is used.

UIM Help Window Borders

You can use the WDWBORDER keyword to specify the border attributes of help windows created with UIM panel groups. Assume that you are using DDS for full-screen displays and the UIM for help windows. If a window is on the display when the Help key is pressed, the UIM help window has the same borders as the DDS window. If no windows are active but the WDWBORDER keyword is specified at the file level or at the record level of a nonwindow record currently on the display, the system determines the border attribute and character values for the UIM help window by combining the file-level, record-level, and default values. Assume that no windows are currently displayed. First, a nonwindow record with the WDWBORDER keyword specified is written to the display. A UIM help window is then written to the display. The UIM help window borders use the attributes specified in the WDWBORDER keyword on the nonwindow record.

Reading Data from Windows

When windows are on the display, you can receive input only from the active window (that is, the last window written to the display). If your application reads a window record and the window exists on the display but is not the active window, then any windows subject to more recent input or output operations are removed. The window containing the record to be read is restored, becoming the active window. Then the record is read from the display.

If your application attempts to read a window record and the window does not exist on the display, a notify message stating that the window does not exist is returned. If the application attempts to read a window record and the window is on the display but the record is not on the display, a message stating that the record is not on the display is returned.

Changing Window Borders and Contents

To change the contents of a window already on the display, you must write that window's window definition record or a window reference record specifying that window to the display. To change the borders of a window already on the display, you must write that window definition record to the display.

If a window definition record is written to the display and a window with that name already exists on the display in the same position, a new window is not created. The new record is considered a normal write operation to the existing window. If the new record specifies different border attributes or characters, the new attributes or characters are displayed when the record is written.

Moving and Duplicating Windows

If a window definition record is written to the display and a window with that name already exists on the display in a different position, a new window is created. The new window appears in the specified position and has the same name as the existing window. To move the window, use the RMVWDW keyword in the window definition record being written. The existing window with that name and any other windows on the display are removed when the new window is written. In effect, the window is moved. If you do not use the RMVWDW keyword, the same window appears on the display in two different positions.

If a window reference record is written to the display and the specified window is on the display, the record is written to the most recently created window with the specified name. To write to an earlier window with that name, use a window definition record specifying the earlier window's location.

Making Two Windows Seem Active at Once

Although only one window can be truly active at a time, you can make two windows appear to be active at once. You might use this to display two windows side by side and allow the work station user to switch back and forth between them.

To make two windows appear active:

1. Set up function keys to perform the switching action for the work station user. For example, you might provide one key to page through data in the first window and another key to page through data in the second window.
2. Write the first window to the display.
3. Write the second window to the display using the USRRSTDSP keyword. The USRRSTDSP keyword keeps the first window from being saved when the second window is displayed. It keeps the second window from being removed when the user returns to the first window and then keeps the first window from being removed when the user returns to the second.


You can also use the USRRSTDSP keyword on the first window; it is not required on the first window because using it on the second window keeps the first window and all subsequent windows from being saved.

4. Be prepared to rebuild each window when the work station user presses the keys that perform the switching action. Once the two windows are displayed, you must rebuild each window whenever the user wants to move to it. The USRRSTDSP keyword keeps both windows from being saved and restored, so they must be rebuilt at every switch. In effect, the system does not know that the previous window existed on the display.


For more information about the USRRSTDSP keyword, see “Improving Application Performance” on page 5-11.

Making One Window in a Series Stand Out

Assume that you display a series of windows that looks like this:



Now you want to return to Window 3 and make it appear to pop out of the series, so that the display looks like this:



To make Window 3 stand out without removing Windows 4 and 5 from the display, take these steps:

1. Specify the USRRSTDSP keyword on Window 4 or any earlier window (that is, Windows 1 through 3). The USRRSTDSP keyword prevents the previous window and any subsequent windows from being saved.
2. Rebuild Window 3 so that it looks the way it did before Window 4 was first displayed. Because USRRSTDSP was used, the display was not saved when Window 4 was added to the display or at any later time. Thus, none of the windows are removed from the display, and Window 3 appears to pop out of the series.

For more information about the USRRSTDSP keyword, see “Improving Application Performance.”

Removing Windows

When a window is removed, it no longer exists on the display, and you can no longer write to or read from it. The window keywords provide you with several different ways to remove windows. Which method you use depends on which windows you want to remove and which operation you want to perform next. The different methods are described in the following sections.

Removing All Windows

Remove all the windows on a display in one of these ways:

1. Write to a nonwindow record. This allows you to remove all existing windows without displaying a new window.
2. Write to a window record that specifies the RMVWDW keyword. The RMVWDW keyword causes all other windows on the display to be removed when the specified window is displayed. If there are no other windows, the RMVWDW keyword is ignored, and no error is returned.

Removing More Recent Windows

To remove more recent windows that are overlaying the window you want to make active, read or write to the window you want to make active. Assume that Window 3 exists on the display but is not the active window. Windows 4, 5, and 6 were subject to more recent write operations than Window 3; therefore, they overlay Window 3. To remove Windows 4, 5, and 6 so that Window 3 is visible and is the active window, read or write to Window 3.

Improving Application Performance

In some cases, you can improve application performance by using the USRRSTDSP keyword to prevent the operating system from saving and restoring the display. The following sections describe how the system performs the operations, and how and when to use the USRRSTDSP keyword.

System Save and Restore Operations

If you do not use the USRRSTDSP keyword, the operating system automatically performs save and restore operations for your application. Before a window is displayed, the system saves the display, including any windows not being removed. When windows are removed, the system restores the display.

If a new window is being created on the display, the record that is active when the window is written is saved, and the entire display remains as background data. Then the new window becomes active. The saved record can be a window record or nonwindow record; the procedure is the same for both.

If a window record is written to the display to change or redisplay an existing window, any more recent windows are removed without being saved, the target window is restored, the new record is written, and the window becomes active.

If a nonwindow record is written to the display, any existing windows are removed without being saved, the new record is written to the initial display, and the display becomes active.

Response Time

The time needed for the system to perform save and restore operations depends on your communications setup and on the window being displayed.

The slowest response time occurs during the read and save operations performed when the first window is added to a display. Assume that the window is of average size and complexity. If the work station is attached to the AS/400 system by a twinaxial, local area network (LAN), or other high-speed communications line, response time is quick. If the work station is attached by a 2400-baud dedicated line, it takes approximately 10 seconds to complete the read and save operations and then display the window. If the line speed is increased to 9600 baud, it usually takes about 2.5 seconds.

Other operations, such as saving the display before the second or third window is added, or restoring the display after windows are removed, take less time.

For more information, including details about other window sizes, terminal types, and line speeds, consult your marketing representative.

Bypassing System Save and Restore Operations

You can use the USRRSTDSP keyword to bypass system save and restore processing and instead have your application rebuild the display only when necessary. This technique can improve system performance and response time for the user of the application. Consider using it when you display only one window at a time and the windows are in a different display file, or when you display a series of windows in which the user will not return to earlier windows, or when you want more than one window to seem active at one time.

For example, under the following conditions, the system ordinarily performs two save operations:

- Your application displays only one window at a time.
- The display file is created with RSTDSP(*YES).
- The first window record to overlay the display is located in a separate file.


The first save operation is performed when the display file is suspended. The second save operation is performed because a window is being displayed. USRRSTDSP eliminates the second, unnecessary save operation.

To bypass system save and restore processing, take these steps:

1. Create your own procedure to rebuild the display after a window is removed. Be sure to include any data that the user enters and that must be redisplayed.
2. Specify the record-level USRRSTDSP keyword on the window following the first window you do not want the system to save. The USRRSTDSP keyword keeps the system from performing save and restore operations. The USRRSTDSP keyword is allowed only on records containing the WINDOW keyword; it is ignored on the window reference record.

Once the USRRSTDSP keyword is specified, it remains in effect, even if the option indicator is set off, until you read or write to either the initial, windowless display or the window that is two windows before the window on which the USRRSTDSP keyword was specified.

Assume that six windows are on the display and the USRRSTDSP keyword was specified on the fourth. To turn off USRRSTDSP and have the system resume saving the display, you must write to the second window. As shown in the diagram, the system has saved only the first two windows:



USRRSTDSP Keyword Processing and Interactions

The USRRSTDSP keyword interacts with other keywords and window-related functions. Before using the keyword, you should understand the following (assume that the USRRSTDSP keyword is in effect):

- If a window record is written to a window that was saved (window 1 or 2 in the above example), the saved display is restored, the current record is written to the target window, and the target window becomes active. At this point, the USRRSTDSP keyword is no longer in effect.
- If a window definition record is written to a window that was not saved (window 3, 4, or 5 in the above example), it becomes a new window. It is merged with the previous display image and written to the display. No windows are removed.
- If a window record is read from a window that was not saved (window 3, 4, or 5 in the above example), an error message is returned to the application.

- If the initial display has been saved and the application writes to a window record specifying the RMVWDW keyword, any existing windows are removed. The new window is displayed on top of the initial display. The new window is active, and USRRSTDSP is no longer in effect.
- If the initial display is not saved and the application writes to a window record that specifies the RMVWDW keyword, all existing windows are removed. The new window is displayed on top of the initial display. The new window is active, and USRRSTDSP is still in effect.
- If a nonwindow record is written to the display and USRRSTDSP is specified on the first window, then the window is not removed, and the nonwindow record may overlay all or part of the window.

Programming Examples

The following sections illustrate the basic functions of the window keywords. The first example shows how to use a variety of window functions. It defines a full-screen display and several windows in one display file. The second example shows how to create windows for a full-screen display defined in a separate display file. The third example shows how to simulate menu bar support.

Using Basic Window Functions

The following scenario demonstrates the basic functions of the window keywords. The scenario is presented in three sections:

- The DDS used to define a full-screen display and windows
- The RPG program used to display the full-screen display and windows
- Discussion and illustration of the results

DDS Full-Screen Display and Window Definitions

The following DDS defines the initial display and two windows used in the scenario:

```
A*-----*
A* DISPLAY FILE - DEMOFM
A*-----*
A* FILE LEVEL KEYWORDS
A*-----*
A                                DSPSIZ(24 80 *DS3)
A                                HELP
A*
A*-----*
A* RECORDS USED IN DEFINING INITIAL DISPLAY
A*-----*
A      R INITIAL
A                                CA03(03)
A                                CA04(04)
A                                CA06(06)
A                                CA07(07)
A                                CA12(12)
A                                CLRL(*ALL)
A                                3 28'NONWINDOW DISPLAY RECORD'
A                                6 1'FLD #1:'
A      FLD48          30A B 6 9
A                                6 43'FLD #2:'
A      FLD49          15A B 6 51
A                                10 1'FLD #3:'
A      FLD50          30A B 10 9
A                                10 43'FLD #4:'
A      FLD51          15A B 10 51
A                                23 1'F3=XXXX'
A                                23 13'F4=XXXXXXXX'
```



```

A                                23 29'F6=XXXXX XXXXX'
A                                23 48'F7=XXXX'
A                                23 59'F12=CANCEL'
A*
A*-----*
A* RECORDS USED IN DEFINING WINDOW1
A*-----*
A      R WINDOW1                                WINDOW(7 3 11 33)
A N01                                WDWBORDER((*COLOR GRN))
A 01                                WDWBORDER((*COLOR RED))
A                                2 13'WINDOW #1'
A                                4 2'CUSTOMER NO.'
A      FLD1                                6A 0 4 15
A                                4 22': '
A*
A      R REC2WIN1                                WINDOW(WINDOW1)
A                                OVERLAY
A                                CA12(12)
A                                10 2'F12=CANCEL'
A*
A      R REC3WIN1                                WINDOW(WINDOW1)
A                                OVERLAY
A                                6 2'NAME:'
A      FLD2                                24A B 6 8
A                                7 2'ADDRESS:'
A      FLD3                                21A B 7 11
A                                8 2'PHONE:'
A      FLD4                                23A B 8 9
A*
A*-----*
A* RECORDS USED IN DEFINING WINDOW2
A*-----*
A      R WINDOW2                                WINDOW(9 25 11 32)
A*
A                                2 12'WINDOW #2'
A      FLD5                                22A 0 4 6
A      FLD6                                25A 0 5 4
A      FLD7                                25A 0 6 4
A      FLD8                                25A 0 7 4
A*
A      R REC2WIN2                                WINDOW(WINDOW2)
A                                OVERLAY
A                                CA12(12)
A                                10 8'XXXXXXXX : '
A      FLD9                                6A B 10 18
A*
A*-----*

```

RPG Display Program

This RPG program displays the full-screen display and windows defined in the preceding section. Steps 1 through 5 are explained in the sections following the program.

```

F*****
F*   RPG PROGRAM - WINDEMO
F*****
FDEMOFM CF E                                WORKSTN
C*****
C* Step 1: Display Initial Display
C*****
C                                EXFMTINITIAL
C*****
C* Step 2: Display Window #1
C*****
C                                MOVE 'nnnnnn' FLD1
C                                WRITEWINDOW1
C                                WRITEREC2WIN1
C                                EXFMTREC3WIN1
C*****
C* Step 3: Display Window #2
C*****

```

Display Files, Examples

```

C      MOVEL 'XXXXXXXXX 'TEMP16 16
C      MOVE  'xxxx x x' TEMP16
C      MOVEL TEMP16      FLD5
C      MOVE  'xxxxxx'   FLD5
C*
C      MOVEL 'xxxxxx x' FLD6
C      MOVEL 'xx xxxx 'TEMP16
C      MOVE  'xx xxxx' TEMP16
C      MOVEL TEMP16      TEMP17 17
C      MOVE  ' '          TEMP17
C      MOVE  TEMP17       FLD6
C*
C      MOVEL 'xxxx xxx' FLD7
C      MOVEL 'xxxx x x' TEMP16
C      MOVE  'x xxxx x' TEMP16
C      MOVEL TEMP16      TEMP17
C      MOVE  'x'          TEMP17
C      MOVE  TEMP17       FLD7
C*
C      MOVEL 'xxxxxxxx 'FLD8
C      MOVEL 'xxxx xxx' TEMP16
C      MOVE  'xx xxxxx' TEMP16
C      MOVEL TEMP16      TEMP17
C      MOVE  '.'          TEMP17
C      MOVE  TEMP17       FLD8
C*
C      WRITEWINDOW2
C      EXFMTREC3WIN2
C*****
C* Step 4: Restore Window #1
C*****
C      EXFMTREC3WIN1
C*****
C* Step 5: Display Initial Display
C*****
C      READ INITIAL                      91
C*****
C* End The RPG Program
C*****
C      SETON                      LR
C*****

```

Step 1: Display Initial Display

The application creates the initial display without using a window keyword:

NONWINDOW DISPLAY RECORD

FLD #1: _____ FLD #2: _____

FLD #3: _____ FLD #4: _____

F3=Xxxx F4=XXXXXXXX F6=XXXXX XXXXX F7=Xxxx F12=CANCEL

Step 2: Display Window 1

The user types some data on the display and presses the Enter key. The application writes to window definition record WINDOW1, which creates the window. Then the application adds information to the window by writing to window reference record REC2WIN1 and performing a write/read operation to window reference record REC3WIN1.

Before the window is displayed, the system performs a read screen immediate operation to obtain the display image and saves the underlying display. The system performs a read screen immediate operation only when the first window is added to the display. It performs a save operation each time a window is created.

NONWINDOW DISPLAY RECORD

FLD #1: DATA ENTERED HERE

FLD #2: DATA ENTERED

F :
: WINDOW #1
: FLD #4: DATA ENTERED
: CUSTOMER NO. nnnnnn :
: NAME: :
: ADDRESS: :
: PHONE: :
: F12=CANCEL
:

F3=Xxxx

F4=XXXXXXXX

F6=Xxxx Xxxx

F7=Xxxx

F12=CANCEL

Step 3: Display Window 2

The user types some information and presses the Enter key. The application writes to window definition record WINDOW2. WINDOW2 is not the active window, and it is not currently on the display; therefore, the system saves the underlying display, associating the saved data with WINDOW1. Then a new window is created. The application adds information to the window by performing a write/read operation to window record REC2WIN2.

```

NONWINDOW DISPLAY RECORD

FLD #1: DATA ENTERED HERE          FLD #2: DATA ENTERED
: .....:
:      WINDOW      : .....:
F :      :      :      : D
:  CUSTOMER NO. nnnnn      WINDOW #2      :
:      :      :      :
:  NAME: MY NAME      :      Xxxxxxx xxx x xxxxxxxx      :
:  ADDRESS: MY ADDRES      :      xxxxxx xxx xxxx xxx xxx      :
:  PHONE: MY PHONE      :      xxxx xxxxxxxx x xx xxxx xx      :
:      :      :      :      xxxxxxx xxxx xxxxx xxxxx.      :
:  F12=CANCEL      :      :      :      :
:      :      :      :      :
: .....:      Xxxxxxx : _____      :
:      :      :      :      :
: .....:      :      :      :
F3=Xxxx      F4=XXXXXXXX      F6=XXXXX Xxxxx      F7=Xxxx      F12=CANCEL

```

Step 4: Restore Window 1

The user types some data and presses the Enter key. The application performs a write/read operation to window record REC3WIN1. The record format name specified on the WINDOW keyword, WINDOW1, is not the active window. However, the window is currently on the display; therefore, the system restores the saved display associated with WINDOW1. The restore operation removes WINDOW2, which was written after WINDOW1. Then REC3WIN1 is written to the restored window.

```

NONWINDOW DISPLAY RECORD

FLD #1: DATA ENTERED HERE          FLD #2: DATA ENTERED
: .....:
:      :
:      WINDOW #1      :
F :      :
:  CUSTOMER NO. nnnnnn :
:      :
:  NAME: MY NAME      :
:  ADDRESS: MY ADDRESS :
:  PHONE: MY PHONE    :
:      :
:  F12=CANCEL          :
:      :
: .....:

F3=Xxxx      F4=XXXXXXXX      F6=XXXXX  XXXXX      F7=Xxxx      F12=CANCEL

```

Step 5: Display Initial Display

The user presses the Enter key. The application performs a read operation to the initial display, which automatically removes the last window from the display.

NONWINDOW DISPLAY RECORD				
FLD #1:	<u>DATA ENTERED HERE</u>		FLD #2:	<u>DATA ENTERED</u>
FLD #3:	<u>DATA ENTERED HERE</u>		FLD #4:	<u>DATA ENTERED</u>
F3=Xxxx	F4=Xxxxxxxx	F6=Xxxxx Xxxx	F7=Xxxx	F12=CANCEL

Defining Windows in a Separate Display File

The following sections show the DDS code for a full-screen display and window and the procedural steps needed to use them. In contrast to the preceding example, this example keeps the window records in a separate display file from the file for the underlying display. This technique allows you to add windows for items, such as help, to existing applications, without rewriting the display-file code for the applications.

In the example, the application uses RSTDSP(*NO) to indicate that a save operation should not be done when a file is suspended. Because displaying a window also performs a save operation, using RSTDSP(*NO) prevents two save operations from being performed. Because removing the window restores the screen that was present prior to the window operation, the application is not required to rebuild the display after window processing. For more information on the USRRSTDSP keyword, see the notes at the end of the example.

DDS Full-Screen Display and Window Definitions

```

A*-----*
A* DISPLAY FILE DISPLAY1 (RSTDSP=NO DFRWRT=*YES)
A*-----*
A      R REC1
A          2 21'FIRST RECORD IN FILE'
A          4 17'Current Customer #:'
A      FIELD1      6A B 4 38
A*
A      R REC2
A          OVERLAY CA03(03)
A          6 21'SECOND RECORD IN FILE'
A          8 17'Current Customer #:'
A      FIELD2      6A B 8 39DSPATR(HI)
A          24 02'CA03=EXIT'
A*-----*

```

RPG Program Source

```

FDISPLAY1CF E
C
C          WRITEREC1
C          WRITEREC2
C          RETRY      TAG
C          READ REC2      90
C 03          GOTO END
C          CALL 'WINPGM'
C          GOTO RETRY
C          END      TAG
C          SETON      LR

```

```

A*-----*
A* DISPLAY FILE DISPLAY2 (RSTDSP=NO)
A*-----*
A      R WINDOW1      WINDOW(7 4 11 25)
A N01      WDWBORDER((*COLOR GRN))
A 01      WDWBORDER((*COLOR RED))
A      2 9'Window #1'
A *
A      R REC2WIN1      WINDOW(WINDOW1)
A      CA12(12) OVERLAY
A      4 1'Customer No. nnnnnn:'
A      6 1'Name:'
A      FIELD3      19A B 6 7
A      7 1'Address:'
A      FIELD4      16A B 7 10
A      8 1'Phone:'
A      FIELD5      18A B 8 8
A      10 1'F12=Cancel'
A*-----*
A* Dummy record to clear window from display before returning
A*-----*
A      R DUMMY1      CLRL(*NO) OVERLAY FRCDTA
A*-----*
A* No I/O will ever be done to this record
A*-----*
A      R DUMMY2      ASSUME
A      11 1' '
A*-----*

```

RPG Program Source for WINPGM

```

FDISPLAY1CF E
C          WRITEWINDOW1
C          EXFMTREC3WIN1
C          WRITEDUMMY1
C          RETRN
C          SETON      LR

```

Step 1: Display Initial Display

The application opens display file DISPLAY1, performs a write operation to record REC1, and performs a write/read operation to REC2.

```

FIRST RECORD IN FILE
Current Customer #: _____
SECOND RECORD IN FILE
Previous Customer #: _____

```

Step 2: Display a Window

The user enters data indicating that a window should be displayed. The application opens window display file DISPLAY2. This can be done from a separate program such as the one which displayed the screen in Step 1. The ASSUME keyword on record DUMMY2 keeps the full-screen display from being cleared, and the system marks display file DISPLAY2 as suspended. No I/O operation ever needs to be performed to record DUMMY2; it only needs to be present in the file.

The application performs a write operation to record WINDOW1. Display file DISPLAY1 is suspended; because of the RSTDSP(*NO) setting, no save is performed. Display file DISPLAY2 is restored; because of the RSTDSP(*NO) setting, no restore data is sent.

The application performs a write operation to record REC2WIN1.

```

FIRST RECORD IN FILE
Current Customer #: xxxxxx
SECOND RECORD IN FILE
.....: #: xxxxxx
:      Window #1      :
:      :               :
: Customer No. nnnnnn:
:      :               :
: Name: _____:
: Address: _____:
: Phone: _____:
:      :               :
: F12=Cancel         :
:      :               :
:.....:

```

Step 3: Return to the Initial Display

The user enters data indicating that the application should return to the initial display file, DISPLAY1. The application performs a write operation to record DUMMY1, which causes the system to remove all windows from the display. Because the application does not close the DISPLAY2 display file, and the USRRSTDSP keyword is not specified, then removing the window restores the initial display. The application is not required to rebuild the initial display. The DUMMY1 record should contain the FRCDTA keyword or specify DFRWRT(*NO) when the display file is created.

The application performs a write operation to record REC1. Display file DISPLAY2 is suspended; because of the RSTDSP(*NO) setting, no save operation is performed. Display file DISPLAY1 is restored; because of the RSTDSP(*NO) setting, no data is sent.

The application performs a write/read operation to record REC2.

FIRST RECORD IN FILE

Current Customer #: _____

SECOND RECORD IN FILE

Previous Customer #: _____

Additional notes on this example:

1. If the application closes DISPLAY2 in Step 3, then the application must rebuild the initial display by performing a write operation to REC1 and then a write/read operation to REC2. This can be avoided by specifying RSTDSP(*YES) for DISPLAY1.
2. USRRSTDSP can be added to the window record in DISPLAY2. However, if this is done, the user must either specify RSTDSP(*YES) for DISPLAY1, or rebuild the initial display in Step 3. However, in Step 3, the application must still write DUMMY1, or the borders of the window are not displayed properly on the next write operation to the window.

Chapter 6. Creating a Graphical Look for Displays

The graphical look is a change in what you see while you run DDS functions. Instead of dotted windows, you have crisp window borders. Instead of typing numbers in an option column to make a selection, you can use a mouse or mnemonics. A **mnemonic** is an underlined character within the text of a choice that you can type to select the choice. Instead of seeing option numbers, you can see radio buttons or check boxes. A **radio button** is a circle that precedes a choice in a single-choice selection field on a graphical display station. A **check box** is a square box that precedes a choice in a multiple-choice selection field on a graphical display station. You can click on radio buttons and check boxes to make choices.




Figure 6-1. Radio Buttons and Check Boxes

In addition to a fresher look, the enhanced function includes menu bars and pull-down menus. Instead of having to simulate a menu bar by using lengthy DDS coding, you can use DDS keywords.

Factors Affecting the Graphical Look

The graphical functions described in this chapter appear differently, depending on the hardware configuration you have and the value you specify on the enhanced display (ENHDSP) parameter.

Hardware Configuration

Table 6-1 and Table 6-2 on page 6-3 show how each graphical function appears on different configurations. Letters A through F in the tables identify the configurations; these letters are referred to throughout this chapter.

Table 6-1. Functions Supported by Hardware Configurations A, B, and C

Function	Hardware Configuration		
	A	B	C
	Graphical User Interface (GUI) Programmable Work Stations¹	InfoWindow II Display Station² Attached to Controller Supporting Enhanced Interface³	3477 Display Station Attached to Controller Supporting Enhanced Interface³
Windows	GUI ⁴ windows and possible improvement in performance	Character-based GUI ⁵ and possible improvement in performance	Character windows and possible improvement in performance
Selection fields and menu bars	GUI ⁴	Character-based GUI ⁵	Mnemonics, bar selection cursor
Continued-entry fields	One field	One field	One field
Edit masks	Yes	Yes	Yes
Highlighting	Yes	Yes	Yes
Cursor progression	Yes	Yes	Yes
Simple hotspots	Yes	Yes	No

Notes:

1. For example, RUMBA/400 (Microsoft Windows** and OS/2*) and AIX* AS/400 Connection Program/6000 Release 2.
2. InfoWindow II display stations: 3486, 3487, 3488.
3. Twinaxial controllers: 5494 Release 1.1, and features 6050, 2661, 9146, and 9148.
4. GUI includes solid-line window borders, selectable background colors, use of a pointer device (for example, a mouse), mnemonic selection, bar selection cursor, radio buttons (for single-choice selection fields), and check boxes (for multiple-choice selection fields).
5. Character-based GUI is similar to GUI except that in character-based GUI, constructs are created using characters, and background colors are not selectable.

Table 6-2. Functions Supported by Hardware Configurations D, E, and F

Function	Hardware Configuration		
	D	E	F
	5250 Display Station Attached to Controller Supporting Enhanced Interface ¹	ASCII Display Station Attached to ASCII Controller Supporting Enhanced Interface ²	Any Display Station Attached to Controller Not Supporting Enhanced Interface ³
Windows	Character windows and possible improvement in performance	Character windows and possible improvement in performance	Character windows
Selection fields and menu bars	Bar selection cursor	Bar selection cursor	Entry field driven
Continued-entry fields	One field	One field	Multiple fields
Edit masks	Yes	Yes	Ignored
Highlighting	Yes	Yes	Ignored
Cursor progression	Yes	Yes	Ignored
Simple hotspots	No	No	No

Notes:

1. Twinaxial controllers: 5494 Release 1.1, and features 6050, 2661, 9146, and 9148.
2. ASCII controllers that support an enhanced interface: features 6041, 6141, 2637, 9145, 9147.
3. For example: 5250 display stations attached to 5294 and 5394 controllers or features 2638, 6040, and 6140; some programmable work stations emulating a controller with an attached 5250 display station (for example, PC Support/400).

Enhanced Display Parameter

The enhanced display (ENHDSP) parameter can be used with the CRTDSPF, CHGDSPF, and OVRDSPF commands. Use this parameter to specify whether the data being shown at a display station uses the enhanced capabilities available on the display station.

Normally, DDS windows and CUA* graphical items are rendered using whatever enhanced capabilities are available on the display station. For example, window borders and menu-bar separators are presented graphically on a graphical display station.

You can use ENHDSP(*NO) to cause all records defined in the display file to be displayed in character-based mode, regardless of the capabilities of the display station. When ENHDSP(*NO) is specified, none of the enhanced capabilities that may be available on a particular display station are used. That is, records display just as they would on a display station in configuration F in Table 6-2.

The default value for ENHDSP is *YES. Any enhanced capabilities of the display station are taken advantage of automatically. If you specify ENHDSP(*YES) and you use the default window border and menu-bar separator, the window border and

the menu-bar separator appear as solid lines. If the display station is attached to a controller that does not support an enhanced interface for nonprogrammable work stations, ENHDSP(*YES) is ignored. The records in the display file are displayed on that display station in character-based mode (as if ENHDSP(*NO) were specified).

Writing records from files with ENHDSP(*YES) and files with ENHDSP(*NO) to the same display. If the record (or records) displayed is from a file with ENHDSP(*YES), the first write operation of a record (such as a window) from a file with ENHDSP(*NO) causes all menu bars, pull-down menus, and other windows on the display to change from graphical to character-based. The records from the file with ENHDSP(*YES) are switched to the ENHDSP(*NO) mode of display.

If the record displayed is from a file with ENHDSP(*NO), a write operation of a record (such as a window) from a file with ENHDSP(*YES) does not change the presentation of any menu bars, pull-down menus, or other windows on the display.

Notes:

1. The system file that is used for UIM help is shipped with ENHDSP(*NO). If you use UIM help with a file that has ENHDSP(*YES) specified, the display will change from graphical to character-based.
2. Some programmable work stations that support an enhanced interface ignore the window border and menu-bar separator keywords.
3. If a window is written to the display station such that a border is in column 1, column 80 (for display size 24 by 80), or column 132 (for display size 27 by 132), the window is always displayed as though ENHDSP(*NO) were specified.

DDS Keywords

The tasks in this chapter refer to the DDS keywords, but may not provide all the details about them. For more information on each keyword, refer to the *DDS Reference*.

CHCACCEL (Choice Accelerator Text)

Specifies the text for the accelerator key on a single-choice selection field in a pull-down record.

CHCAVAIL (Choice Color/Display Attribute when Available)

Specifies the color or display attributes to be used when displaying the available choices in a menu bar or selection field.

CHCCTL (Choice Control)

Controls the availability of the choices for the field.

CHCSLT (Choice Color/Display Attribute when Selected)

Specifies the color or display attributes to be used when displaying a selected choice in a menu bar.

CHCUNAVAIL (Choice Color/Display Attribute when Unavailable)

Specifies the color or display attributes to be used when displaying the unavailable choices in a selection field.

CHOICE (Selection Field Choice)

Defines a choice for a selection field.

|

| **CNTFLD (Continued-Entry Field)**

| Defines a field as a continued-entry field. Continued-entry fields are sets of

| associated entry fields that are treated by the work station controller as a single-

| entry field during field data entry and editing.

|

| **EDTMSK (Edit Mask)**

| Defines an edit mask for fields with EDTCDE or EDTWRD keywords.

|

| **ENTFLDATR (Entry-Field Attribute)**

| Defines the leading attribute of the field that changes to a specified attribute

| whenever the cursor enters the field. When defined at both the field- and

| record-level, the field-level specification is used for the field.

|

| **FLDCSRPRG (Cursor Progression Field)**

| Defines the next field that the cursor moves to when exiting this field.

|

| **HLPID (Help Identifier)**

| Specifies an identifier for the constant in the help for a field.

|

| **MLTCHCFLD (Multiple-Choice Selection Field)**

| Defines a field as a multiple-choice selection field. A multiple-choice selection

| field is a field that contains a fixed number of choices from which a user can

| select multiple choices.

|

| **MNUBAR (Menu Bar)**

| Defines a menu bar. A menu bar is a horizontal list of choices that is followed

| by a separator line.

|

| **MNUBARHC (Menu-Bar Choice)**

| Defines a choice for a menu-bar field. A menu-bar choice represents a group of

| related actions that the application user can select.

|

| **MNUBARDSP (Menu-Bar Display)**

| Displays the menu bar.

|

| **MNUBARSEP (Menu-Bar Separator)**

| Specifies the color, display attributes, or character used to form the menu-bar

| separator line.

|

| **MNUBARSW (Menu-Bar Switch Key)**

| Assigns a CA key to the Switch-to-menu-bar key.

|

| **MNUCNL (Menu Cancel Key)**

| Assigns a CA key to be the cancel key for menu bars or pull-down menus.

|

| **PULLDOWN (Pull-Down Menu)**

| Defines a record as a pull-down menu for a menu bar.

|

| **SFLCSRPRG (Subfile Cursor Progression)**

| Causes the cursor to move to the same input field in the next subfile record

| when exiting this field.

|

| **SNGCHCFLD (Single-Choice Selection Field)**

| Defines a field as a single-choice selection field. A single-choice selection field

| is a field that contains a fixed number of choices from which a user can select

| one choice.

Creating Menu Bars

Figure 6-2 shows an example of a **menu bar**, which is a horizontal list of choices that appears at the top of a display. A **menu-bar separator** appears below the list. When you select a choice from the menu bar, a pull-down menu appears. A **pull-down menu** is a group of actions associated with a menu-bar choice.




Figure 6-2. Example of a Menu Bar

Defining the Menu-Bar Choices

A menu bar is a special type of record containing a MNUBAR keyword and one menu-bar field. The **menu-bar field** is a numeric field containing one or more MNUBARHC keywords. The MNUBARHC keywords define the menu-bar choices and the pull-down menus associated with each choice. The menu bar always displays on the first line. The menu-bar record cannot contain any displayable fields other than the menu-bar field.

The number of rows occupied by the menu bar is determined by the number of choices and the maximum lengths of the choice text for all the menu-bar choices. The number of rows the menu bar occupies must be less than or equal to 12.

If you define a pull-down record that is too large to fit beneath the maximum number of rows occupied by the menu bar, the file is not created.

Defining the Menu-Bar Separator

You can use the system defaults for the menu-bar separator or you can use the MNUBARSEP keyword. Using MNUBARSEP, you can specify the color and display attributes of the menu-bar separator and the character that makes up the separator. The default presentation of the menu-bar separator is a solid line on display stations in configurations A and B in Table 6-1 on page 6-2. The default character that makes up the menu-bar separator is an underline () on display stations in configuration C in Table 6-1 on page 6-2, and configurations D, E, and F in Table 6-2 on page 6-3. For an example of using the MNUBARSEP keyword, see Figure 6-3 on page 6-7.

Note: The menu-bar separator is used as the top border of the pull-down menus. Its color does not change when a pull-down menu is displayed. To ensure a consistent appearance for your displays, use the same color and display attributes for both the menu-bar separator and the pull-down menu borders.

Figure 6-3 on page 6-7 shows an example of the DDS for a menu bar.

	1	2	3	4	5	6	7
A	R	MENUBAR			MNUBAR		
A		MNUFLD	2Y 0B	1 2			
A					MNUBARHC(1 PULLFILE +		
A					'>File)	
A 02					MNUBARHC(2 PULLEDIT +		
A					&EDITXT)		
A					MNUBARHC(3 PULLVIEW +		
A					'>View)	
A 04					MNUBARHC(4 PULLOPT +		
A					'>Options	' +	
A					&RTNFLD)		
A					MNUBARHC(5 PULLHELP +		
A					'>Help)	
A					MNUBARSEP((*COLOR WHT))		
A		EDITXT	20A P				
A		RTNFLD	2Y 0H				
A			.				
A			.				
A			.				

Figure 6-3. DDS for a Menu Bar. Assume that field EDITXT contains the text >Edit.

You can control which menu-bar choices are displayed by specifying option indicators on the MNUBARHC keywords. Option indicators are used by the application program to specify if a menu-bar choice should be displayed (optioned on) or should not be displayed (optioned off). The DDS for option indicators are shown in Figure 6-3 on page 6-7. The application specifies the option indicators as on or off and then writes the menu-bar record (without MNUBARDSP in effect) to send the option indicators to the system. If a menu-bar choice is optioned off, the list of choices is compressed. However, the number of rows occupied by the menu-bar record is not compressed (because records cannot be variable length). The number of rows occupied by the menu bar is the number of rows needed if all the choices were displayed plus one row for the menu bar separator. If, through optioning, the list of choices is compressed so that it is displayed using fewer rows, the separator line is displayed on the line following the last row of choices. There are blank lines between the menu-bar separator and the next record on the display.

You can allow for translation of the menu-bar choices by leaving blank space at the end of the text specified for each choice. Another way is to use a program-to-system field whose length includes translation space. When the menu bar displays, any trailing blanks in the choice text are truncated and the choices have three spaces between them. Thus, the number of rows of choices that appear depends on the translation. However, the number of rows occupied by the menu-bar record is the maximum number of rows needed if the text for each choice used all the translation space. When the extra translation space causes compression to a fewer number of rows, blank lines appear between the menu-bar separator and the next record on the display.

On display stations in configurations A and B from Table 6-1 on page 6-2, the menu bar looks like this:




Figure 6-4. Menu Bar on a Graphical Display Station with Enhanced Interface

On display stations in configuration C from Table 6-1 on page 6-2, the menu bar looks like this:




Figure 6-5. Menu Bar on a Nongraphical Display Station with Underline Capability

On display stations in configurations D and E from Table 6-2 on page 6-3, the menu bar looks like this:




Figure 6-6. Menu Bar on a Nongraphical Display Station without Underline Capability

On display stations in configuration F from Table 6-2 on page 6-3, the menu bar looks like this:




Figure 6-7. Menu Bar on a Display Station without Enhanced Interface

Creating Selection Fields

There are two types of selection fields: single-choice and multiple-choice.

Single-choice selection fields and **multiple-choice selection fields** contain a fixed group of choices displayed in a vertical list. You can select any number of choices from the multiple-choice selection field. You can only make one choice from the single-choice selection field. Figure 6-8 shows an example of both the single-choice selection field and the multiple-choice selection field.

Display Title

Single selection field . . . : ☐ One
☐ Two
☐ Three

Multiple selection field . . . : ☐ One
☐ Two
☐ Three

RV2W860-1

Figure 6-8. Selection Fields on a Graphical Display Station with Enhanced Interface

Single-Choice Selection Field

You can define the number of choices and the selection numbers for each choice. On display stations in configurations A and B from Table 6-1 on page 6-2, the choices are preceded by radio buttons. This is true unless *NOSLTIND is specified on the PULLDOWN keyword. A blank line appears between choices that are not sequential. The location that you specify for the single-choice selection field is the location of the input field (on a character-based nongraphical display) or the location of the first radio button (on display stations in configurations A and B from Table 6-1 on page 6-2).

Notes:

1. If you suppress the selection characters, the location that you specify for the single-choice selection field is the location of the first character in the first choice.
2. If the single-choice selection field is within a pull-down menu, the location you specify is relative to the pull-down menu borders.

A single-choice selection field is a numeric field containing a SNGCHCFLD keyword and one or more CHOICE keywords. The CHOICE keywords define the choices

within the single-choice selection field. Figure 6-9 on page 6-10 shows an example of the keywords to use.

You can have choice numbers up to two digits long. The maximum number you can specify for a choice is 99. On output, if the field contains a choice number, that choice is the default selection.

Multiple-Choice Selection Field

A multiple-choice selection field is a special numeric field containing:

- A MLTCHCFLD keyword to identify it as a multiple-choice selection field. When a user makes a selection, the field itself contains the number of choices that are selected.
- One or more CHOICE keywords that define the choices.
- A CHCCTL keyword for each choice to define a hidden field for each choice. The hidden field is used to indicate if the choice was selected.

Figure 6-9 shows an example of the DDS for both single-choice and multiple-choice selection fields.

```

| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|
| A          R RECORD
| A          2 30'Display Title'
| A          4 5'Single selection field . . . : '
| A          F1          2Y 0B 4 40SNGCHCFLD
| A          CHOICE(1 '>One')
| A          CHCCTL(1 &CTLONE1 MSG1111 QUSER/A)
| A 01          CHOICE(2 '>Two')
| A          CHCCTL(2 &CTLTWO1 &MSG1 &LIB/&MSGF)
| A          CHOICE(3 'T>hree')
| A          CHCCTL(3 &CTLTHR1)
| A          CTLONE1          1Y 0H
| A          CTLTWO1          1Y 0H
| A          CTLTHR1          1Y 0H
| A          MSG1             7A P
| A          LIB              10A P
| A          MSGF             10A P
| A          8 5'Multiple selection field . . . : '
| A          F2          2Y 0B 8 40MLTCHCFLD
| A          CHOICE(1 '>One')
| A          CHCCTL(1 &CTLONE2 MSG1112 QUSER/A)
| A 01          CHOICE(2 '>Two')
| A          CHCCTL(2 &CTLTWO2 &MSG2 &LIB/&MSGF)
| A          CHOICE(3 'T>hree')
| A          CHCCTL(3 &CTLTHR2)
| A          CTLONE2          1Y 0H
| A          CTLTWO2          1Y 0H
| A          CTLTHR2          1Y 0H
| A          MSG2             7A P

```

Figure 6-9. DDS for Single-Choice and Multiple-Choice Selection Fields

On display stations in configurations A and B from Table 6-1 on page 6-2, the selection fields look like this:

Display Title

Single selection field . . . : ☐ One

☐ Two

☐ Three

Multiple selection field . . . : ☐ One

☐ Two

☐ Three

RV2W860-1

Figure 6-10. Selection Fields on a Graphical Display Station with Enhanced Interface

On display stations in configuration C from Table 6-1 on page 6-2 and configurations D, E, and F from Table 6-2 on page 6-3, the selection fields look like this:

Display Title

Single selection field . . . : 1. One

2. Two

3. Three

Multiple selection field . . . : - One

- Two

- Three

RV2W070-0

Figure 6-11. Selection Fields on a Nongraphical Display Station

Controlling the Availability of Choices

You can control the availability of the choices in a selection field using the CHCCTL keyword. Specify the name of a hidden field on the CHCCTL keyword. Your program can set a value in this field to specify whether the choice is available, unavailable, or selected (multiple-choice selection fields only). Figure 6-12 on page 6-12 describes the control values and their meanings.

Control Value	Sets Choice to
0	available (or not selected)
1	selected
2	unavailable

Figure 6-12. Control Values for the CHCCTL Keyword

Value 1 is ignored for single-choice selection fields, because default selection is done by setting the selection in the single-choice selection field itself. Value 1 is used for multiple-choice selection fields to let more than one choice default to the selected choice.

You can also specify a message to be displayed if the user selects an unavailable choice. If you do not specify a message, the system displays a default message.

Figure 6-13 is an example of the DDS to control the availability of choices showing a single-choice selection field in an ordinary record:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R RECORD
A          2 2'Flavor . . . '
A          F1          2Y 0B 2 16SNGCHCFLD
A          CHOICE(1 '>Chocolate ')
A          CHCCTL(1 &CTLCHOC MSG1112 QUSER/A)
A 01          CHOICE(2 '>Strawberry ')
A          CHCCTL(2 &CTLSTRA &MSG &LIB/&MSGF)
A          CHOICE(3 '>Vanilla ')
A          CHCCTL(3 &CTLVANI)
A          CHOICE(5 '>Peach ')
A          CTLCHOC          1Y 0H
A          CTLSTRA          1Y 0H
A          CTLVANI          1Y 0H
A          MSG          7A P
A          LIB          10A P
A          MSGF          10A P

```

Figure 6-13. DDS to Control the Availability of Choices

On display stations in configuration C from Table 6-1 on page 6-2 and configurations D, E, and F from Table 6-2 on page 6-3, the single-choice selection field looks like this:


Flavor . . . _

- 1. Chocolate
- 2. Strawberry
- 3. Vanilla
- 5. Peach

Figure 6-14. Single-Choice Selection Field with an Unavailable Choice. Assume that at run time, CTLCHOC and CTLSTRA are set to 0 (available) and CTLVANI is set to 2 (unavailable). The choice text, Vanilla, appears gray to indicate it is unavailable.

Creating Pull-Down Menus Using Single-Choice Selection Fields

When you select a choice from the menu bar, a pull-down menu appears. A pull-down menu is a group of actions associated with a menu bar choice. Figure 6-15 is an example.



RV2W859-1

Figure 6-15. Example of a Pull-Down Menu

You must define the pull-down menus and the corresponding menu bar in the same file.

The last field in any pull-down menu always operates as though the CHECK(FE) (Field Exit) keyword were specified. This keeps the cursor in the pull-down menu after you enter the input that is in the last field in the pull-down menu. Then, if you press the Field Exit key with the cursor in the last field, the field is cleared and the cursor moves to the next pull-down menu. If the last field did not operate with CHECK(FE), the cursor automatically moves on to the next pull-down menu after you press the Enter key.

A pull-down record can contain anything that a window record can contain. However, use only single-choice selection fields or multiple-choice selection fields in a pull-down menu. If you use fields other than single-choice selection fields or multiple-choice selection fields, the cursor does not move consistently on all display stations. On display stations attached to a controller that supports an enhanced interface for nonprogrammable work stations, the cursor-right keys and cursor-left keys display the next pull-down menu when both of these conditions are true: (1) there is only one selection field in the displayed pull-down menu, and (2) the cursor is positioned on the selection field. On display stations attached to a controller that does not support an enhanced interface for nonprogrammable work stations, the cursor movement keys move the cursor one character position within the pull-down menu.

Figure 6-16 on page 6-14 is an example of the DDS for a pull-down menu. The figures that follow show how the pull-down menu appears on each type of display.

Note: Assume that the record PULLDOWN is specified on the MNUBARHC keyword for the Edit choice, and that the MARKTXT field contains the text, >Mark.

On display stations in configuration F from Table 6-2 on page 6-3, the pull-down menu looks like this:




Figure 6-20. Pull-Down Menu on a Display without Enhanced Interface


Controlling the Selection Characters

A **selection character** is a character that precedes a choice in a selection field. It is used to select the choice or to show that a choice has been selected. An example of a selection character is a radio button. The default is for selection characters to appear. You can suppress them by specifying the *NOSLTIND parameter on the PULLDOWN keyword. Figure 6-21 is an example of the DDS to suppress the selection characters.

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A          R PULLDOWN          PULLDOWN(*NOSLTIND)
A          F1                  2Y 0B 1 1SNGCHCFLD
A    01                      CHOICE(1 '>Undo      ')
A                               CHOICE(2 &MARKTXT)
A                               CHOICE(3 '>Copy      ')
```

Figure 6-21. DDS for Suppressing Selection Characters

On display stations in configurations A and B from Table 6-1 on page 6-2, the pull-down menu looks like this:



RV2W857-1

Figure 6-22. Suppressed Selection Characters on Graphical Display Station

On display stations in configuration C from Table 6-1 on page 6-2, the pull-down menu looks like this:




Figure 6-23. Suppressed Selection Characters on Nongraphical Display Station

The *NOSLTIND value is ignored for display stations that are not attached to a controller that supports an enhanced interface for nonprogrammable work stations.

Defining Accelerator Keys

An **accelerator key** is a function key that starts the application-defined function and is displayed next to a pull-down menu choice.

You can specify accelerators for a single-choice selection field in a pull-down menu by doing the following:

1. Specify the necessary CFnn keys.
2. Use the CHCACCEL keyword.

Specify the accelerator text on the CHCACCEL keyword. You can use a P-field to specify the text. Note that the CHCACCEL keyword does not define the accelerator key itself. You must define the CFnn keyword for the key and design your application to recognize this key as an accelerator for this choice. You must also ensure that the text you specify on CHCACCEL correctly reflects the key you have defined. For example, if you want CF08 to be an accelerator key, specify something like F8 or CF08 on the CHCACCEL keyword for the appropriate choice.

The accelerator text appears three spaces after the length of the longest choice text in the field.

Because the accelerator key functions even if the pull-down menu is not displayed, you should define the necessary CFnn keys at the file level. If you define them at the record level, specify them for every record from which they should be available.

Single-choice selection fields may be defined in any record. However, an accelerator can be defined only for a single-choice selection field within a pull-down menu. Figure 6-24 on page 6-17 is an example.

	1	2	3	4	5	6	7
A		R PULLEDIT			CF04 CF06		
A					PULLDOWN		
A		F1	2Y 0B 1		1SNGCHCFLD		
A					CHECK(ER)		
A	01				CHOICE(1 '>Undo)
A					CHCACCEL(1 'F4')		
A					CHOICE(2 &MARKTXT)		
A					CHCACCEL(2 &F6)		
A					CHOICE(3 '>Copy)
A		MARKTXT	20A P				
A		F6	2 P				

Figure 6-24. DDS for Accelerator Keys

On display stations in configurations A and B from Table 6-1 on page 6-2, the pull-down menu looks like this:




Figure 6-25. Accelerators in a Pull-Down Menu

Defining a Menu-Bar Switch Key

A **menu-bar switch key** alternates the cursor between the menu bar and the application display.

You can define a menu-bar switch key using the MNUBARSW keyword at either the file level or the record level. If the cursor is in the application record, pressing the menu-bar switch key moves the cursor to the first choice in the menu bar. Pressing the key again moves the cursor from the menu bar back to its previous location in the application record. If you move the cursor using the cursor keys from the application record to the menu bar and then press the menu-bar switch key, the cursor returns to its initial position on the application record. This is the first input field unless cursor positioning keywords are specified on the application record. If a pull-down menu is displayed, pressing the menu-bar switch key cancels the pull-down menu and moves the cursor to the application record.

The system always handles the menu-bar switch key regardless of whether the application or the system displayed the menu bar. (For more information, see the *DDS Reference*.)

For the menu-bar switch key to be active, it must have been active on the last record written to the display. The easiest way to ensure that the menu-bar switch key will always be active is to specify MNUBARSW at the file level. If you specify MNUBARSW at the record level, you must specify it on all records on which it should be active.

Defining a Cancel Key

You can define a cancel key for the menu-bar record and pull-down menu records using the MNUCNL keyword. You can define them either at the file level or the record level.

A **cancel key** closes a pull-down menu and moves the cursor to the associated choice on the menu bar. This is true even if the cursor is not in the pull-down menu. If no pull-down menus are displayed and the cursor is located within the menu bar, the key cancels the menu bar and moves the cursor back to the application record. This location is the cursor's previous location in the application record if the menu-bar switch key was used to move the cursor to the menu bar. If the cursor had been moved to the menu bar with the cursor keys, this location is the initial location of the cursor within the application record. If no pull-down menus are displayed and the cursor is located on the application record, the key returns control to the application program. In this case, the MNUCNL keyword works just as any other key definition keyword, and includes the ability to return a response indicator.

Like the menu-bar switch key, the cancel key is active only if it was active for the last record written to the display. The easiest way to ensure that the cancel key will always be active is to specify the MNUCNL keyword at the file level. If you use the MNUCNL keyword at the record level, you must specify it on all records on which it should be active.

Figure 6-26 shows how to use the MNUBARSW keyword and the MNUCNL keyword. The example sets up command attention key 10 as the menu-bar switch key and command attention key 12 as the cancel key. (These settings are the defaults.)

	1	2	3	4	5	6	7
A					MNUBARSW(CA10)	MNUCNL(CA12)	
A		R MNUBAR			MNUBAR		
A		MNUFLD	2Y 0B	1 2			
A					MNUBARHC(1 PULLFILE +		
A					'>File	'	
A 02					MNUBARHC(2 PULLEDIT +		
A					&EDITTXT)		
A					MNUBARHC(3 PULLVIEW +		
A					'>View	'	
A 04					MNUBARHC(4 PULLOPT +		
A					'>Options	'	
A					MNUBARHC(5 PULLHELP +		
A					'>Help	'	
A		EDITTXT	20A	P			
A		.					
A		.					
A		.					

Figure 6-26. DDS for Menu-Bar Switch Key and Cancel Key

Defining Mnemonics

You can define mnemonics for menu-bar choices, single-choice selection field choices, and multiple-choice selection field choices by using a greater-than (>) character. To identify a mnemonic, place the > character just before the character that you want to be the mnemonic. The > character is not counted as part of the text length. If you want to use the > character as a character in the text rather than as a pointer to the mnemonic, you must use two > characters consecutively. If you specify the > character as the last character in the text, the > character appears as part of the text and no mnemonic appears. Figure 6-27 is an example.

Keyword Specification	Text Appears as
MNUBARHC(1 PULLFILE '>File')	File
MNUBARHC(2 PULLFIN 'F>inish')	Finish
CHOICE(1 'Save >As...')	Save <u>A</u> s...
CHOICE(2 'X >= 1')	X \equiv 1
CHOICE(3 'X >>= 1')	X \geq 1

You cannot specify the > character as a mnemonic.

Figure 6-27. Examples of Valid DDS for Mnemonics

The mnemonic cannot be a blank. Only one mnemonic may be specified in the choice text. Figure 6-28 is an example of incorrect coding.

Keyword Specification	Error
MNUBARHC(1 PULLFILE '>File')	Same mnemonic specified for more than one choice.
MNUBARHC(2 PULLFIN '>finish')	
CHOICE(1 'S>ave >As...')	Two mnemonic characters specified.
CHOICE(4 'X >>= >1')	

Figure 6-28. Examples of DDS Not Valid for Mnemonics

You can select a mnemonic by typing either the uppercase or lowercase mnemonic character. This is true for all languages. The system uses the monospace rules for the appropriate language to identify the mnemonic you typed. Double-byte characters cannot be mnemonics.

Because the system does not support both mnemonic and numeric selection for a field, mnemonics work only when choices are not displayed using numbers.

To determine which configurations support mnemonics, see Table 6-1 on page 6-2.

Defining Choice Colors and Attributes

Normally, the system uses the Common User Access* (CUA) default colors and display attributes when displaying menu-bar choices and selection-field choices. If you do not want to use these defaults, you can define the colors and attributes to be used for the choices using the CHCAVAIL, CHCUNAVAIL, and CHCSLT keywords. Table 6-3 on page 6-20 shows which keywords can be used with each graphical item.

Table 6-3. Keywords Used to Define Colors and Display Attributes

Graphical Item	DDS Keyword		
	CHCAVAIL	CHCUNAVAIL	CHCSLT
Menu-Bar Choice	X		X
Selection Fields	X	X	X

The selection cursor on display stations attached to a controller that supports an enhanced interface for nonprogrammable work stations uses the reverse image form of the colors and attributes you specify for each of the choice states. For example, if you specify pink (normal display) for the available choices, the selection cursor is reverse image pink when it is located on an available choice. If you specify pink reverse image for the available choices, the selection cursor is pink (normal display). Likewise, if you do not specify CHCAVAIL, CHCUNAVAIL, or CHCSLT and use the CUA default colors and attributes, the selection cursor is the reverse image of those colors and attributes.

You can use only the CHCAVAIL keyword and the CHCSLT keyword for menu bars because menu-bar choices are either available or selected. For selection fields, use only the CHCAVAIL keyword and the CHCUNAVAIL keyword when you are using selection characters (for example, numbers or radio buttons). The CHCSLT keyword is ignored in these cases. However, you can use CHCSLT for selection fields in a pull-down menu on graphical display stations or character-based graphical display stations when you have specified that the pull-down menu should not contain selection characters (PULLDOWN(*NOSLTIND) specified).

The display-attribute (*DSPATR) parameter specifies the way in which the separator characters display. The parameter is expressed in this form:

(*DSPATR value1 <value2 <value3...>>)

The valid values for the display attributes are:

Value	Meaning
BL	Blink
CS	Column separator
HI	High intensity
ND	Nondisplay
RI	Reverse image
UL	Underline

The default display attribute for unavailable choices in a selection field on monochrome display stations is normal (or low) intensity. Also, the first character of an unavailable choice on a monochrome display station is overwritten with an asterisk (*).

Display attributes CS, HI, and BL can cause fields on 5292, 3179, and 3197 Model C1 and C2 display stations to appear as color fields. Display attributes HI, RI, and UL cause a separator line not to be displayed. For more information, see the CHCAVAIL keyword, the CHCUNAVAIL keyword, and the CHCSLT keyword in *DDS Reference*.

In Figure 6-29 on page 6-21, the choices in the menu bar are displayed in white on color display stations and in high intensity on monochrome display stations.

When a menu-bar choice is selected, it is displayed in green on color display stations and reverts to normal (not high intensity) display on monochrome display stations.

```

| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|      A      R MENUBAR      MNUBAR
|      A      MNUFLD      2Y 0B 1 2
|      A      MNUBARHC(1 PULLFILE +
|      A      '>File ')
|      A 02      MNUBARHC(2 PULLEDIT +
|      A      &EDITTXT)
|      A      MNUBARHC(3 PULLVIEW +
|      A      '>View ')
|      A 04      MNUBARHC(4 PULLOPT +
|      A      '>Options ')
|      A      MNUBARHC(5 PULLHELP +
|      A      '>Help ')
|      A      MNUBARSEP((*COLOR WHT))
|      A      CHCAVAIL((*COLOR WHT) (*DSPATR HI))
|      A      CHCSLT((*COLOR GRN))
|      A      EDITTXT      20A P
|      .
|      .
|      .

```

Figure 6-29. DDS Using CHCAVAIL and CHCSLT for Menu-Bar Choices

In Figure 6-30, the available selection-field choices are displayed in pink on color display stations and in high intensity on monochrome display stations. The unavailable selection-field choices are displayed in turquoise on color display stations. On monochrome display stations, the unavailable choices are displayed with normal (or low) intensity, and the first character in the choices is overwritten with an asterisk (*).

```

| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|      A      F1      2Y 0B 1 1SNGCHCFLD
|      A 01      CHOICE(1 '>Chocolate ')
|      A      CHOICE(2 '>Strawberry ')
|      A      CHOICE(3 '>Vanilla ')
|      A      CHCCTL(1 &CTLCHOC MSG1112 QUSER/A)
|      A      CHCCTL(2 &CTLSTRA &MSG &LIB/&MSGF)
|      A      CHCCTL(3 &CTLVANI)
|      A      CHCAVAIL((*COLOR PNK) (*DSPATR HI))
|      A      CHCUNAVAIL((*COLOR TRQ))
|      A      CTLCHOC      1Y 0H
|      A      CTLSTRA      1Y 0H
|      A      CTLVANI      1Y 0H
|      A      MSG      7A P
|      A      LIB      10A P
|      A      MSGF      10A P

```

Figure 6-30. DDS Using CHCAVAIL and CHCUNAVAIL for Selection Fields

In Figure 6-31, the selection-field choice that is selected is displayed in yellow. If CHECK(ER) (automatic-enter) is specified on this field, control is returned immediately after selecting the choice.

	1	2	3	4	5	6	7
A	R	PULLDOWN			PULLDOWN(*NOSLTIND)		
A	F1		2Y 0B 1	1	1SNGCHCFLD		
A	01				CHOICE(1 '>Undo')		
A					CHOICE(2 '>Mark')		
A					CHOICE(3 '>Copy')		
A					CHCCTL(1 &CTLUNDO MSG1112 QUSER/A)		
A					CHCCTL(2 &CTLMARK &MSG &LIB/&MSGF)		
A					CHCCTL(3 &CTLCOPY)		
A					CHCAVAIL((*COLOR PNK) (*DSPATR HI))		
A					CHCUNAVAIL((*COLOR TRQ))		
A					CHCSLT((*COLOR YLW))		
A		CTLUNDO		1Y 0H			
A		CTLMARK		1Y 0H			
A		CTLCOPY		1Y 0H			
		.					
		.					
		.					

Figure 6-31. DDS Using CHCAVAIL, CHCUNAVAIL, and CHCSLT for Selection Fields

How the Menu Bar Interacts with the Application

The MNUBARDSP keyword is used to display a menu bar. The MNUBARDSP keyword can be used on an application record (the record that defines the application display) or on a menu-bar record. Option indicators can be used on the MNUBARDSP keyword to control when the menu bar is displayed. If MNUBARDSP is used on the application record, several optioned MNUBARDSP keywords can be specified so that the application can display different menu bars for the same record. If more than one MNUBARDSP keyword is in effect, the system uses the first one.

Defining the MNUBARDSP Keyword on the Application Record

When the MNUBARDSP keyword is used on the record that defines the application display, the system handles all menu-bar operations for the application. The system returns the number of the menu-bar choice selected in a hidden field that is specified on the MNUBARDSP keyword and defined in the application record. If no menu-bar choice is selected, 0 is returned in the hidden field.

		1	2	3	4	5	6	7
A						HELP ALTHelp CF03		
A						MNUBARSW(CA10) MNUCNL(CA12)		
A	R MNUBAR					MNUBAR		
A	MNUFLD	2Y	0B	1	2			
A						MNUBARCHC(1 PULLFILE +		
A						'>File	')
A 02						MNUBARCHC(2 PULLEDIT +		
A						&EDITTXT)		
A						MNUBARCHC(3 PULLVIEW +		
A						'>View	')
A 04						MNUBARCHC(4 PULLOPT +		
A						'>Options	')
A						MNUBARCHC(5 PULLHELP +		
A						'>Help	')
	:							
	:							
A	R APPSCR					MNUBARDSP(MENUBAR &MNUCHOICE)		
A	FIELD1	10A	B	10	12			
A	FIELD2	5S	0B	14	12			
A				24	1	F1=Help F3=Exit +		
A						F10=Actions F12=Cancel		'
A	MNUCHOICE	2Y	0H					

Figure 6-32. DDS Using MNUBARDSP on the Application Record

The DDS in Figure 6-32 causes the following to happen:

1. The application writes any pull-down menu records or menu-bar records that have output to be supplied by the application.
2. The application does a write-read operation to the record with the MNUBARDSP keyword.
3. The system displays the menu bar identified by the MNUBARDSP keyword and handles all interaction between the menu bar and the pull-down menu.
4. If the user selects a menu-bar choice and enters input in the pull-down menu, the system returns the number of the menu-bar choice selected in the choice-hidden field specified on MNUBARDSP.

The system displays the menu-bar record first and then performs the write-read operation to the application record. The active function keys and command keys are those defined on the application record and not those defined on the menu-bar record. If you want to use the MNUCNL keyword or the MNUBARSW keyword, define them at the file level or on the application record.

Ordinarily, writing a record to the display without the OVERLAY keyword causes the entire display to be erased before the record is displayed. The system displays the menu-bar record followed by the application record as if they were logically one record. The system automatically prevents the application record from erasing the menu-bar record. In Figure 6-32, when the system writes the application record, it clears the entire display except for the menu-bar record. The menu-bar record is always processed as though it contains the OVERLAY keyword regardless of any other specifications. For example, if the CLRL keyword is specified on the menu-bar record, it is not used when the menu-bar record is processed. The

OVERLAY keyword and the CLRL keyword are processed normally for the application record; however, the menu-bar record is not cleared.

Defining the MNUBARDSP Keyword on the Menu-Bar Record

If you use the MNUBARDSP keyword on the record containing the menu bar, the application controls when the menu bar is displayed. The system continues to handle any pull-down menu interaction that takes place, and returns the number of the menu-bar choice selected in the menu-bar field itself. If no menu-bar choice was selected, 0 is returned in the menu-bar field. The application must both write the menu-bar record to display the menu bar and read the menu-bar record to determine what choice, if any, was selected.

```

|...+...1...+...2...+...3...+...4...+...5...+...6...+...7...
A                                     HELP ALTHelp CF03
A                                     MNUBARSW(CA10) MNUCNL(CA12)
A      R MNUBAR                      MNUBAR OVERLAY
A 01                                MNUBARDSP
A      MNUFLD                      2Y 0B 1 2
A                                     MNUBARHC(1 PULLFILE +
A                                     '>File      ')
A 02                                MNUBARHC(2 PULLEDIT +
A                                     &EDITTXT)
A                                     MNUBARHC(3 PULLVIEW +
A                                     '>View      ')
A 04                                MNUBARHC(4 PULLOPT +
A                                     '>Options  ')
A                                     MNUBARHC(5 PULLHELP +
A                                     '>Help    ')
A      EDITTXT                      20A P
A      :
A      :
A      R APPSCR                      OVERLAY
A      FIELD1                      10A B 10 12
A      FIELD2                      5S 0B 14 12
A                                     24 1'F1=Help  F3=Exit  +
A                                     F10=Actions F12=Cancel '

```

Figure 6-33. DDS Using MNUBARDSP on the Menu-Bar Record

Following is one scenario using the DDS in Figure 6-33.

1. The application writes the menu-bar record, with the MNUBARDSP keyword active, to display the menu bar.
2. The application does a write-read operation to the application record.
3. The system handles any interaction between the menu bar and the pull-down menu.
4. On input, the application receives the application record.
5. The application reads the menu-bar record to determine which menu-bar choice, if any, was selected.

The only active command keys and function keys are those defined on the application record and not those defined on the menu-bar record. If you want to use the

MNUCNL keyword or the MNUBARSW keyword, define them at the file level or on the application record.

Following is another scenario using the DDS in Figure 6-33 on page 6-24.

1. The application writes the application record.
2. The application performs a write-read operation to the menu-bar record, with the MNUBARDSP keyword active, to display the menu bar.
3. The system handles any interaction between the menu bar and the pull-down menu.
4. On input, the application receives the menu-bar record and determines which menu-bar choice, if any, was selected.
5. The application can also read the application record to receive any input entered on the display.

The only command keys and function keys that are valid are those defined on the menu-bar record. If you want to use the MNUCNL keyword or the MNUBARSW keyword, define them at the file level or on the menu-bar record.

Receiving Input from the Pull-Down Menus

Before a menu-bar record is displayed, any pull-down menu records that have output are written. For example, option indicators may be set or output fields may be filled in. These pull-down menu records are not displayed when written; the system processes and saves the record output until the menu bar is displayed.

A menu-bar record may also be written without being displayed. If the system attempts to write a pull-down menu record or a menu-bar record (without the MNUBARDSP keyword optioned on) while the corresponding menu bar is displayed, an error occurs and the record is not written.

When a valid attention identifier (AID) key (other than the cancel key and the menu-bar switch key) is pressed when a pull-down menu is displayed, control is returned to the application and input may be received from the pull-down menu. The valid AID keys that return input are the Enter key and any CFxx keys that are defined on the pull-down menu record. (A CAXx key returns control to the application, but does not return input.) Keys that are defined for the background display are not valid unless they are also defined on the pull-down menu record. Therefore, define the background keys and the pull-down menu keys once at the file level.

Once a valid AID key (one that returns input) is pressed for a pull-down menu, the application receives input for the record being read (either the application record or the menu-bar record). By looking at the menu-bar choice number that is returned in this record, the application can determine which pull-down menu record has input. The application then must read that pull-down menu record. No I/O operation is done to the display; the input from the pull-down menu is returned to the application and the pull-down menu remains displayed.

Receiving Input from Pull-Down Menus Using the Pull-Down Input Parameter

When one or more of the pull-down menu records contain only one single-choice selection field, you can use the pull-down input (PULLINPUT) parameter on the MNUBARDSP keyword. This lets you receive the single-selection field choice along with the menu-bar choice, instead of reading the pull-down menu record to receive the single-selection field choice.

Figure 6-34 illustrates the use of the PULLINPUT parameter on the MNUBARDSP keyword.

...+....1....+....2....+....3....+....4....+....5....+....6....+....7...									
A									HELP ALTHelp CF03
A									MNUBARSW(CA10) MNUCNL(CA12)
A		R MENUBAR							MNUBAR
A		MNUFLD	2Y	0B	1	2			
A									MNUBARCHC(1 PULLFILE +
A									'>File ')
A									MNUBARCHC(2 PULLEDIT +
A									'>Edit ')
A									MNUBARCHC(3 PULLVIEW +
A									'>View ')
A		R PULLFILE							PULLDOWN
A					2	1			'File name . . . '
A		FNAME	10A	I	2	18			
A		R PULLEDIT							PULLDOWN
A		F1	2Y	0B	1	1			SNGCHCFLD
A									CHOICE(1 '>Copy ')
A									CHOICE(2 '>Delete ')
A		R PULLVIEW							PULLDOWN
A		F1	2Y	0B	1	1			SNGCHCFLD
A									CHOICE(1 '>All ')
A									CHOICE(2 '>Some... ')
A		F2	2Y	0B	4	1			SNGCHCFLD
A									CHOICE(1 'By >date ')
A									CHOICE(2 'By >subject ')
A		R APPSCR							MNUBARDSP(MENUBAR &MNUCHOICE +
A									&PULLINPUT)
A		FIELD1	10A	B	10	12			
A		FIELD2	5S	0B	14	12			
A					24	1			'F1=Help F3=Exit +
A									F10=Actions F12=Cancel '
A		MNUCHOICE	2Y	0H					
A		PULLINPUT	2S	0H					

Figure 6-34. DDS for Pull-Down Input (PULLINPUT) Parameter

When the PULLINPUT parameter is specified on the MNUBARDSP keyword, one of the following values will be returned to the application:

Note: The value is returned in the hidden field (PULLINPUT in Figure 6-34) you have defined in the record with the MNUBARDSP keyword.

PULLINPUT Contents	Meaning
0	No selection made.
n	Choice n in the pull-down menu was selected.

-1 Pull-down menu record contains something other than one single-choice selection field. You must read the pull-down menu record to receive its contents.

Table 6-4 shows the values that are returned in the MNUCHOICE field and the PULLINPUT field using the DDS in Figure 6-34 on page 6-26.

Table 6-4. Values Returned in MNUCHOICE and PULLINPUT

Menu-Bar Choice Selected	Value Returned in Appropriate Field	
	MNUCHOICE	PULLINPUT
File	1	-1
Edit (no selection made in pull-down menu)	2	0
Edit (Copy choice in pull-down menu selected)	2	1
View	3	-1

Removing a Pull-Down Menu after Receiving Input

After the application receives input from a pull-down menu, it may remove the pull-down menu under certain conditions. For example, the application removes the pull-down menu when the application writes or reads (1) a non-window record (in the same display file) or (2) a window record (in the same display file) that contains the RMVWDW keyword. The pull-down menu remains on the display if the application writes or reads a window record (without RMVWDW). This allows the application, UIM help, or application help to write a help window to the display without removing the pull-down menu.

To remove a pull-down menu and present another non-window application display, the application writes the appropriate application record, and the pull-down menu is removed.

To remove the pull-down menu and keep the current application display (perhaps updated), the application performs another write-read (or read) operation to the current (or changed) application record.

To remove the pull-down menu and display a window, the application writes a window with the RMVWDW keyword specified.

To remove the pull-down menu and call another program, the application writes to a dummy record and then calls the other program.

To leave the pull-down menu on the display and present a window (perhaps a help window), the application writes the window record (without RMVWDW).

A pull-down menu remains on the display while UIM help is displayed in a window. A pull-down menu also remains on the display while application help is displayed if the application help record is a window and does not have the RMVWDW keyword specified.

Updating a Pull-Down Menu before Displaying

You can enable your application to update a pull-down menu using the return-field parameter on the MNUBARHC keyword. The pull-down menu is updated after a menu-bar choice is selected and before the pull-down menu is displayed. The return-field parameter is a hidden field that returns the number of the choice selected for the application to (1) determine that control was returned before the pull-down menu was displayed rather than because input was entered in the pull-down menu, and (2) determine which pull-down menu record to update and write.

```
| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A      R MNUBAR          MNUBAR
A      MNUFLD          2Y 0B 1 2
A      MNUBARHC(1 PULLFILE +
A      '>File          ' &RTNFLD)
:
:
A      MNUBARHC(4 PULLOPT +
A      '>Options          ' +
A      &RTNFLD)
:
A      RTNFLD          2Y 0H
:
A      R PULLFILE
A      PULLDOWN
A      F1          2Y 0B 1 1SNGCHCFLD
:
:
A      R PULLOPT
A      PULLDOWN
A      F1          2Y 0B 1 1SNGCHCFLD
:
:
```

Figure 6-35. DDS for Return-Field Parameter

For the DDS in Figure 6-35, if the user selects menu-bar choice 1 or 4, control is returned to the application with the choice number set in the RTNFLD field. The menu-bar field or the choice field in the application record contains 0, indicating no pull-down menu input was received. The application must read the menu-bar record to get the contents of the RTNFLD field. The application then updates the pull-down menu record for that choice and writes it. The application must read the menu-bar record or the application record to request the display. After control has been returned for updating the pull-down menu, the next record written must be the pull-down menu specified on the MNUBARHC keyword. In this example, if choice 1 was selected, record PULLFILE must be written; if choice 4 was selected, record PULLOPT must be written. The system then displays the pull-down menu for the choice and resumes control of the menu bar and pull-down menu interaction. A read operation to a pull-down menu is not allowed until input has been received for the pull-down menu. A write-read operation is never allowed.

Defining Application Help

You can define application help for menu-bar choices, selection-field choices, named fields, constant fields, menu bars, and pull-down menus.

Defining Choice-Level Help

You can define help for menu-bar choices, single-choice selection fields, and multiple-choice selection fields using the HLPARA keyword. Figure 6-36 is an example of the DDS coding for menu-bar choice help.

```
| .....1.....2.....3.....4.....5.....6.....7...
|
| A                                     HELP
| A          R MENUBAR                 MNUBAR
| A          H                         HLPARA(*FLD MNUFLD 1)
| A                                     HLPRCD(FILEHLP LIB/FILE)
| A          H                         HLPARA(*FLD MNUFLD 2)
| A                                     HLPRCD(EDITHLP LIB/FILE)
| A          H                         HLPARA(*FLD MNUFLD 3)
| A                                     HLPRCD(VIEWHLP LIB/FILE)
| A          H                         HLPARA(*FLD MNUFLD 4)
| A                                     HLPRCD(OPTHLP LIB/FILE)
| A          H                         HLPARA(*FLD MNUFLD 5)
| A                                     HLPRCD(HLPHLP HLPLIB/HLPFILE)
| A          MNUFLD          2Y 0B 1 2
| A                                     MNUBARHC(1 PULLFILE +
| A                                     '>File          ')
| A 02                                     MNUBARHC(2 PULLEDIT +
| A                                     &EDITTXT)
| A                                     MNUBARHC(3 PULLVIEW +
| A                                     '>View          ')
| A 04                                     MNUBARHC(4 PULLOPT +
| A                                     '>Options        ')
| A                                     MNUBARHC(5 PULLHELP +
| A                                     '>Help          ')
| A          EDITTXT          10  P
```

Figure 6-36. DDS for Menu-Bar Choice Help

Figure 6-37 on page 6-30 is an example of the DDS coding for single-selection field choice help.

	1	2	3	4	5	6	7
A							HELP
A		R	PULLEDIT				CF04 CF06
A							WDWBORDER(((*CHAR '+-+ +-+')
A							PULLDOWN
A		H					HLPARA(*FLD F1 1)
A							HLPRCD(UNDOHLP LIB/FILE)
A		H					HLPARA(*FLD F1 2)
A							HLPRCD(MARKHLP LIB/FILE)
A		H					HLPARA(*FLD F1 3)
A							HLPRCD(COPYHLP LIB/FILE)
A		F1		2Y 0B 1	1		1SNGCHCFLD
A							CHECK(ER)
A	01						CHOICE(1 '>Undo')
A							CHOICE(2 '>Mark')
A							CHOICE(3 '>Copy')

Figure 6-37. DDS for Single-Selection Field Choice Help

Use the *FLD special value on the HLPARA keyword to indicate that the help area is for a field. Following *FLD, specify the name of the field for which you are defining help. Following the name of the field, specify the number of the choice for which you are defining help.

The help area that you specify for a choice is the area that the choice text occupies (plus the attribute byte positions on either side). If compression occurs, the help area moves with the choice. When a choice is optioned off, the help specification for that choice is also optioned off because the help area for that choice does not exist.

As with any help specification, the text for choice-level help can be defined using DDS records (HLPRCD keyword), OfficeVision/400* documents (HLPDOC keyword), or UIM panel groups (HLPPNLGRP).

Help specifications must define help areas within the area encompassed by the menu-bar record or the pull-down record.

If you use UIM help, item-specific help for a menu-bar choice includes the help modules for the menu-bar choice and its pull-down menu. If you use DDS or OfficeVision/400 document help, item-specific help for the menu-bar choice is the help for the menu-bar choice. The help area for the menu-bar choice includes the text for the choice plus one space on each side of the text. The middle space between the choices is part of the extended help area.

Item-specific help for menu bars is displayed when the cursor is located in one of the following areas:

- A menu-bar choice (if there is help for that choice).
- Anywhere within an active pull-down record that does not include an active help area. When the cursor is on the pull-down menu border, item-specific help is displayed for the menu-bar choice item.

Item-specific help for a pull-down menu choice is displayed when the cursor is in an active help area in the pull-down menu. The help area for a pull-down menu choice starts on the first digit of the number and ends at the border of the selection

field. Help for pull-down menus and menu bars are part of the extended help for the display. When the pull-down menu is displayed, all help areas are active except the ones that are overlapped by the pull-down menu. Help for overlapped areas can be viewed only in extended help. If a base display help area is partially overlapped by a pull-down menu, the part of the help area that is not overlapped is still active.

There are two help lists; one for the base display and one for the menu bar and its pull-down menus. The help list for the menu bar is created when the menu bar is displayed. The help list is destroyed when the menu bar is removed from the display. For an example of a help list for a menu bar, see Figure 6-38. The help list is updated when the menu bar or pull-down menu is written again. When the cursor is in a menu bar or pull-down menu, the menu-bar help list is searched for item-specific help. The menu-bar help list is considered above the base-display help list. When extended help is displayed, help for menu bars and pull-down menus is presented immediately after general help. Base display help is presented after menu-bar help and pull-down menu help. If DDS help is used and the user initially selects pull-down menu help, the user then can page up to see menu-bar help and page down to see base-display help.

Help for File menu bar choice
Help for File pulldown choice 1
Help for File pulldown choice 2
.
.
.
Help for View menu bar choice
Help for View pulldown choice 1
Help for View pulldown choice 2
.
.
.

Figure 6-38. A Help List for a Menu Bar

Defining Help for a Field

Help can be defined for a field or constant using the HLPARA keyword. For a named field, specify the help area using the *FLD special value and the name of the field. For a constant field, specify the help area using the *CNST special value and an identifier for the constant field. The identifier you specify on the HLPARA keyword should be the same as the value specified on the HLPID keyword for the constant field.

1	2	3	4	5	6	7
A						HELP
A		R	RECORD			
A		H				HLPARA(*FLD FIELD)
A						HLPACD(FIELDHLP LIB/FILE)
A		FIELD	10A	B	5	5

Figure 6-39. Help for a Named Field

1	2	3	4	5	6	7
A						HELP
A		R	RECORD			
A		H				HLPARA(*CNST 1)
A						HLPACD(HLPCNST1 LIB/FILE)
A				2	2	'Constant field' HLPID(1)

Figure 6-40. Help for a Constant Field

When the display file is created, the actual help area coordinates are determined by the DDS compiler. These coordinates are shown in the expanded source section of the DDS listing (unless the field is a choice field).

If the field or constant field location or length is changed and the file is re-created, the help area for the field is updated to reflect the new location or length.

Key Interaction for Menu Bars and Pull-Down Menus

Figure 6-41 shows an example of a display you might create with a menu bar and a pull-down menu. Capital letters A, B, C, D, and E indicate possible cursor locations.




Figure 6-41. Cursor Locations

Table 6-5 on page 6-33 describes the actions that are performed when certain keys are pressed at the cursor locations.

Table 6-5. Actions Performed at Different Cursor Locations

Cursor Location	Action Performed When Appropriate Key Is Pressed			
	Help	Cancel	Menu-Bar Switch	Enter
A	Help for File menu-bar choice is displayed. (Includes help for the pull-down menu.)	Pull-down menu is removed. Cursor moves to Edit menu-bar choice.	Pull-down menu is removed. Cursor returns to display work area.	File pull-down menu is displayed; Edit pull-down menu is removed.
B	Extended help is displayed.	Pull-down menu is removed. Cursor moves to Edit menu-bar choice.	Pull-down menu is removed. Cursor returns to display work area.	<i>Cursor not on menu bar choice</i> message is displayed. Cursor does not move.
C	Help for Undo choice is displayed.	Pull-down menu is removed. Cursor moves to Edit menu-bar choice.	Pull-down menu is removed. Cursor returns to display work area.	If user made a selection, control returns to application. If not, cursor moves to input field and message to make a selection is sent.
D	Help for Edit menu-bar choice is displayed. (Includes help for the pull-down menu.)	Pull-down menu is removed. Cursor moves to Edit menu-bar choice.	Pull-down menu is removed. Cursor returns to display work area.	If user made a selection, control returns to application. If not, cursor moves to input field and message to make a selection is sent.
E	Help for function keys is displayed.	Pull-down menu is removed. Cursor moves to Edit menu-bar choice.	Pull-down menu is removed. Cursor returns to display work area.	If user made a selection, control returns to application. If not, sound beep and cursor moves to input field.

Creating Continued-Entry Fields

A **continued-entry field** is a set of associated entry fields. Continued-entry fields are supported on displays attached to any controller. Controllers that support an enhanced interface for nonprogrammable work stations treat continued-entry fields as single-entry fields while data is being entered and edited in the fields.

Note: Controllers that do not support an enhanced interface for nonprogrammable work stations treat continued-entry fields as separate input fields. Insert and delete characters one segment at a time. When you reach the end of a segment, the cursor does not move automatically to the next segment.

Neither type of controller supports double-byte character set (DBCS) data.

Figure 6-42 on page 6-34 illustrates the use of continued-entry fields to create a rectangular text entry field. Consider using this format to avoid using a single input field that wraps across multiple lines.

Note: The empty space at the end of the last line is still part of the continued-entry field. You cannot define another field in this space.

Enter Text . . . _____

Figure 6-42. Continued-Entry Fields in Rectangular Arrangement

A continued-entry field allows a multiple-row entry field to be defined inside of a window or display.

The DDS for the field looks like this:

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
      A              F1              90A B 3 4CNTFLD(30)
```

The CNTFLD keyword tells the system that this is a continued-entry field and its parameter tells the system how wide the field should be. The system breaks the field into columns and uses as many lines as it needs to reach the specified width.

The system processes local keyboard functions specified within the continued-entry fields on a display station attached to a controller that supports an enhanced interface for nonprogrammable work stations by the following definitions:

Character data

In replace mode, there is no unique character data processing. When character data is entered in the last character position of one of the fields in the set, the cursor moves to the first character position of the next field in the set. When character data is entered in the last character position of the last field in the continued fields, forward field-exit processing is performed (see "Forward Field-Exit Processing" on page 6-36).

In insert mode, when a character data key is pressed, the following actions occur:

- The null in the last character position of the last field in the continued-entry fields is deleted. If there is no null in the last position of this field, operator error 0012 is posted.
- All field data within the continued-entry fields at (and logically following) the current cursor location are shifted one position. Each data character in the last character position of the current and remaining fields (except the last) in the set is shifted to the first character position of the following field.
- The data character entered is written at the cursor location.
- The cursor advances to the next cursor position.

Field Mark

Processed the same as character data.

Delete	<p>If the delete key is pressed within a continued-entry field, the following actions occur:</p> <ul style="list-style-type: none"> • All field data within the continued-entry fields logically following the current cursor location is shifted toward the cursor one position. Each data character in the first character position of the remaining fields in the set is shifted to the last character position of the preceding field. • A null is written in the last character position in the continued-entry fields.
Erase EOF	All field positions at (and logically following) the current cursor location within the continued-entry fields are nulled.
Erase Input	All field positions of all changed fields are nulled. This includes all continued-entry field segments if any continued-entry field segment has been changed.
Field Exit	<p>Pressing the Field Exit key within a continued-entry field causes the following actions to occur:</p> <ul style="list-style-type: none"> • All field data within the continued-entry fields at (and logically following) the current cursor location are nulled. • Forward field-exit processing is performed (see “Forward Field-Exit Processing” on page 6-36).
Field Plus	Processed the same as Field Exit.
Field Minus	Not allowed. Operator error 0016 is posted.
Dup	<p>Pressing the Dup key within a continued-entry field causes the following actions to occur:</p> <ul style="list-style-type: none"> • All field data within the continued-entry fields at (and logically following) the current cursor location are set to the Dup character (1C). • Forward field-exit processing is performed (see “Forward Field-Exit Processing” on page 6-36).
Character Backspace	Pressing the Character Backspace key in the first position of the first segment, moves the cursor to the last position of the previous field. (The previous field could be a continued-entry field. The cursor moves to the last position of the last segment which could be further down on the display.) Pressing the Character Backspace key in the first position in a segment other than the first segment, moves the cursor to the last position of the previous segment.
Character Advance	Pressing the Character Advance key in the last position of the last segment, moves the cursor to the first position of the next field. Pressing the Character Advance key in the last position of a segment other than the last segment, moves the cursor to the first position of the next segment.

New Line

Pressing the New Line key generally moves the cursor to the next position on the display that allows a cursor. If the cursor is in a continued-entry field and an additional continued-entry field segment is on the next row or a subsequent row, the cursor moves to the first position of that segment. If the continued-entry field is also a highlighted field with an invisible text cursor, then pressing the New Line key exits the continued-entry field. When the cursor moves into a continued-entry field because the New Line key was pressed, the cursor is always positioned in the first position of the first segment. Pressing the New Line key never moves the cursor into a middle or last continued-entry field segment.

Field Advance

Field Advance performs forward field-exit processing (see “Forward Field-Exit Processing”).

Field Backspace

Field Backspace performs backward field-exit processing (see “Backward Field-Exit Processing”).

Forward Field-Exit Processing

The system does not validate field data when the cursor exits continued-entry fields because mandatory fill and self-check functions are not supported.

If the continued-entry fields are specified as automatic-enter or forward-edge trigger, the system performs automatic-enter or forward-edge trigger processing for the last position of the last segment.

If cursor progression is specified on the first continued-entry field segment, the cursor moves to the cursor-progression target field when it exits any of the continued-entry field segments.

If cursor progression is not specified on the first continued-entry field segment, and the cursor exits the continued-entry field in the forward direction, the cursor skips any subsequent segments of the continued-entry field and moves to the next non-protected field.

Note: If a continued-entry field is also defined as a highlighted field, the system restores the leading-field attribute of each segment when the cursor exits the field.

Backward Field-Exit Processing

When exiting the field backward, the cursor skips any previous segments of the continued-entry field and moves to the previous nonprotected field. Cursor progression may cause the cursor to move to a different field.

Defining Cursor Progression for Entry Fields

The FLDCSRPRG keyword lets the user specify the next field the cursor should move to when the cursor leaves a field.

The DDS for the field looks like this:

		...	+	1	+	2	+	3	+	4	+	5	+	6	+	7	...
	A				F1				10A	B	3		4FLDCSRPRG(F3)																	
	A				F2				10A	B	13		4FLDCSRPRG(F1)																	
	A				F3				10A	B	16		4FLDCSRPRG(F2)																	

| *Figure 6-43. DDS for Field-Level Cursor Progression*

| The parameter for the FLDCSRPRG keyword is the name of the field the cursor will
 | go to when forward field-exit processing is performed. When the cursor leaves F1
 | because of a field exit key, it goes to F3. If the field named with this keyword is
 | optioned off, cursor progression for this field is ignored.

| **Note:** When the cursor leaves a field using backward field-exit processing, the
 | cursor moves to the first field on the display that has the exited-field name
 | specified on the FLDCSRPRG keyword. For the DDS in Figure 6-43, if
 | backward field-exit processing is used to leave field 2, the cursor moves to
 | field 3.

| SFLCSRPRG is the keyword used for subfile cursor progression. The DDS for
 | subfiles looks like this:

		...	+	1	+	2	+	3	+	4	+	5	+	6	+	7	...
	A				R SFL01								SFL																	
	A				S1				10A	B	5		5SFLCSRPRG																	
	A				S2				10A	B	5	25																		
	A				R CTL01								SFLCTL(SFL01)																	
	A												SFLPAG(5) SFLSIZ(20) SFLDSP																	

| *Figure 6-44. DDS for Subfile-Level Cursor Progression*

| The SFLCSRPRG keyword causes the cursor to move from a field in a subfile
 | record to the same field in the next displayed subfile record. Without
 | SFLCSRPRG, the cursor moves from a field in a record to the next field in the
 | same record. When the cursor leaves field S1 of the first record of the subfile, it
 | goes to S1 of the second record of the subfile. Without the SFLCSRPRG keyword,
 | the cursor goes to field S2 of the first record. When the cursor leaves S2, it goes
 | to S1 of the next record because S2 does not have the SFLCSRPRG keyword.
 | This keyword is not allowed with subfiles that use field selection. It can be used
 | with horizontal subfiles. When the cursor is on S1 of the last SFL record displayed,
 | the cursor moves to the next input field below the last SFL record. If there are no
 | remaining SFL fields, the cursor moves to the top of the display.

| **Note:** The FLDCSRPRG keyword and the SFLCSRPRG keyword are ignored on
 | displays that are attached to a controller that does not support an enhanced
 | interface for nonprogrammable work stations.

| **Defining Attributes for Entry Fields**

| An entry field's leading field attribute is changed to a specified attribute when the
 | cursor enters the field.

| The DDS for the field looks like this:

```
| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|      A          F1          10A B 3 4ENTFLDATR(*CURSOR (*DSPATR CS))
|      A          F2          10A B 13 4ENTFLDATR(*NOCURSOR (*COLOR RED))
```

ENTFLDATR tells the system to change the attribute of the field when the cursor enters the field. *CURSOR and *NOCURSOR are used to specify whether the cursor is visible when it enters the field. If the *NOCURSOR option is specified, the cursor row and column values in the input-output feedback area indicate the first position in the field. You can also specify a color or an attribute.

Note: The ENTFLDATR keyword is ignored on displays that are attached to a controller that does not support an enhanced interface for nonprogrammable work stations.

Protecting Entry Fields Using Edit Masks

The EDTMSK keyword is a new DDS keyword for fields with EDTCDE or EDTWRD keywords. When the field is displayed, certain areas of the field will be protected. You define which areas to protect.

The DDS for the field looks like this:

```
| ...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
|      A          F1          6 0B 3 4EDTWRD(' / / ')
|      A          EDTMSK(' & & ')
|      A          F2          6 0B 4 4EDTCDE(Y)
|      A          EDTMSK(' & & ')
|
```

The ampersand (&) represents a protected part of the field. A blank represents an unprotected part of the field. The length of the edit mask must equal the display length of the field. The number of unprotected positions must at least equal the program length of the field. You must only protect nonnumeric data because protected data is not returned if the field is changed. Wherever there is an &, that part is protected no matter what data is in the field.

The first field has the slash (/) characters protected in a date. For the second field, the / in the date is always protected.

Keyboard functions on displays attached to a controller that supports an enhanced interface for nonprogrammable work stations are the same for edit-mask fields as they are for continued-entry fields.

Note: The EDTMSK keyword is ignored on display stations attached to a controller that does not support an enhanced interface for nonprogrammable work stations.

Cursor Movement

You can move the cursor on the application displays that you create using the Tab key or the Cursor keys.

Pressing the Tab Key

Pressing the tab key moves the cursor from field to field on the display, progressing from left to right and top to bottom.

On display stations in configuration F from Table 6-2 on page 6-3, the following is true:

- The Menu-bar choices are individual fields.
- The single-choice selection field is one field.
- The multiple-choice selection fields are individual fields.

Pressing the Tab key for one of these displays when no pull-down menu is displayed moves the cursor from choice to choice in the menu bar. Then, the cursor moves from input field to input field on the rest of the display. When a pull-down menu is displayed on one of these displays, pressing the Tab key does the following:

1. Moves the cursor from choice to choice in the menu bar.
2. Skips over the choice selected.
3. Moves the cursor from input field to input field within the pull-down menu.
4. Moves the cursor back to the first choice in the menu bar (the pull-down menu for that choice is not automatically displayed).

While the pull-down menu is displayed, you cannot enter data in the input fields on the base display nor can you tab to the input fields.

On display stations in configurations A, B, and C from Table 6-1 on page 6-2, and configurations D and E from Table 6-2 on page 6-3, the menu bar is a single field. If no pull-down menu is displayed, pressing the Tab key moves the cursor from choice to choice within the menu bar. The cursor performs a wraparound. When a menu-bar choice is selected, the cursor is placed in the first input field within the pull-down menu. Pressing the Tab key moves the cursor from input field to input field within the pull-down menu and then moves the cursor to the next menu-bar choice. While the pull-down menu is displayed, you cannot enter data in the input fields on the base display nor can you tab to the input fields on the base display.

Pressing the Cursor Keys

On display stations in configuration F from Table 6-2 on page 6-3, pressing a cursor key moves the cursor one position in the appropriate direction.

On display stations in configurations A, B, and C from Table 6-1 on page 6-2, and configurations D and E from Table 6-2 on page 6-3, the cursor moves differently depending on the type of field it is in.

- In the menu bar, pressing the cursor-right or cursor-left keys moves the cursor from choice to choice. The cursor does not perform a wraparound.
- In the base display, pressing any cursor key moves the cursor one position in the appropriate direction.
- When the cursor is positioned on a selection field that is the only selection field in a pull-down menu, pressing the cursor-right or cursor-left keys does the following:
 1. Displays the pull-down menu for the next choice (to the right or left)
 2. Places the cursor within that pull-down menu.

The cursor performs a wraparound.

Simple Hotspots

Controllers that support an enhanced interface for nonprogrammable work stations provide simple hotspots. A **hotspot** is an area of a display that, when clicked on, performs a function. You must have a display station with a mouse. Hotspots are available on configurations A and B from Table 6-1 on page 6-2. On InfoWindow II display stations, the hotspot must be selected with the left mouse button.

The following hotspots are provided by controllers that support an enhanced interface for nonprogrammable work stations:

- Command key emulation
- Page Up and Page Down key emulation
- Enter key emulation

The user can perform the Enter function on InfoWindow II display stations by double-clicking the left mouse button.

Command Key Emulation

When the user clicks on a command key, the pointer device cursor must be between the first and last characters (inclusive) of the command key. When the user selects the command key, the keyboard locks and the command key is processed. The function performed is defined by DDS. The system performs the function as if the actual command key had been pressed. This includes setting response indicators.

When the user clicks on a command key, the system scans the command key text to the left until it finds one of the following:

- An attribute
- Two blanks
- Two nulls
- A blank and a null
- Column one of the row

After finding the beginning of the command key text string, the system scans the text to the right until it finds a match with one of the following:

Fx=	x can be 1 to 9.
Fyx=	y can be 0, 1, or 2. If y is 0, x can be 1 to 9. If y is 1, x can be 0 to 9. If y is 2, x can be 0 to 4.
PFx=	x can be 1 to 9.
PFyx=	y can be 0, 1, or 2. If y is 0, x can be 1 to 9. If y is 1, x can be 0 to 9. If y is 2, x can be 0 to 4.
PFx	x can be 1 to 9.
PFyx	y can be 0, 1, or 2. If y is 0, x can be 1 to 9. If y is 1, x can be 0 to 9. If y is 2, x can be 0 to 4.

After the system finds a match, it performs the command key function.

Page Up and Page Down Key Emulation

The user can click on the plus (+) and minus (–) characters to page down (roll up) and page up (roll down), respectively. When the user clicks on the + or – characters, the keyboard locks and a Roll Up AID key and Roll Down AID key is generated. The function performed is defined by DDS. The system performs the function as if the actual key had been pressed.

One way to implement this function is to do the following:

1. Specify *MORE on the Subfile End (SFLEND) keyword.

This causes the display file to use the text defined on the CPX6AB2 and CPX6AB1 messages. The default text for these messages is More ... and Bottom, respectively.

2. Change the text for the CPX6AB2 message to More: +/-.
3. Change the text for the CPX6AB1 message to Bottom: -.

Programming Examples

Following are examples of the DDS required to display a menu bar and a pull-down menu with a description of how the DDS coding works.

Using the MNUBARDSP Keyword on the Application Record

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A                                     HELP ALTHelp CF03
A                                     MNUBARSW(CA10) MNUCNL(CA12)
A                                     CF04(04) CF06(06)
A          R MNUBAR                  MNUBAR
A          H                        HLPARA(*FLD MNUFLD 1)
A                                     HLPARCD(FILEHLP HLPLIB/HLPFILE)
A          H                        HLPARA(*FLD MNUFLD 2)
A                                     HLPARCD(EDITHLP HLPLIB/HLPFILE)
A          H                        HLPARA(*FLD MNUFLD 3)
A                                     HLPARCD(VIEWHLP HLPLIB/HLPFILE)
A          H                        HLPARA(*FLD MNUFLD 4)
A                                     HLPARCD(OPTHLP HLPLIB/HLPFILE)
A          H                        HLPARA(*FLD MNUFLD 5)
A                                     HLPARCD(HELPHLP HLPLIB/HLPFILE)
A          H                        HLPARA(*FLD MNUFLD)
A                                     HLPARCD(MNUBARHLP HLPLIB/HLPFILE)
A          MNUFLD                    2Y 0B 1 2
A                                     MNUBARHC(1 PULLFILE +
A                                     '>File      ')
A 02                                     MNUBARHC(2 PULLEDIT +
A                                     &EDITTXT)
A                                     MNUBARHC(3 PULLVIEW +
A                                     '>View      ')
A 04                                     MNUBARHC(4 PULLOPT +
A                                     '>Options    ' &RTNFLD)
A                                     MNUBARHC(5 PULLHELP +
A                                     '>Help      ')
A                                     MNUBARSEP((*COLOR WHT))
A                                     CHCAVAIL((*COLOR YLW) (*DSPATR HI))
A                                     CHCSLT((*COLOR GRN))
A          EDITTXT                    20A P
```

A	RTNFLD	2Y 0H	
A	R PULLEDIT		
A			PULLDOWN
A	H		HLPARA(*FLD F1 1)
A			HLPRCD(UNDOHLP HLPLIB/HLPFILE)
A	H		HLPARA(*FLD F1 2)
A			HLPRCD(MARKHLP HLPLIB/HLPFILE)
A	H		HLPARA(*FLD F1 3)
A			HLPRCD(COPYHLP HLPLIB/HLPFILE)
A	F1	2Y 0B 1	1SNGCHCFLD
A			CHECK(ER)
A	01		CHOICE(1 '>Undo')
A			CHOICE(2 &MARKTXT)
A			CHOICE(3 '>Copy')
A			CHCCTL(1 &CTLUNDO MSG1112 QUSER/A)
A			CHCCTL(2 &CTLMARK &MSG &LIB/&MSGF)
A			CHCCTL(3 &CTLCOPY)
A			CHCACCEL(1 'F4')
A			CHCACCEL(2 'F6')
A			CHCAVAIL((*COLOR WHT))
A			CHCUNAVAIL((*COLOR BLU))
A	MARKTXT	20A P	
A	CTLUNDO	1Y 0H	
A	CTLMARK	1Y 0H	
A	CTLCOPY	1Y 0H	
A	MSG	7A P	
A	LIB	10A P	
A	MSGF	10A P	
A	R PULLOPT		
A			PULLDOWN
A	H		HLPARA(*FLD F1 1)
			:
			:
A	F1	2Y 0B 1	1SNGCHCFLD
			:
			:
A	R APPSCR		MNUBARDSP(MENUBAR &MNUCHOICE +
A			&PULLINPUT)
A	FIELD1	10A B 10 12	
A	FIELD2	5S 0B 14 12	
A		24 1'	F1=Help F3=Exit +
A			F10=Actions F12=Cancel '
A	MNUCHOICE	2Y 0H	
A	PULLINPUT	2S 0H	

Description

In the example using the MNUBARDSP keyword on the application record, the application does a write-read operation to the APPSCR record. This causes the MENUBAR record and the APPSCR record to be displayed. Because the field EDITTXT in the MENUBAR record contains the text >Edit, Edit is displayed as the text for the second menu-bar choice.

Pressing the F10 key provides quick access to the menu bar (which is always active). Pressing F10 moves the cursor to the first choice in the menu bar.

Pressing F10 again (or F12) moves the cursor back to where it was on the application display. On display stations in configuration F from Table 6-2 on page 6-3, pressing the Tab key moves the cursor from choice to choice in the menu bar. The cursor skips over any menu-bar choice that is selected. It then moves from input field to input field on the entire display. On display stations in configurations A, B, and C from Table 6-1 on page 6-2, and configurations D and E from Table 6-2 on page 6-3, when the cursor is located within a menu bar, the cursor movement keys or the Tab key moves the cursor from choice to choice within the menu bar.

If the user selects the Edit action, the system displays the pull-down menu record (PULLEDIT). CHECK(ER) specifies automatic-enter. When the user types a value in F1, control is returned to the application without the user having to press the Enter key. If the user presses F4 or F6, control is also returned to the application.

Because the application performed a write-read operation to the APPSCR record, the APPSCR record is returned to the application. Field MNUCHOICE contains a 2 to identify that menu-bar choice 2 was selected. The PULLINPUT field contains the single-selection field choice (the contents of F1) of the PULLEDIT record.

If the user selects the Options action, control is returned to the application, with 4 set in field RTNFLD and 0 set in field MNUCHOICE. The application determines from the 0 in field MNUCHOICE that control has been returned for pull-down menu update. The application reads record MENUBAR to obtain the choice number set in field RTNFLD. The application updates the record PULLOPT and then writes record PULLOPT. The system then displays PULLOPT as the pull-down menu for the options choice. The system resumes control of the menu bar interaction when the application performs a read operation to the APPSCR record.

On display stations in configurations A and B from Table 6-1 on page 6-2, the menu bar separator and the pull-down menus display as solid lines.

On display stations in configuration C from Table 6-1 on page 6-2, and configurations D, E, and F from Table 6-2 on page 6-3, the menu-bar separator is made up of dashes. The side and bottom borders of the pull-down menu are made up of colons and periods, respectively.

On display stations in configuration C from Table 6-1 on page 6-2, each menu-bar choice has a mnemonic. On display stations in configurations A and B from Table 6-1 on page 6-2, each single-selection field choice in the PULLEDIT pull-down menu has a mnemonic. This is true unless ENHDSP(*NO) is specified on the CRTDSPF command or CHGDSPF command). In this example, the mnemonic has been set up to be the first character in each of the choices.

Using the MNUBARDSP Keyword on the Menu-Bar Record

	1	2	3	4	5	6	7
A	HELP	ALTHELP	CF03	(03)			
A	MNUBARSW	(CA10)	MNUCNL	(CA12 12)			
A	CF04	(04)	CF06	(06)			
A		R	MENUBAR				
A	01						
A		H					
A							
A		H					
A							
A		H					

	A				HLPRCD(VIEWHLP HLPLIB/HLPFILE)
	A	H			HLPARA(*FLD MNUFLD 4)
	A				HLPRCD(OPTHLP HLPLIB/HLPFILE)
	A	H			HLPARA(*FLD MNUFLD 5)
	A				HLPRCD(HELPHLP HLPLIB/HLPFILE)
	A	MNUFLD	2Y 0B	1 2	
	A				MNUBARHC(1 PULLFILE +
	A				'>File')
	A	02			MNUBARHC(2 PULLEDIT +
	A				&EDITTXT)
	A				MNUBARHC(3 PULLVIEW +
	A				'>View')
	A	04			MNUBARHC(4 PULLOPT +
	A				'>Options' &RTNFLD)
	A				MNUBARHC(5 PULLHELP +
	A				'>Help')
	A				MNUBARSEP((*COLOR WHT) +
	A				(*CHAR '-'))
	A	EDITTXT	20A	P	
	A	RTNFLD	2Y	0H	
	A	R PULLEDIT			
	A				PULLDOWN
	A	H			HLPARA(*FLD F1 1)
	A				HLPRCD(UNDOHLP HLPLIB/HLPFILE)
	A	H			HLPARA(*FLD F1 2)
	A				HLPRCD(MARKHLP HLPLIB/HLPFILE)
	A	H			HLPARA(*FLD F1 3)
	A				HLPRCD(COPYHLP HLPLIB/HLPFILE)
	A	F1	2Y 0B	1 1	SNGCHCFLD
	A	01			CHOICE(1 '>Undo')
	A				CHOICE(2 &MARKTXT)
	A				CHOICE(3 '>Copy')
	A				CHCCTL(1 &CTLUNDO MSG1112 QUSER/A)
	A				CHCCTL(2 &CTLMARK &MSG &LIB/&MSGF)
	A				CHCCTL(3 &CTLCOPY)
	A				CHCACCEL(1 'F4')
	A				CHCACCEL(2 'F6')
	A	MARKTXT	20A	P	
	A	CTLUNDO	1Y	0H	
	A	CTLMARK	1Y	0H	
	A	CTLCOPY	1Y	0H	
	A	MSG	7A	P	
	A	LIB	10A	P	
	A	MSGF	10A	P	
	A				
	A	R PULLOPT			
	A				PULLDOWN
	A	H			HLPARA(*FLD F1 1)
					:
					:
	A	F1	2Y 0B	1 1	SNGCHCFLD
		:			
		:			
	A				
	A	R APPSCR			
	A	FIELD1	10A	B 10 12	
	A	FIELD2	5S	0B 14 12	

A	24 1'F1=Help F3=Exit +
A	F10=Actions F12=Cancel

Description

In the example using the MNUBARDSP keyword on the menu-bar record, the application writes the MENUBAR record to display the menu bar. The application then performs a write-read operation to the APPSCR record to display the application display.

As in the previous example, F10 provides quick access to the menu bar (which is always active). Pressing F10 moves the cursor to the first choice in the menu bar. Pressing F10 again (or F12) moves the cursor back to where it was on the application display.


On display stations in configuration F from Table 6-2 on page 6-3, pressing the Tab key moves the cursor from choice to choice in the menu bar and from input field to input field on the entire display. The cursor skips over any menu-bar choice that is selected.

When the cursor is located within a menu bar on display stations in configurations A, B, and C from Table 6-1 on page 6-2, and configurations D and E from Table 6-2 on page 6-3, the cursor movement keys or the Tab key moves the cursor from choice to choice within the menu bar.

If the user selects the Edit action, the system displays the pull-down menu record (PULLEDIT). Because CHECK(ER) is not specified on field F1, the user enters a value by typing the choice number and pressing the Enter key, or by pressing F4 or F6. When a value is entered or an accelerator key is pressed, control is returned to the application. Because the application was doing a write-read operation to the APPSCR record, the APPSCR record is returned to the application. The application must then read the MENUBAR record to determine the choice selected (2 is returned in field MNUFLD). Because the input-field parameter was not specified on the MNUBARDSP keyword, the application reads record PULLEDIT to receive the pull-down menu input.

How the Displays Look

On display stations in configurations A and B from Table 6-1 on page 6-2, the display looks like this:



RV2W855-1

On display stations in configuration C from Table 6-1 on page 6-2, the display looks like this:

File	Edit	View	Options	Help
:	1. Undo	F4	:	:
:	2. Mark	F6	:	:
:	3. Copy	:	:	:
:	:	:	:	:

RV2W067-0

On display stations in configurations D and E from Table 6-2 on page 6-3, the display looks like this:

File	Edit	View	Options	Help
:	1. Undo	F4	:	:
:	2. Mark	F6	:	:
:	3. Copy	:	:	:
:	:	:	:	:

RV2W068-1

On display stations in configuration F in Table 6-2 on page 6-3, the display looks like this:

File	Edit	View	Options	Help
:	1. Undo	F4	:	:
:	2. Mark	F6	:	:
:	3. Copy	:	:	:
:	:	:	:	:

Chapter 7. Overriding Display Files and Display File Attributes

You can use overrides to temporarily change a file name, a device name associated with the file, or some of the other attributes of a file. Overrides allow you to make minor changes to the way a program functions or to select the data on which it operates without having to recompile the program.

Determining Whether or Not to Use Overrides

The following properties of overrides will help you decide if overrides are appropriate for the task you want to perform:

- Overrides remain in effect only for the job, program, or display station session in which they are issued. They do not permanently change the attributes of a file.
- Overrides have no effect on other jobs that may be running at the same time.
- Overrides that are to be applied must be specified either before the file is opened by a program or before a program that opens the file is compiled.
- Override commands may be entered interactively from a display station or as part of a batch job.
- Override commands may be included in a control language (CL) program, or they may be issued from other programs via a call to the program QCMDEXC.
- Overrides allow you to make minor changes to the way a program functions or for selecting the data on which it operates, without having to recompile the program.

Overriding File Attributes in HLL Programs

File attributes are built as a result of the following:

Create file commands	These commands build file attributes when the file is first created.
Program using the files	At compile time, the user program can specify some of the file attributes. (The attributes that can be specified depend on the high-level language in which the program is written.)
Override commands	At program run time, these commands can override the file attributes previously built by the merging of the file description and the file parameters specified in the user program.

The simplest form of overriding a file in a high-level language (HLL) program is to override some attributes of the file using the Override with Display File (OVRDSPF) command.

Example: You create a display file named DISPLAY33 using the Create Display File command:

```
CRTDSPF FILE(QGPL/DISPLAY33) SRCFILE(DDSFIL1) +
      DEV(STATION1) IGCDTA(*YES) WAITFILE(30) LVLCHK(*NO)
```

Your application program specifies display file DISPLAY33 with STATION50 for the display station and *NO for the IGCDTA parameter, which determines double-byte character processing.


Before you run the application program, you want to change the display station to STATION23 and wait file time to 45 seconds. The override command looks like this:

```
OVRDSPF FILE(DISPLAY33) DEV(STATION23) WAITFILE(45)
```

When the application program opens the file, the file overrides, program-specified attributes, and file attributes are merged to form the open data path (ODP), which is used during the running of the program to manage access to the file and to manage its attributes. File overrides have precedence over program-specified attributes. Program-specified attributes have precedence over file-specified attributes. In this example, when the file is opened, the following is used:

- Display station STATION23
- A double-byte character processing value of *NO
- A wait file time of 45 seconds
- The level identifiers of the records formats are not checked when the file is opened.

The following illustration explains the previous example:



RV2W016-3

Overriding File Names in HLL Programs


Another simple form of overriding a file in a high-level language program is to change the file that is used by the program. This may be useful for files that have been moved or renamed after the program has been compiled. Use the OVRDSPF command for file name overrides also.

Example: You want the output from your application program to be displayed using the display file DISPLAY12 instead of the display file DISPLAY33 (DISPLAY33 is specified in the application program). Before you run the program, enter the following:

```
OVRDSPF FILE(DISPLAY33) TOFILE(DISPLAY12)
```

The file DISPLAY12 must have been created by a CRTDSPF command before it can be used.

The following illustration explains the previous example:



You may want to override a file with a file that has a different file type; for example, you may want to override a display file with a diskette file using the Override Diskette File (OVRDKTF) command. To determine if your file can be overridden with a file that has a different file type, see the information under “Using File Redirection to Override File Names and Libraries or File Types” on page 7-6. More information about overriding with different file types is available in the *Data Management Guide*.

Overriding Both File Names and Attributes in HLL Programs

This form of overriding a file in a high-level language program is simply a combination of overriding file attributes and overriding file names or types. With this form of override, you can override the file that is to be used in a program and you can also override the attributes of the overriding file. Use the OVRDSPF command to override both the display file name and attributes.

Example: You want the output from your application program to be displayed using the display file REPORTS instead of the display file OUTPUT. (OUTPUT is specified in the application program.) In addition to having the application program use the display file REPORTS, you wish to override the wait file time to 50 seconds.

Assume the file REPORTS was created with the following command:

```
CRTDSPF FILE(REPORTS) SRCFILE(DDSFIL1) SRCMBR(MEMBER1) WAITFILE(25)
```

Before you run the program, type the following command:

```
OVRDSPF FILE(OUTPUT) TOFILE(REPORTS) WAITFILE(50)
```

Then call the application program. The display file REPORTS is used with a wait file time of 50 seconds.

Note that the single override command used in the previous example is *not* equal to the following two override commands:

```
Override 1  OVRDSPF  FILE(OUTPUT)  TOFILE(REPORTS)
Override 2  OVRDSPF  FILE(REPORTS)  WAITFILE(50)
```

Only one override is applied for each call level for an open operation of a particular file. If you want to override the file that is used by the program and also override the attributes of the overriding file from one call level, you must use a single command. If two overrides are used, override 1 causes the output to be displayed using the display file REPORTS, but override 2 is ignored.

Applying Overrides When Compiling a Program

Overrides may be applied at the time a program is being compiled for either of two purposes:

- To select the display file
- To provide external data definitions for the compiler to use in defining the record formats to be used on I/O operations

Overrides to the source file are handled just like any other override. They may select another file, another member of a database file, or change other file attributes.

Overrides may also be applied to files that are used within the program being compiled, if they are being used as externally described files in the program. These files are not opened at compile time, and thus the overrides are not applied in the normal manner. These overrides are used at compile time only to determine the file name and library that will be used to define the record formats and fields for the program to use I/O operations. Any other file attributes specified on the override are ignored at compile time. It is necessary that these file overrides be active at compile time only if the file name specified in the source for the program is not the file name that contains the record formats that the application needs.

The file name that is opened when the compiled program is run is determined by the file name that the program source refers to, changed by whatever overrides are in effect at the time the program runs. The file name used at compile time is not kept. The record formats in the file that is actually opened must be compatible with

those used when the program was compiled. Obviously, the easiest way to assure record compatibility is to have the same overrides active at run time that were active at compile time. If your program uses externally described data and a different field level file is used at run time, it is usually necessary to specify LVLCHK(*NO) on the override. See "Using File Redirection to Override File Names and Libraries or File Types" on page 7-6 for details.

Example: Assume that the source for the program INVENTORY, which has a wait file time of 15 seconds, contains an open to the display file LISTOUT:

```
Override 1  OVRDBF FILE(RPGSRC) TOFILE(SRCPGMS) MAXRCDLEN(77)
Override 2  OVRDSPF FILE(OUTPUT) TOFILE(REPORTS)
            CALL PGM(A)

            Program A
Override 3   OVRDSPF FILE(LISTOUT) TOFILE(OUTPUT)
Override 4   OVRDBF FILE(RPGSRC) WAITFILE(30)
            CRTRPGPM PGM(INVENTORY) SRCFILE(RPGSRC)
            RETURN

Override 5   OVRDSPF FILE(LISTOUT) TOFILE(REPORTS) IGCDTA(*YES)
            CALL PGM(INVENTORY)
```

The program INVENTORY opens the display file REPORTS in place of display file LISTOUT and allows DBCS data.

The program INVENTORY is created (compiled) from database file SRCPGMS and allows a maximum record length of 77 characters. Override 4 (applied first) overrides an optional file attribute. Override 1 (applied last) causes the file RPGSRC to be overridden with the database file SRCPGMS and a maximum record length of 77 characters.

The program INVENTORY is created with the display formats from the file REPORTS. Override 3 (applied first) causes the file LISTOUT to be overridden with OUTPUT. Override 2 (applied last) overrides OUTPUT with REPORTS. Other attributes may be specified here, but it is not necessary because only the record formats are used at compile time.

At run time, override 3 is no longer active, because program A has ended. Therefore override 2 has no effect on LISTOUT. However, override 5, which is active at run time, replaces LISTOUT with REPORTS and allows DBCS data. Because the same file is used for both compilation and run-time, level checking may be left on.

Deleting Overrides

If you want to delete an override, you can use the Delete Override (DLTOVR) command.

If you use the DLTOVR command in an application that either calls or transfers control to other programs, the override may or may not be deleted. More information about deleting overrides in application programs is available in the *Data Management Guide*

Displaying Overrides

You can display all file overrides or file overrides for a specific file using the Display Override (DSPOVR) command.

If you use the DSPOVR command to display the overrides used by an application that either calls or transfers control to other programs, you can control which overrides are displayed. More information about displaying overrides used in application programs is available in the *Data Management Guide*

Using File Redirection to Override File Names and Libraries or File Types

File redirection refers to using overrides to change the file name and library or the type of the file to be processed. For example, you can substitute one display file for another or change from using an ICF file to using a display file. The system may or may not support file redirection. Refer to “Recognizing Commands That Ignore or Restrict Overrides” on page 7-9 for rules on how the system processes overrides.

Overriding Files with the Same File Types

When you replace the file that is used in a program with another file of the same type, the new file is processed in the same manner as the original file. If a field level file, or any other file containing externally described data is redirected, it usually is necessary to either specify LVLCHK(*NO) or recompile the program. With level checking turned off, it is still necessary that the record formats in the file be compatible with the records in the program. If the formats are not compatible, the results cannot be predicted.

Overriding Files with Different File Types

If you change to a different type of file, the device-dependent characteristics are ignored and records are read or written sequentially. Some device parameters must be specified in the new device file or the override. Defaults are taken for others. The effect of specific redirection combinations is described later in this section.

Any attributes specified on overrides of a different file type than the final file type are ignored. The parameters SPOOL, SHARE, and SECURE are exceptions to this rule. They will be accepted from any override applied to the file, regardless of device type.

Some redirection combinations present special problems due to the specific characteristics of the device. In particular:

- File redirection is not recommended for save files.
- Display files and ICF files that use multiple devices (MAXDEV or MAXPGMDEV > 1) can be redirected only to a display file or ICF file.
- Redirecting a display file to any other file type, or another file type to a display file, requires that the program be recompiled with the override active if there are any input-only or output-only fields. This is necessary because the display file omits these fields from the record buffer in which they are not used, but other file types do not.

Table 7-1 on page 7-7 summarizes valid file redirections:

<i>Table 7-1. File Redirections</i>						
To-File	From-File					
	Printer	ICF	Diskette	Display	Database	Tape
Printer	O*	O	O	O	O	O
ICF	O	I/O O I	O I	I/O O I	O I	O I
Diskette	O	O I	O I	O I	O I	O I
Display	O	I/O O I	O I	I/O O I	O I	O I
Database	O	O I	O I	O I	O I	O I
Tape	O	O I	O I	O I	O I	O I
Legend: I=input file O=output file I/O=input/output file *=redirection to a different type of printer						

To use this chart, identify the file type to be overridden in the FROM-FILE columns and the file type overriding in the TO-FILE column. The intersection specifies an I or O or both, meaning that the substitution is valid for these two file types when used as input files or as output files.

For instance, you can override a diskette output file with a tape output file, and a diskette input file with a tape input file. The chart refers to file type substitutions only. That is, you cannot change the program function by overriding an input file with an output file.

The following chart describes the specific defaults taken and what is ignored for each redirection combination involving display files:

<i>Table 7-2 (Page 1 of 2). File Redirection Combinations</i>		
From	To	Specific Defaults Taken and What Is Ignored
Printer	Display	Records are written to the display with each record overlaying the previous record. For program-described files, you can request each record using the Enter key. Printer control information is ignored.
ICF input	Display	Records are retrieved from the display one at a time. Type in the data for each record and press the Enter key when the record is complete.
ICF output	Display	Records are written to the display with each record overlaying the previous record.
ICF input/output	Display	Input records are retrieved from the display one at a time. Type in the data for each record and press the Enter key when the record is complete. Output records are written to the display with each record overlaying the previous input or output record. Input and output records are essentially independent of each other and may be combined in any manner.

Table 7-2 (Page 2 of 2). File Redirection Combinations

From	To	Specific Defaults Taken and What Is Ignored
Diskette input	Display	Records are retrieved from the display one at a time. Type in the data for each record and press the Enter key when the record is complete. A non-field-level display file must be specified. Diskette label information is ignored.
Diskette output	Display	Records are written to the display with each record overlaying the previous record. You can request each output record using the Enter key.
Display input	ICF	Records are retrieved from the ICF file one at a time.
	Diskette	Records are retrieved in sequential order. Diskette label information must be provided in the diskette file or on an override command.
	Database	Input records are retrieved.
	Tape	Records are retrieved in sequential order. Tape label information must be specified in the tape file or on an override command.
Display output	ICF	Records are written to the ICF file one at a time.
	Database	Records are written to the database in sequential order.
	Diskette	The amount of data written on diskette is dependent on the exchange type of the diskette. Diskette label information must be provided in the diskette file or on an override command.
	Tape	Records are written on tape in sequential order. Tape label information must be specified in the tape file or on an override command.
	Printer	Records are printed and folding or truncating is performed as specified in the printer file.
Display input/output	ICF	Input records are retrieved from the
Database input (sequentially processed)	Display	Records are retrieved from the display one at a time. Type in the data for each record and press the Enter key when the record is complete. A non-field-level display file must be specified.
Database output (sequentially processed)	Display	Records are written to the display with each record overlaying the previous record. You can request each output record using the Enter key.
Tape input	Display	Records are retrieved from the display one at a time. Type in the data for each record and press the Enter key when the record is complete. A non-field-level display file must be specified. Tape label information is ignored.
Tape output	Display	Records are written to the display with each record overlaying the previous record. You can request each output record using the Enter key.

Recognizing Commands That Ignore or Restrict Overrides

The following commonly used commands ignore overrides entirely:

ADDLFM	DSPJRN
ADDPFM	EDTOBJAUT
ALCOBJ	EDTDLOAUT
APYJRNCHG	ENDJRNPF
CHGOBJOWN	GRTOBJAUT
CHGPTR	INZPFM
CHGSBSD	MOV OBJ
CHGXXXF (all change file commands)	RGZPFM
CLRPFM	RMVJRNCHG
CLRSVAF	RMVM
CPYIGCTBL	RNMOBJ
CRTDKTF	RSTUSRPRF
CRTDUPOBJ	RVKOBJAUT
CRTAUTHLR	SAVCHGOBJ
CRTSBSD	SAVLIB
CRTTAPF	SAVOBJ
DLCOBJ	SAVPGMPRD
DLTF	SAVSAVFDTA
DLTAUTHLR	SAVSYS
DSPDBR	SBMDBJOB
DSPFD	SIGNOFF
DSPFFD	STRDBRDR
	STRJRNPF

Overrides are not applied to any system files that are opened as part of an end-of-routing step or end-of-job processing. For example, overrides cannot be specified for the job log file. In some cases, when you need to override something in a system file, you may be able to change it through a command other than an override command. For example, to change the output queue for a job log, the output queue could be changed before sign-off using the OUTQ parameter on the Change Job (CHGJOB) command to specify the name of the output queue for the job. If the printer file for the job log contains the value *JOB for the output queue, the output queue is the one specified for the job.

The SRCFILE and SRCMBR parameters on the following commands are affected by overrides: overrides for the SRCFILE

CRTCMD	CRTPF
CRTICFF	CRTPRTF
CRTDSPF	CRTSRCPF
CRTLFL	CRTTBL
	CRTXXXPGM

(All create program commands. These commands also use overrides to determine which file will be opened by a compiled program. See "Applying Overrides When Compiling a Program" on page 7-4 for more information.)

The OPNQRYF command is affected by the following override parameters: TOFILE, MBR, SEQONLY, LVLCHK, and INHWRT.

The following commands allow overrides, but do not allow changing the MBR to *ALL:

CPYFRMPCD	CPYTOPCD
-----------	----------

The following commands do not allow overrides to be applied to the display files they use. Overrides to the printer files they use should not change the file type or the file name. Various restrictions are placed on changes that may be made to printer files used by these commands, but the system cannot guarantee that all combinations of possible specifications will produce an acceptable report.

DMPOBJ and DMPYSOJB (In addition to the preceding limitations, these commands do not allow overrides to the file they dump.)

DSPXXXXXX (All display commands. The display commands that display information about a file do not allow overrides to that file.)

DSPIGCDCT
EDTIGCDCT

GO (Message file can be overridden.)

PRTXXXXXX (All print commands.)

QRYDTA

TRCXXX (All trace commands.)

WRKXXXXXX (All work-with commands.)

Chapter 8. Handling Messages and Errors for Display Files

This chapter covers the following:


- Creating and displaying your own messages
- Analyzing error messages sent from the system

Creating and Displaying Your Own Messages

You can create and display your own messages on the Application System/400. These messages may indicate that a processing error has occurred, that incorrect input has been entered, or simply that the keyboard is temporarily locked while the system processes a lengthy request.

You can specify the following message handling functions for display files:

- Display a message on the message line
- Display a message on the message line when a subfile control record is written
- Define a message line
- Display messages in a field on the display
- Display messages in a program message queue



You can also do the following:

- Display error messages on the message line using a system-supplied error subfile
- Have the system automatically handle jobs that are about to receive a permanent I/O error

Information about DDS keywords

This section uses DDS keywords to define and display messages. For more information about specific DDS keywords, see the *DDS Reference*.

Displaying a Message on the Message Line

You can specify that a message is to be displayed on the message line with the ERRMSG or ERRMSGID keyword. For a message defined as a constant, use the ERRMSG keyword; message help is not supported for these kinds of messages. For a message defined in a message file, use the ERRMSGID keyword. When you use these keywords, the keyboard locks and the user must press the Reset key to clear the message from the display and continue.

When you use ERRMSG, the record that you want to present the message for must already be on the display. If it is not, the ERRMSG function is not performed.

When you use the ERRMSG keyword to present a message, that message is written to the message line of the display, which is usually the line at the bottom of the screen. The user would then press the Reset key to clear the message from the display and unlock the keyboard to continue typing. You provide the text of the message right on the ERRMSG keyword. When you write a record that has the ERRMSG keyword in effect, it causes that message to appear. Typically, you would use an option indicator to cause the ERRMSG keyword to take effect. When the application program turns on an option indicator, the keywords that have that option indicator specified in the DDS then take effect. In this case, an application program would leave an indicator that optioned an ERRMSG keyword off until the message needed to be displayed.

The ERRMSGID and SFLMSGID keywords have an optional parameter for message data (msg-data). This allows you to define a program-to-system field that contains the message data (substitution text). For more information on how the message data parameter works, refer to the Send Program Message CL command in the *CL Reference*.

Note: When you use the ERRMSG or ERRMSGID keyword, you should specify RSTDSP(*YES) on the CRTDSPF or CHGDSPF command; otherwise, data may be lost if the display file is suspended.

Displaying a Message on the Message Line When a Subfile Control Record is Written

You can specify that messages are to be displayed on the message line when a subfile control record is written using the SFLMSG or SFLMSGID keyword. If the message is a constant, use the SFLMSG keyword; if it is defined in a message file, use the SFLMSGID keyword. The restrictions on these keywords are the same as ERRMSG and ERRMSGID.

Displaying a Message on the Message Line Using a Message Field

You can specify a message field (M in position 38). The value from this output field will appear on the message line. The value in the field is specified by the application program in the output buffer. The length of this field should not exceed 78 positions if the message is to be displayed on a 24 by 80 screen, or 130 positions if the message is to be displayed on a 27 by 132 screen. Message help and substitution variables are not supported for a message line.

Priorities for Displaying Messages on a Message Line

The message displayed on the message line is determined by the following order of priority (1 is the highest):

1. ERRMSG
2. ERRMSGID
3. SFLMSG
4. SFLMSGID
5. Position 38 in DDS is M

In addition, you can change the line on which messages are displayed by using the MSGLOC keyword. If not specified otherwise, the message line is the last line on the display. If you use the MSGLOC keyword, the new message line applies to messages that are displayed for validity-checking errors and keys that are not valid as well as to user-defined messages.

Notes:

1. If the MSGLOC keyword is not specified, and a display station capable of displaying 27 lines is attached to a local display station controller or attached to a remote 5294 or 5394 controller, the default values are:
 - Line 28 for the 27 by 132 screen size
 - Line 25 for the 24 by 80 screen size
2. If line 25 is specified for the 24 by 80 mode, either because the default was used or line 25 was specified in the MSGLOC keyword, the message actually appears on line 24 unless the display is capable of displaying the message on line 25.
3. The normal system display for message help gives the user access to extended help (by pressing the Help key again), and may allow the user to use F10 to display all messages in the job log. The message help display used for a display station other than the job requester display station or for a display station associated with a multi-display file does not provide these functions.

Displaying Messages in a Field on the Display

You can specify that messages are to be displayed in a field on the display using the MSGID keyword. The message is truncated if it is longer than the MSGID field. The message is padded with blanks if it is shorter than the MSGID field.

When the MSGID keyword is used, the keyboard is not locked because the field on which it is specified is a normal output-capable field. Message help and substitution variables are not supported for the MSGID keyword.

Displaying Messages on a Program Message Queue

You can specify that messages that are contained on a program message queue are to be displayed by using the SFLMSGRCDD, SFLMSGKEY, and SFLPGMQ keywords. When you use subfile support for messages, you can display more than one message at a time and the keyboard does not lock while the message is being displayed. Because the messages specified here are from the program message queue, both message help and substitution text are supported. See “Displaying Error Messages from Subfiles” on page 4-19 for more information. See also the *CL Programmer's Guide* for information on message queues and sending messages.

Displaying Error Messages through a Subfile

The ERRSFL (error subfile) keyword can be used to indicate that the error messages associated with ERRMSG, ERRMSGID, SFLMSG, and SFLMSGID keywords will be displayed on the message line using a system-supplied error subfile.

The ERRSFL keyword can be used in addition to the ERRMSG and ERRMSGID or SFLMSG and SFLMSGID keywords to allow a user to roll through a subfile of error messages. One error message is displayed at a time. The user's program handles the validity checking of the fields, setting on the option indicators for the appropriate message to be sent for the fields in error. The system handles putting the message associated with the field in error in the error subfile, and displaying the error messages.

The ERRSFL keyword can also be used to put error messages into an error subfile when the system handles validity checking. Error messages are put into the error subfile when input fails the validity check for the following reasons:

- DDS keywords CHECK(M10 M11 VN VNE), COMP, RANGE, and VALUES
- Floating point operations
- More than one decimal point is entered in a field that has one or more decimal positions
- Either too many or too few decimal positions are entered in a field that has one or more decimal positions

The messages can be viewed by paging through the error subfile. Only one error message is displayed at a time. When the error subfile is displayed, the keyboard is not locked. It is not necessary to press the Reset key prior to correcting the fields in error.

If there is a record format currently displayed that covers the line defined to be the message line, the ERRSFL keyword is ignored.

When both validity checking and ERRMSG/ERRMSGID or SFLMSG/SFLMSGID are used on the screen at the same time, the resulting errors are not all present in the error subfile at the same time. When the write operation is done, the messages from ERRMSG, ERRMSGID, SFLMSG, and SFLMSGID are present in the error subfile. After data is typed and validity checking errors occur, the error subfile is cleared and only the validity checking errors are present.

Following is an example of how the ERRSFL keyword can be used:

```

|...+...1...+...2...+...3...+...4...+...5...+...6...+...7...
A                                     MSGLOC(24)
A                                     ERRSFL
A          R RCD1
A          FIELD1          5A  B  2  3
A 10                                     ERRMSGID(MSG0001 MSGF1 10 &MDTA1)
A 11                                     ERRMSG('Error Msg 1' 11)
A          FIELD2          10A B  3  3
A 20                                     ERRMSG('Error Msg 2' 20)
A 21                                     ERRMSGID(MSG0002 MSGF1 21)
A 22                                     ERRMSGID(MSG0003 MSGF1 22 &MDTA3)
A          FIELD3          2A  B  4  3
A 30                                     ERRMSGID(MSG0004 MSGF1 30)
A          MDTA1          78A  P
A          MDTA3          78A  P
A
A
A
A
A
A

```

Figure 8-1. Sample DDS Source for ERRSFL Keyword

In this example, assume that RCD1 is currently on the display. When validating the input data, your program detects several errors and sets on the option indicators 11, 21, and 30. On the subsequent output operation:

- FIELD1, FIELD2, and FIELD3 are displayed in reverse image.
- The cursor is located in position 2, 3 (start of FIELD1).
- The keyboard is not locked.
- An error subfile is displayed on line 24. The subfile contains three records: Error Msg 1, the MSG2 message, and the MSG4 message. The user can page through the messages, and by placing the cursor on the message line and pressing the Help key, view the message help for MSG2 or MSG4. Message CPF9897, which indicates that no help information is available, is displayed if the cursor is not located on the message line when the user is attempting to view the message help of MSG2 or MSG4.
- If the Help key is pressed on the message line for Error Msg 1, the message help for message CPF9897 appears. The message help explains that no message help is available.
- On the subsequent display of RCD1, the error subfile is cleared of the previous error messages.

The following is a DDS example of defining the SFLMSGID keyword in a display file:

```

|...+. ...1....+. ...2....+. ...3....+. ...4....+. ...5....+. ...6....+. ...7...
A                                     MSGLOC(24)
A                                     ERRSFL
A          R SFLRCD1                  SFL
A          SFL1                      5A B 2 3
A          R CTLRCD1                  SFLCTL(SFLRCD1)
A                                     SFLPAG(1)
A                                     SFLSIZ(15)
A                                     SFLDSP SFLDSPCTL
A 10                                     SFLMSGID(SFL0001 USERMSGF 10)
A 11                                     SFLMSG('Error Msg 1' 11)
A          R SFLRCD2                  SFL
A          SFL2                      7A 0 4 3DFT('FIELD 2')
A          R CTLRCD2                  SFLCTL(SFLRCD2)
A                                     SFLPAG(1)
A                                     SFLSIZ(15)
A                                     SFLDSP SFLDSPCTL
A 20                                     SFLMSG('Error Msg 2' 20)
A 21                                     SFLMSGID(SFL0002 USERMSGF 21)
A
A

```

Figure 8-2. Sample DDS Source for SFLMSGID Keyword

Assume that CTLRCD1 and CTLRCD2 are on the display. When validating the input data, your program detects several errors and sets on the option indicators 11 and 21. On the subsequent output operation:

- The cursor is located in position 2, 3 (start of SFLRCD1).
- The keyboard is not locked.
- An error subfile is displayed on line 24. The subfile contains two records: Error Msg 1 and the message of SFL0002. The user can page through the messages, and by placing the cursor on the message line and pressing the Help key, view the message help for SFL0002. If the Help key is pressed on the message line for Error Msg 1, the message help for message CPF9897 appears, which explains that no help information is available.
- On the subsequent display of CTLRCD1 and CTLRCD2, the error subfile is cleared of the previous error messages.

The SFLEND keyword is specified on the ERRSFL subfile control record. An error is issued and the keyboard is locked if the user attempts to roll beyond the top or bottom of the file.

The following considerations apply to the ERRSFL keyword, except when used with the ERRMSG and ERRMSGID keywords and the SFLMSG and SFLMSGID keywords:

- When the error subfile is displayed (that is, there are one or more fields in error), pressing a Roll key results in the error subfile being rolled, regardless of the cursor position at the time or whether other subfiles are currently displayed.
- When processing errors from validity check, the error subfile is built every time a valid command key, Roll key, or Enter key is pressed and errors occur.

- When a valid command key or Enter key is pressed, the message for the first field in error is always displayed.
- If the error subfile is rolled and the field that corresponds to the message that was displayed when the Roll key was pressed is valid, the error subfile is displayed with the message of the first field in error.
- If the error subfile is rolled and the field that corresponds to the message that was displayed when the Roll key was pressed is not valid, the error subfile is rolled to the next field in error.
- When rolling through the error subfile, the cursor is positioned in the field corresponding to the error message being displayed.
- If no fields are in error and a Roll key is pressed, a roll is attempted on the subfile and a roll error message is displayed (assuming no other area that can be rolled is encountered first). See Chapter 4, “Displaying Groups of Records Using Subfiles” on page 4-1 for more information about rolling subfiles.
- If the program writes a record and the user presses a Roll key after typing data that is not valid, the error subfile is built and the error message for the first field in error is displayed.

Sounding an Alarm for Messages

To sound an audible alarm when an active ERRMSG, ERRMSGID, SFLMSG, or SFLMSGID keyword is detected or when a validity check message is displayed, specify the MSGALARM keyword. This keyword is allowed at the file or record level. The alarm sounds for only a short time.

The MSGALARM keyword can be used on any record in a display file, including subfile control records. The MSGALARM keyword can also be used with the ERRSFL keyword.

Note: If the MSGALARM and ALARM keywords are specified and active on the same record format, the alarm sounds only once.

If the SFLMSG or SFLMSGID keyword is active and both the MSGALARM and ALARM keywords are specified, an alarm is sounded. If no message is displayed, the ALARM keyword and not the MSGALARM keyword is responsible for sounding the alarm.

Automatically Handling Permanent I/O Errors on Display Stations

Permanent I/O errors on display stations can be handled automatically when you use the device-recovery-action job attribute. The Device Recovery Action (DEVRCYACN) parameter of the Change Job (CHGJOB) command indicates a system action for jobs that are about to receive a permanent I/O error (such as a display station being powered off). You can use the following parameter values:

*DSCMSG	When the I/O error occurs, the system runs a Disconnect Job (DSCJOB) command to suspend the job. The user remains disconnected until signing on again to the same display. The job is resumed at the point just after the I/O operation. Display data management sets the major/minor return code to 83E1 and sends a CPF509F message to the program message queue. These indicate that the display has been cleared and is again available for use.
----------------	--

- *DSCENDRQS This option also runs the DSCJOB command when an I/O error occurs, but when the job is resumed, the system runs the End Request (ENDRQS) command to give control to the most recent request-processing program.
- *ENDJOB When an I/O error occurs, the job ends automatically and its priorities are lowered to conserve system resources.
- *ENDJOBNO LIST Again, the job ends automatically and its priorities are lowered to conserve system resources. However, no job log is produced for the job.

When an I/O error occurs (especially in the case of a communications line failing for several active jobs at once), using the device-recovery-action job attribute can save system resources. Also, the device-recovery-action job attribute makes the job of coding for I/O errors easier. Once the display station is recovered, the user application can continue at the point the error occurred by using the *DSCMSG and *DSCENDRQS values. For *DSCMSG, if the major/minor return code is 83E1 after an I/O operation, the program needs to assume that the display is blank. The program must branch back to the point at which the first I/O operation to the display is done. For *DSCENDRQS, the request-processing program receives control when connecting to the job again. This is similar to selecting option 2 on the System Request menu. No error recovery is performed for *MSG or *DSCMSG until an I/O operation is performed to the device in error. For all other values, the recovery occurs immediately when the error occurs.

The device-recovery-action job attribute works only for *REQUESTER display stations and does not apply to batch jobs, pass-through jobs, or work-station-function jobs.

Analyzing Error Messages Sent from the System

This section describes error conditions that an application program may encounter during its operation and the provisions that can be made within the program itself to attempt to deal with these conditions. The *CL Programmer's Guide* discusses how to use the debug functions to resolve unexpected errors encountered in the application programs. The chapter on handling problems in the *Operator's Guide* describes the programs that are available for analyzing and reporting system errors and hardware failures.

Errors can be detected when a file is opened, when a program device is acquired or released, during I/O operations to a file, and when the file is closed. When appropriate, the system will automatically try to run a failing operation again, up to a retry limit. When a retry is successful, neither operator nor program action is required. Errors that can affect the processing of the program may be reported in any or all of the following ways:

- A notify, status, diagnostic, or escape message may be sent to the program message queue of the program using the file. These messages may also appear in the job log, depending on the message logging level set for the job.
- A notify, status, diagnostic, or escape message may be sent to the operator message queue (QSYSOPR) or the history message queue (QHST).
- A file status code may be returned by the high-level language.
- A major/minor return code is returned in the I/O feedback area for display files.

- Information regarding the error may be saved in the system error log for use by the problem analysis and resolution programs.
- An alert message may be sent to an operator at another system in the network.
- The normal program flow may be interrupted and control may be transferred to an error-handling subroutine, or other language operations may occur. For additional information about how to handle run-time errors, see the appropriate high-level language manual.

Only some of these are significant to a program that is attempting error recovery.

Not all file errors allow programmed error recovery. Some errors are considered permanent; that is, the file, device, or program cannot work until some corrective action is taken. This might involve resetting the device by varying it off and on again, or correcting an error in the device configuration or the application program. Some messages and return codes are used to inform the user or the application program of conditions that are information rather than errors, such as change in the status of a communications line, or system action taken for an unexpected condition. In many cases, it is possible for the application program to test for an error condition and take some preplanned recovery action which allows the program to continue without intervention from the user.

Understanding Messages and Message Monitors

Displayed messages are the primary source of information for anyone who is testing a new application. A message usually contains more specific information than the file status code, the indicators, or the major/minor return code. The control language allows messages to be monitored so that the CL program can intercept a message and take corrective action. See the *CL Programmer's Guide* for more information about message types and message monitors. In most high-level languages, either the file status code or major/minor return code (described in the following section) is a more convenient source of information.

Message numbers are assigned in categories to make it easier for a program to monitor for any of a group of related messages. The following message number ranges are assigned for file error messages:

Table 8-1. System Message Number Ranges

Message IDs	Operation	Message Type
CPF4001–40FF	Open	Diagnostic and status.
CPF4101–43FF	Open	Escapes that make the file unusable.
CPF4401–44FF	Close	Diagnostic and status.
CPF4501–46FF	Close	Escapes that make the file unusable.
CPF4701–48FF	I/O, Acquire, and Release	Notify with a default reply of cancel, status and escapes that do not make the file or device unusable.
CPF4901–49FF	I/O, Acquire, and Release	Notify with a default reply of ignore.
CPF5001–50FF	I/O, Acquire, and Release	Notify with a default reply of cancel.
CPF5101–53FF	I/O, Acquire, and Release	Escapes that make the file or device unusable.
CPF5501–56FF	I/O, Acquire, and Release	Escapes that make the file or device unusable.

Some status messages, CPF4018 for example, are preceded by a diagnostic message that provides additional information. Diagnostic messages may be kept in the job log, depending on the message logging level of the job. If a CL program monitors for CPF4018, CPF5041, or similar messages, it can retrieve the accompanying diagnostic message from the program message queue.

If an error occurs for which an escape message is issued and the message is not monitored, your program will be ended and the message displayed in the operator message queue. Status messages may also be monitored, but if they are not monitored, the program continues. Most high-level languages except CL monitor for all the file errors that are likely to be encountered, and provide some standard recovery. Depending on the severity of the error, the high-level language may simply end the program and issue a message of its own. Alternatively, you may code an error recovery routine to handle errors that are anticipated in that particular application.

Within these error-handling routines, it is usually necessary to examine the file status or major/minor return codes to determine the cause of the error. The manuals for the language you are using explain how to access file status and major/minor return codes. The language manuals also explain the file status codes as they are defined for each language.

Understanding Major/Minor Return Codes

Major/minor return codes are used to report errors and certain status information for display files. They are usually stated as four characters: the first two referring to the major code and the second two referring to the minor code. The major code indicates the general type of error, and the minor provides further detail. Minor codes, except zero, have the same or a similar meaning, regardless of the major code with which they are combined.

The application program can test the return code after each I/O operation. If the major return code is 00, the operation completed successfully and the minor return code contains status information that indicates whether a read or a write operation should be performed next. A major return code of 04 or above indicates that an error occurred. The program may test for any specific errors for which programmed

recovery is attempted. The application program may test for a specific condition by comparing the major and minor codes as a unit, or may identify a class of conditions by testing the major code alone.

Most major/minor return codes are accompanied by any one of several message numbers, for which the typical recovery action is similar. File status codes are defined by the individual languages and may be set based on the major/minor return codes.

The following table defines the major return codes. Appendix E, "Display File Return Codes" contains specific definitions of the major and minor return codes as they are used for display files and the message numbers associated with each.

Table 8-2. Major Return Code Definitions

Code	Definition
00	The operation requested by your program completed successfully. The minor includes state information, such as change direction.
02	Input operation completed successfully, but job is being ended (controlled). The minor includes state information.
03	Successful input operation, but no data was received. The minor includes state information.
04	Error occurred because an output operation was attempted while data was waiting to be read.
08	An acquire operation failed because the device has already been acquired or the session has already been established.
11	A read-from-invited-program-devices operation failed because no device or session was invited.
34	An input exception occurred. The data length or record format was not acceptable for the program.
80	A permanent system or file error, which cannot be recovered from, occurred. Programmer action is required to correct the problem.
81	A permanent device or session error, which cannot be recovered from, occurred during an I/O operation.
82	A device or session error occurred during an open or acquire operation. Recovery may be possible.
83	A device or session error occurred during an I/O operation. Recovery may be possible.

Recovering from Errors

The following sections describe the error recovery action that is appropriate for each group of major return codes.

Normal Completion

A major/minor return code of 0000 indicates that the operation requested by your program was completed successfully. Most of the time, no message is issued. In some cases, a diagnostic message might be used to inform the user of some unusual condition that the system was able to handle, but which might be considered an error under some conditions. For example, a parameter that is not valid might be ignored, or some default action taken.

Completion with Exceptions

Several rather specific major return codes have been assigned to conditions for which a specific response from the application program is appropriate.

A major return code of 02 indicates that the requested input operation completed successfully, but the job is being ended (controlled). The application program should complete its processing as quickly as possible. The controlled cancel is intended to allow programs time to end in an orderly manner. If your program does not end within the time specified on the ENDJOB command, the job will be ended by the system without further notice.

A major return code of 03 indicates that an input operation completed successfully without transferring any data. For some applications, this might be an error condition, or it might be expected when the user presses a function key instead of entering data. It might also indicate that all the data has been processed, and the application program should proceed with its completion processing. In any case, the contents of the input buffer in the program should be ignored.

A major/minor code of 0309 is used to indicate that no data was received *and* the job is being ended (controlled). A major/minor code of 0310 indicates that there is no data because the specified wait time has ended. Other minor return codes accompanying the 02 or 03 major code are the same as for a 00 major code, indicating communications status and the operation to be performed next.

A major return code of 04 indicates that an output exception occurred. Specifically, your program attempted to send data when there was data waiting to be received. This is probably the result of not handling the minor return code properly on the previous successful completion. Your program can recover by simply receiving the incoming data and then repeating the write operation.

A major return code of 34 indicates that an input exception occurred. The received data was either too long or incompatible with the record format. The minor return code indicates what was wrong with the received data, and whether the data was truncated or rejected. Your program can probably handle the exception and continue. If the data was rejected, you may be able to read it by specifying a different record format.

Two other return codes in this group, 0800 and 1100, are both usually the result of application programming errors, but are still recoverable. 0800 indicates that an acquire operation failed because the device has already been acquired or the session has already been established. 1100 indicates that the program attempted to read from invited devices with no devices invited. In both cases, the request that is not valid is ignored, and the program may continue.

No message is issued with a 02 major code or most minor codes with the 03 major code, but the other exceptions in this group are usually accompanied by a message in the CPF4701–CPF47FF or CPF5001–CPF50FF range.

Permanent System or File Error

A major return code of 80 indicates a serious error affecting the file. The application program must close the file and reopen it before attempting to use it again, but recovery is unlikely until the problem causing the error is found and corrected. To reset an error condition in a shared file by closing it and opening it again, all programs sharing the open data path must close the file. This may require returning to previous programs in the program stack and closing the shared file in each of those programs. You should refer to the text of the accompanying message to determine what action is appropriate for the particular error.

Within this group, several minor return codes are of particular interest. A major/minor code of 8081 indicates a serious system error for which an APAR probably will be required. The message sent with the major/minor return code may direct you to run the Analyze Problem (ANZPRB) command to obtain more information.

A major/minor code of 80EB indicates that incompatible options or options that are not valid were specified in the display file or as parameters on the open operation. In most cases you can close the file, end the program, correct the parameter that is not valid with an override command, and run the program again. The override command affects only the job in which it is issued. It allows you to test the change easily, but you may eventually want to change or re-create the display file as appropriate to make the change permanent.

Permanent Device or Session Error on I/O Operation

A major return code of 81 indicates a serious error affecting the device or session. This includes hardware failures affecting the device, communications line, or communications controller. It also includes errors due to a device being disconnected or powered off unexpectedly and abnormal conditions that were discovered by the device and reported back to the system. Both the minor return code and the accompanying message provide more specific information regarding the cause of the problem.

Depending on the file type, the program must either close the file and open it again, release the device and acquire it again, or acquire the session again. To reset an error condition in a shared file by closing it and opening it again, all programs sharing the open data path must close the file. In some cases, the message may instruct you to reset the device by varying it off and on again. It is unlikely that the program will be able to use the failing device until the problem causing the error is found and corrected, but recovery within the program may be possible if an alternate device is available.

Some of the minor return codes in this group are the same as those for the 82 major return code. Device or line failures may occur at any time, but an 81 major code occurs on an I/O operation. This means that your program had already established a link with the device or session. Therefore, some data may have been transferred, but when the program is started again, it starts from the beginning. A possible duplication of data could result.

Message numbers accompanying an 81 major code may be in the range indicating either an I/O or a close operation. A device failure on a close operation simply may be the result of a failure in sending the final block of data, rather than action specific to closing the file. An error on a close operation may result in the file being left partially closed. Your error recovery program should respond to close failures with

a second close operation. The second close will always complete, regardless of errors.

Device or Session Error on Open or Acquire Operation

A major return code of 82 indicates that a device or session error occurred during an open or acquire operation. Both the minor return code and the accompanying message will provide more specific information regarding the cause of the problem.

Some of the minor return codes in this group are the same as those for the 81 major return code. Device or line failures may occur at any time, but an 82 major code indicates that the device or session was unusable when your program first attempted to use it. Thus no data was transferred. The problem may be the result of a configuration or installation error.

Depending on the minor return code, it may be appropriate for your program to recover from the error and try the failing operation again after some waiting period. The number of times you try should be specified in your program. It may also be possible to use an alternate or backup device or session instead.

Message numbers accompanying an 82 major code may be in the range indicating either an open or an acquire operation. If the operation was an open, it is necessary to close the partially opened file and reopen it to recover from the error. If the operation was an acquire, it may be necessary to do a release operation before trying the acquire again. In either case, the file wait time should be specified long enough to allow the system to recover from the error.

Recoverable Device or Session Errors on I/O Operation

A major return code of 83 indicates that an error occurred in sending data to a device or receiving data from the device. Recovery by the application program is possible. Both the minor return code and the accompanying message provide more specific information regarding the cause of the problem.

Most of the errors in this group are the result of sending commands or data that are not valid to the device, or sending valid data at the wrong time or to a device that is not able to handle it. The application program may recover by skipping the failing operation or data item and going on to the next one, or by substituting an appropriate default. There may be a logic error in the application.

Chapter 9. Creating and Accessing Menus Using Display Files

This chapter describes user-defined menus and tells you how to create them and use them with system menus.

The first two types of user-defined menus can be created using the information in this chapter:

- | | |
|---------------------------|---|
| Display file menus | Menus that use a display defined by data description specifications (DDS) to present a menu format. The menu functions are controlled by a message file containing the commands used to run each of the menu options. |
| Program menus | Menus that use a high-level language program to present the menu format and provide the functions necessary to run the menu options. |
| UIM menus | Menus that a menu object defined by the user interface manager (UIM) panel group definition language. For more information on defining your own menus using the UIM, see "Defining a Menu Object Using UIM" on page 16-6. |

Information about CL commands

Some of the examples in this chapter use CL commands. For more information about specific CL commands, see the *CL Reference*.

Running System and User-Defined Menus

Menus that consist of *MENU object types are run using the Go to Menu (GO) command. The GO command allows you to specify either a particular menu or a generic menu name. If you specify a generic name, you are shown the Work with Menus display, which shows all the menus available for your use. From this list, you can choose a menu to run.

Returning to a Menu after Running the GO command

Using the Return Point (RTNPNT) parameter of the GO command, you can specify whether or not you want to return to the menu from which the command was entered after running the menu specified by the GO command.

Determining the Previous Menu

A menu is placed on an internal menu stack before it is run. If a stack is not available for the menu, one is created. When the Cancel key is pressed for a menu, the previous menu in the stack is shown. Each menu stack is 10 elements (menus) deep. When the eleventh menu is placed on the menu stack, the first, or oldest, menu is removed from the stack. This menu cannot be returned to by using the Cancel key.

Using the Cancel and Exit Keys on Menus

In the following example, a series of menus is presented using both the menu options and the GO command.

1. From the AS/400 Main Menu, GO PROGRAM RTNPNT(*YES) is typed on the command line. Specifying RTNPNT(*YES) here means that the Main Menu will be used as a return point.

```
MAIN                                Main Menu                                System  XXXXXXXX
Select one of the following:

    1. User tasks
    2. Office tasks
    3. General system tasks
    4. Files, libraries, and folders
    5. Programming
    6. Communications
    7. Define or change the system
    8. Problem handling
    9. Display a menu

    90. Sign off

Selection or Command
===> GO PROGRAM RTNPNT(*YES)_____

F3=Exit  F4=Prompt  F9=Retrieve  F12=Cancel  F13=Information Assistant
F23=Set initial menu
```

2. Next, by typing GO PROBLEM RTNPNT(*NO) on the command line of the Programming menu and pressing the Enter key, the Problem Handling menu is shown. The Programming menu is *not* set as a return point.

```
PROGRAM                            Programming                            System  XXXXXXXX
Select one of the following:

    1. Programmer's menu
    2. Programming Development Manager
    3. Utilities
    4. Programming language debug
    5. SQL pre-compiler
    6. Question and answer
    7. IBM product information
    8. Copy screen image

    50. System/36 programming

    70. Related commands

Selection or Command
===> GO PROBLEM RTNPNT(*NO)_____

F3=Exit  F4=Prompt  F9=Retrieve  F12=Cancel  F13=Information Assistant
F16=System main menu
```


PROBLEM	Problem Handling	System	XXXXXXX
---------	------------------	--------	---------

Select one of the following:

1. Question and answer
2. Work with problems
3. Network problem handling
4. Display system operator messages
5. Display the history log
6. System service tools
60. More problem handling options
70. Related commands

Selection or Command
====>

F3=Exit F4=Prompt F9=Retrieve F12=Cancel F13=Information Assistant
F16=System main menu

3. In this example, if the Cancel key is pressed while viewing the Problem Handling menu, the user is returned to the Programming menu because the Programming menu is the preceding display on the menu stack. If F3 (Exit) is pressed while viewing the Problem Handling menu, the user is returned to the Main Menu, because the Main Menu is the most recent display from which a GO command was entered with RTNPNT(*YES).

Note that since the default value for the RTNPNT parameter is *YES, GO PROBLEM will have the same effect as GO PROBLEM RTNPNT(*YES).

Pressing either F3 (Exit) or F12 (Cancel) while viewing the help for a menu returns the user to the menu itself.

Choosing the Menu That Is Shown at Sign-On Time

To specify a menu as your **initial menu**, or the first menu you see when you sign on, press F23 when the menu is shown. F23 sets the initial menu attribute in your user profile. Unless your initial program requests some other menu, the menu selected by pressing F23 is shown as the initial menu the next time you sign on.

Note: You can only use this key if LMTCPB(*NO), which allows you to change the initial menu, is specified in your user profile.

See the *Security Reference* for information about initial menus and limited users.

Defining Your Own Display File Menus

Display file menus consist of three parts:

- A DDS-defined display file to define the way the menu looks at the display station
- A message file to define what action is taken when any of the menu options are selected
- A menu object (*MENU) that contains the menu

Help is available on display file menus for the following:

Commands	Command help is shown by typing the command on the command line, then pressing the Help key.
Function keys	Help for function keys is shown by moving the cursor to the function area and pressing the Help key.
Messages	Help for messages is shown by moving the cursor to a message and pressing the Help key.

Help for the menu options may also be provided using DDS. See “Naming Help Formats for Menus” on page 9-6 for more about help information.

Information about DDS keywords

More information about the specific DDS keywords used in this chapter is found in the *DDS Reference*.

Understanding DDS and Display File Considerations for Menus

Several restrictions exist for the DDS used in defining a menu:

Table 9-1 (Page 1 of 2). Restrictions for Display File Menus

Affected Area	Restriction
Display size	The menu format and the associated help record formats for the menu in the display file must have a display size of 24 rows by 80 columns, DSPSIZ(*DS3) in DDS.
Display file and record format names	The menu record format name must be the same as the display file name.
Help format names	Help format names must follow the convention #Hxxyy, described in “Naming Help Formats for Menus” on page 9-6. The help record format is limited to 150 items.
Indicator area	A separate indicator area (INDARA keyword) must be declared in the DDS for the display.
Subfile use	Subfiles cannot be used.

Table 9-1 (Page 2 of 2). Restrictions for Display File Menus

Affected Area	Restriction
Allowed lines	<p>Only the first 21 lines of the display should be described. Only the first 21 lines of the help display should be described. Lines 22 and 23 are used with long command lines; system messages are shown on line 24. (Line 23 is used with short command lines and line 24 is used for messages.)</p> <p>The following lines can be used when a function key legend is requested:</p> <ul style="list-style-type: none"> • For a long command line with no function key legend, lines 1 through 21 • For a long command line with a function key legend, lines 1 through 19 • For a short command line with no function key legend, lines 1 through 22 • For a short command line with a function key legend, lines 1 through 20 • For no command line with no function key legend, lines 1 through 21 • For no command line with a function key legend, lines 1 through 19
Keyboard locking	The LOCK record level keyword should be used to prevent the keyboard from unlocking before the display is shown.
Paging	The Allow Roll (ALWROL) record level keyword cannot be specified.
Deferring the write operation	DFRWRT(*NO) is <i>required</i> on the CRTDSPF command when creating a display file menu. DFRWRT(*NO) ensures the menu format is displayed when the menu is run.

The following suggestions can also be used to help you define your menu using DDS:

Table 9-2. Suggestions for Display File Menus

Affected Area	Option
Restoring the display	The RSTDSP(*NO) is optional on the CRTDSPF command, but may significantly improve system performance if specified.
Menu and display station alias	An alias can be used for the name of the menu and for the name of the display station (for the System/36 environment). When issuing the CRTMNU command, you can specify a different name than the name used in the DDS. This way, the name of the display station identifier will be displayed with the menu. By giving the menu a different name, you can use the GO command to find that menu.

Describing Menu Actions in a Message File

Message files are used to describe what action is taken when a menu option is selected. Commands controlling the action to be taken are usually placed in the message. In some cases, the command string may be too long to fit in the message. In these cases, the message contains the message identifier for the message; the command is then placed in the message help.

Messages used in display file menus must be named using the message prefix USR. The remaining four digits of the message identifier correspond to the menu option number.

For example, if option 3 on a given display file menu is:

3. Personnel Menu

then the message describing the action taken when 3 is entered on the command line uses identifier USR0003. The message could contain any command, such as 'GO PERSMENU RTNPNT(*NO)'.

See “Creating and Displaying Your Own Messages” on page 8-1 for more information about messages.

Naming Help Formats for Menus

Help formats for display file menus are named using the form:

#Hxxyy

where:

xx is the number of the first menu option to which the help information applies

yy is the number of the last menu option to which the help information applies

For example, #H0103 could be used to name help that applies to menu options 1 through 3. #H0202 names the help that applies to menu option 2.

#H0000 names the extended help for the menu.

The help formats may be described in any order in the DDS. The system sorts the help formats in ascending order when the menu is run.

If two or more help format names apply to the same option, only the first help format (as sorted by the system) will be shown when Help is requested for that option. For example, if the following help formats are given:

#H0000

#H0101

#H0205

#H0306

#H0707

Typing 3 on the command line (to select option 3) and pressing the Help key will show the help designated #H0205. In this example, #H0306 can be viewed using the Page Down key, but will be shown *directly* only by requesting help for option 6.

Similarly, by moving the cursor to the command line and pressing the Help key with no option typed on the command line, the user is shown extended help for the menu (#H0000). The cursor movement keys can be used to look through the other help formats for the menu options.

The following example shows a menu with five options. The names of the help formats and the menu options to which they apply are shown following the example.

PERSMENU
Personnel Menu

Select one of the following:

1. Departments menu
2. Education menu
3. Benefits menu
4. Job openings
5. Job applicants

Selection or Command
 ===> _____

Help Name	Contents
#H0000	General help for the Personnel Menu (PERSMENU)
#H0101	Help for option 1, Departments menu
#H0202	Help for option 2, Education menu
#H0303	Help for option 3, Benefits menu
#H0405	Help for options 4 and 5, Job openings and Job applicants

The help information for the menu options can be shown by typing the option number on the command line and pressing the Help key, or by pressing Help (extended help for the menu), and then using the Page Down key to page through the help for the options.

Building a Display File Menu

The following steps allow you to create a display file (*DSPF) menu:

1. Describing the menu and menu help information
2. Creating the display file
3. Creating the message file
4. Adding messages to the message file
5. Creating the menu
6. Running the menu

The following sections explain each step in detail.

Describing the Menu and Menu Help Information

DDS is used to describe both the appearance and the help for the menu.

The following DDS is for the sample display called PERSMENU. The first record format (PERSMENU) is used to describe the appearance of the menu when displayed. Five menu options are listed, starting in position 7 of lines 5 through 9.

Five more record formats are shown: #H0000, #H0101, #H0202, #H0303, and #H0405. Each of these is used to provide help information for the menu and its options. Following the system convention described above (see “Naming Help

Formats for Menus” on page 9-6), #H0000 is used to provide extended help for the menu. The other record formats provide help for the menu options.

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A* PERSONNEL MENU (PERSMENU) SPECIFICATION
A*
A                                PRINT DSPSIZ(*DS3)
A                                INDARA
A*
A      R PERSMENU                LOCK
A                                1 02'PERSMENU'
A                                1 29'PERSONNEL MENU'
A                                3 02'SELECT ONE OF THE FOLLOWING:'
A                                5 07'1. DEPARTMENTS MENU'
A                                6 07'2. EDUCATION MENU'
A                                7 07'3. BENEFITS MENU'
A                                8 07'4. JOB OPENINGS'
A                                9 07'5. JOB APPLICANTS'
A                                21 02'SELECTION OR COMMAND'
A*
A      R #H0000                  LOCK
A                                1 02'GENERAL'
A                                2 26'HELP FOR THE PERSONNEL MENU
A                                3 02'THIS IS THE GENERAL HELP'
A
A                                3 27'FOR THE PERSONNEL MENU.'
A*
A      R #H0101                  LOCK
A                                1 02'HELP1'
A                                1 26'HELP FOR OPTION 1'
A                                3 02'THIS IS THE HELP'
A                                3 19'FOR OPTION 1.'
A*
A      R #H0202                  LOCK
A                                1 02'HELP2'
A                                1 26'HELP FOR OPTION 2'
A                                3 02'THIS IS THE HELP'
A                                3 19'FOR OPTION 2.'
A*
A      R #H0303                  LOCK
A                                1 02'HELP3'
A                                1 26'HELP FOR OPTION 3'
A                                3 02'THIS IS THE HELP'
A                                3 19'FOR OPTION 3.'
A*
A      R #H0405                  LOCK
A                                1 02'HELP45'
A                                1 26'HELP FOR OPTIONS 4 AND 5'
A                                3 02'THIS IS THE HELP'
A                                3 19'FOR OPTIONS 4 AND 5.'
A*

```

Figure 9-1. DDS Source for Sample Menu Called PERSMENU

Creating the Display File

To create the display file for the menu, enter the following command:

```
CRTDSPF FILE(PERLIB/PERSMENU) +  
        SRCFILE(USERLIB/SFPERS) +  
        DFRWRT(*NO) +  
        RSTDSP(*NO)
```

The DDS source member, PERSMENU, in the source file SFPERS in library PERLIB, is used to create the display file for the PERSMENU menu.

Creating the Message File

Enter the following Create Message File (CRTMSGF) command to create a message file called PERSMENU (same name as record format):

```
CRTMSGF MSGF(PERLIB/PERSMENU) +  
        TEXT('Message file of commands for menu PERSMENU.')
```

The message file will be used to contain messages describing the actions taken when the various menu options are selected.

Adding Messages to the Message File

The Add Message Description (ADDMSGD) command is used to add messages to the message file. The messages describe the different actions taken when various menu options are selected.

The MSGID parameter of each ADDMSGD command is in the form USRxxxx, where xxxx is the menu option number. The MSG parameter contains the command to run the menu option.

In the following example, the MSG parameters of the first three messages contain commands to run menus (using the GO command); the last two messages contain commands which will call programs (using the CALL command) when either of those menu options are selected from the menu.

```
ADDMSGD MSGID(USR0001) MSGF(PERLIB/PERSMENU) +  
        MSG('GO DEPTMENU RTNPNT(*NO)')  
ADDMSGD MSGID(USR0002) MSGF(PERLIB/PERSMENU) +  
        MSG('GO EDUCMENU RTNPNT(*NO)')  
ADDMSGD MSGID(USR0003) MSGF(PERLIB/PERSMENU) +  
        MSG('GO BENEMENU RTNPNT(*NO)')  
ADDMSGD MSGID(USR0004) MSGF(PERLIB/PERSMENU) +  
        MSG('CALL JOBOPEN')  
ADDMSGD MSGID(USR0005) MSGF(PERLIB/PERSMENU) +  
        MSG('CALL JOBAPPS')
```

Creating the Menu Object

Enter the following Create Menu (CRTMNU) command to create the menu object:

```
CRTMNU MENU(PERLIB/PERSMENU) TYPE(*DSPF) DSPF(*MENU) +  
        MSGF(*MENU) DSPKEY(*NO) CMDLIN(*LONG) +  
        TEXT('Personnel menu')
```

The DSPKEY parameter specifies whether the function key legend is shown at the bottom of the menu when the menu is displayed. *NO specifies that the function key legend is not shown at the bottom of the menu. *YES specifies that the function key legend is shown at the bottom of the menu. You do not have the option to display only certain function keys.

The CMDLIN parameter specifies the length of the command line to be displayed. *LONG specifies a 153-byte long command line. *SHORT specifies a 73-byte long command line. *NONE specifies a 4-byte option line in place of a command line.

Note: Note that for both the DSPF and MSGF parameters, the value *MENU was specified. *MENU specifies that the name of the display or message file is the same as the name of the menu. Display and message file names *do not* have to have the same name as the menu.

Running the Menu

The new display file menu can now be run using the GO command:

GO PERSMENU

PERSMENU

Personnel Menu

Select one of the following:

1. Departments menu

2. Education menu

3. Benefits menu

4. Job openings

5. Job applicants

Selection or Command

===>

Defining Your Own Program Menus

Program menus provide an alternative to display file and system menus by using the GO command to call a program. The user has complete control of the display and function of the program menu through the program.

Passing Parameters for Program Menus

Three parameters are passed to the program when the menu is run:

- The 10-character name of the menu object
- The 10-character name of the library containing the menu object
- A 2-character binary return code

All three parameters must be declared as variables in the program. The return code determines how the program menu is exited, simulating the function keys found on IBM-supplied menus. The four possible values are:

Binary Return Code	Hex Equivalent	Description
0	0000	Call the program (display the menu) again

Binary Return Code	Hex Equivalent	Description
-1	FFFF	Exit function requested
-2	FFFE	Previous function requested
-4	FFFC	Home function requested (display the initial menu)

Note: The hexadecimal values shown above are used for those high-level languages (such as CL) that do not support binary numbers. CL programs should use a 2-byte character variable.

Building a Program Menu

This example shows how a program (*PGM) menu is created. The following steps will be shown and described in detail:

1. Describing the menu
2. Creating the display file
3. Entering source and creating a CL program to control the menu function
4. Creating the menu
5. Running the menu

Describing the Menu

The program menu is designed using data description specifications (DDS) to describe the menu's appearance. The following DDS is for the sample display called PGMMENU.

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
A                                     DSPSIZ(*DS3)
A                                     PRINT
A                                     CA03(01)
A                                     CA12(02)
A                                     HOME(03)
A                                     INDARA
A                                     BLINK OVERLAY
A      R MENUFMT
A      DSPMNUN      10A 0 1 2
A                                     1 72 TIME
A                                     1 31'EXAMPLE PROGRAM MENU'
A                                     DSPATR(HI)
A                                     2 2'SELECT ONE OF THE FOLLOWING:'
A                                     3 5'1.' DSPATR(HI)
A                                     3 10'DISPLAY LIBRARY LIST (DSPLIBL)'
A                                     4 5'2.' DSPATR(HI)
A                                     4 10'WORK WITH ACTIVE JOBS (WRKACTJOB)'
A                                     5 5'3.' DSPATR(HI)
A                                     5 10'WORK WITH YOUR JOB (WRKJOB)'
A                                     6 5'90.' DSPATR(HI)
A                                     6 10'RETURN'
A                                     23 2'OPTION:'
A      OPTION      3 I 23 12DSPATR(PC)

```

Figure 9-2. DDS Source for Program Menu Example

Creating the Display File

Create the display file using the Create Display File (CRTDSPF) command:

```
CRTDSPF FILE(QGPL/PGMDDS) SRCFILE(USERLIB/SOURCE1)
```

The DDS source file called SOURCE1 is used to create the display file for the PGMMENU menu.

Entering the Source and Creating a CL Program

The following CL program is used to control the menu function. (See the *CL Programmer's Guide* for more information about entering CL source.) Note that any high-level language supported by the system could be used to control a menu.

```
PGM      PARM(&MENUNAME &MENULIB &ACTION) /* Begin the program and +
        indicate that 3 parameters will be passed to it when +
        called. The parameters include 1) The menu name, 2) +
        The menu library name 3) The action desired by this +
        program on return. */
DCL      VAR(&MENUNAME) TYPE(*CHAR) LEN(10) /* Menu name */
DCL      VAR(&MENULIB) TYPE(*CHAR) LEN(10) /* Menu library name */
DCL      VAR(&ACTION) TYPE(*CHAR) LEN(2) /* Action variable */
DCLF     FILE(QGPL/PGMDDS) RCDFMT(MENUFMT) /* Display file */
CHGVAR   VAR(&DSPMNUN) VALUE(&MENUNAME) /* Set the menu name on the +
        menu */
SNDRCVF  DEV(*FILE) RCDFMT(MENUFMT) /* Display the menu at the +
        display station */
CHGVAR   VAR(&ACTION) VALUE(X'0000') /* Indicate the menu should +
        be displayed again */
/*****
/* Handle function keys */
*****/
IF      COND(&IN01 *EQ '1') THEN(CHGVAR VAR(&ACTION) +
        VALUE(X'FFFF')) /* If F3 was pressed, set action +
        to EXIT */
IF      COND(&IN02 *EQ '1') THEN(CHGVAR VAR(&ACTION) +
        VALUE(X'FFFE')) /* If F12 was pressed, set action +
        to PREVIOUS */
IF      COND(&IN03 *EQ '1') THEN(CHGVAR VAR(&ACTION) +
        VALUE(X'FFFC')) /* If HOME was pressed, set action +
        to HOME */
/*****
/* Handle menu options */
*****/
IF      COND(&OPTION *EQ '1') THEN(DSPLIBL) /* If the menu user +
        has selected option 1, then display the library list */
IF      COND(&OPTION *EQ '2') THEN(WRKACTJOB) /* If the menu user +
        has selected option 2, then display the active jobs */
IF      COND(&OPTION *EQ '3') THEN(WRKJOB) /* If the menu user +
        has selected option 3, then display the current job. */
IF      COND(&OPTION *EQ '90') THEN(CHGVAR VAR(&ACTION) +
        VALUE(X'FFFE')) /* If the menu user has selected option +
        90, then set the action to previous. */
ENDPGM   /* End the program */
```

Create the CL program using the Create CL Program (CRTCLPGM) command:

```
CRTCLPGM PGM(QGPL/PGMCL) SRCFILE(USERLIB/SOURCE1)
```

Creating the Menu

Create the program menu using the Create Menu (CRTMENU) command:

```
CRTMENU MENU(QGPL/PGMMENU) TYPE(*PGM) PGM(QGPL/PGMCL)
```

Running the Menu

The new display file menu can now be run using the GO command:

```
GO PGMMENU
```

```
PGMMENU                                EXAMPLE PROGRAM MENU                09:02:51
SELECT ONE OF THE FOLLOWING:
  1.  DISPLAY LIBRARY LIST  (DSPLIBL)
  2.  WORK WITH ACTIVE JOBS (WRKACTJOB)
  3.  WORK WITH YOUR JOB   (WRKJOB)
  90. RETURN
```

```
OPTION:  ____
```

Exiting from a Program Menu without Returning to the Previous Menu

When you code a TYPE(*PGM) menu to go from one program menu to another and use the RTNPNT(*NO) parameter, you need to tell the menu driver when to exit the original menu.

The program menu needs to communicate with the menu driver that F3 was pressed. If the program menu is coded to go to program MENU2, with a RTNPNT(*NO), it has to be able to convey information between programs and to convey information to the menu driver to tell it what should be done. You can use data queues to communicate between the programs. For more information about data queues, see the *CL Programmer's Guide*. The following example shows you how to communicate between program menus if you want to use the RTNPNT(*NO) parameter to go from one menu to another:

Program 1

```

PGM
DCL VAR(&FLDLEN) TYPE(*DEC) LEN(5 0) VALUE (10)
DCL VAR(&FIELD) TYPE(*CHAR) LEN(10)
DCL VAR(&WAIT) TYPE(*DEC) LEN(5 0) VALUE(0) /* Don't wait */
.
.
/* Handle the function keys on the menu */
IF COND(&IN03 *EQ '1') + /* F3=Exit pressed */
    THEN(DO)
        /* Delete the Data Queue */
        DLTDTAQ DTAQ(QGPL/DTAQ1)
        /* Create the Data Queue */
        CRTDTAQ DTAQ(QGPL/DTAQ1) MAXLEN(10)
        TEXT('Test Data Queue')
        GOTO SNDDQ /* Send info to data queue*/
    ENDDO
.
/* Handle the options on the menu */
IF COND(&OPTION *EQ 1)
    THEN(GO MENU(*LIBL/MENU2) RTNPNT(*NO))
.
.
/* Returned from menu 2 after F3 or F12 pressed */
CALL PGM(QRCVDTAQ) PARM(QGPL DTAQ1 &FLDLEN &FIELD &WAIT)
IF COND((&FLDLEN *NE 0) *AND (&FIELD *EQ 'EXIT '))
    THEN(GOTO SNDDQ)
ELSE GOTO END
.
.
SNDDQ:DO
    /* Change the variable so the menu driver will know to */
    /* exit and send information to the data queue to */
    /* communicate to next program what happened */
    CHGVAR VAR(&ACTION) VALUE(X'FFFF')
    CHGVAR VAR(&FLDLEN) VALUE(4)
    CHGVAR VAR(&FIELD) VALUE('EXIT ')
    CALL PGM(QSNDDTAQ) PARM(QGPL DTAQ1 *FLDLEN &FIELD)
    GOTO END
ENDDO
END: ENDPGM

```

Program 2

```
PGM
DCL VAR(&FLDLN) TYPE(*DEC) LEN(5 0) VALUE (10)
DCL VAR(&FIELD) TYPE(*CHAR) LEN(10)
DCL VAR(&WAIT) TYPE(*DEC) LEN(5 0) VALUE(0) /* Don't wait */
.
.
/* Handle the function keys on the menu */
IF COND(&IN03 *EQ '1') + /* F3=Exit pressed */
    THEN(DO)
        /* Delete the Data Queue */
        DLTDTAQ DTAQ(QGPL/DTAQ1)
        /* Create the Data Queue */
        CRTDTAQ DTAQ(QGPL/DTAQ1) MAXLEN(10) +
            TEXT('Test Data Queue')
        GOTO SNDDQ /* Send info to data queue*/
    ENDDO
.
.
/* Handle the options on the menu */
IF COND(&OPTION *EQ 1) +
    THEN(GO MENU(*LIBL/MENU2) RTNPNT(*NO))
.
.
/* Returned from menu 2 after F3 or F12 pressed */
CALL PGM(QRCVDTAQ) PARM(QGPL DTAQ1 &FLDLN &FIELD &WAIT)
IF COND((&FLDLN *NE 0) *AND (&FIELD *EQ 'EXIT '))
    THEN(GOTO SNDDQ)
ELSE GOTO END
.
.
SNDDQ:DO
    /* Change the variable so the menu driver will know to */
    /* exit and send information to the data queue to */
    /* communicate to next program what happened */
    CHGVAR VAR(&ACTION) VALUE(X'FFFF')
    CHGVAR VAR(&FLDLN) VALUE(4)
    CHGVAR VAR(&FIELD) VALUE('EXIT ')
    CALL PGM(QSNDDTAQ) PARM(QGPL DTAQ1 *FLDLN &FIELD)
    GOTO END
ENDDO
END: ENDPGM
```

Avoiding Menu Name Conflict

Because high-level system menus are named by full words, there is some potential for conflict with user-defined menu names. For example, if you use the CRTMNU command to create a menu called MAIN, there may be a conflict with the system-supplied menu, MAIN. If you use the GO command to call that menu (GO MAIN), the system menu MAIN will probably be shown, because it resides in the QSYS library. A conflict can also occur if a future release contains a new system menu that has the same name as a menu you created during the previous release.

Naming Your Menus

To avoid naming conflicts with system command menus, you should avoid menu names that start with CMD. The system command menu names use the format CMDxxxxxxx, where xxxxxxx is any subject or verb used in CL command names.

Placing Your Menu in a Higher Library in the Library List

All branches to system menus from other system menus use the library list search order. Use of the library list search order allows multilingual support for the system menus. It also allows you to override a system menu by placing your own version of it in a library higher on the search order than library QSYS.

Specifying the Library That Contains the Menu

You can avoid menu name conflict by specifying the library that contains the menu you want to run. For example, you can use `GO MENU(*USRLIBL/menu-name)` to call user-defined menus, and use `GO MENU(*LIBL/menu-name)` to call system menus.

Using the Generic Menu Specification

When working interactively, you can use a generic menu specification on the `GO` command to avoid menu name conflict. In an example given earlier (see “Avoiding Menu Name Conflict” on page 9-15), a potential conflict existed between system and user-defined menus called `MAIN`. By specifying `GO MAIN*`, the system will display a list of all menu names that start with `MAIN` in your library list and allow you to select which menu you want.

Changing the Command Default after Duplicating a Command

You can use the Create Duplicate Object (`CRTDUPOBJ`) command to create a duplicate of the `GO` command for calling user-defined menus. The following example creates a duplicate of the `GO` command called `GOUSR`:

```
CRTDUPOBJ OBJ(GO) FROMLIB(QSYS) OBJTYPE(*CMD) NEWOBJ(GOUSR) TOLIB(QGPL)
```

Next, use the Change Command Default (`CHGCMDDFT`) command to change the command default for the `MENU` parameter to use library `*USRLIBL` rather than `*LIBL`:

```
CHGCMDDFT CMD(QGPL/GOUSR) NEWDFT('MENU(*USRLIBL/*N)')
```

With the `MENU` parameter default changed to `*USRLIBL`, the `GOUSR` command will bypass system menus and find only those menus in the user portion of your library list.

Displaying Menu Attributes

The Display Menu Attributes (`DSPMNUA`) command can be used to show the attributes of a menu object. These include:

- The menu type (`*UIM`, display file, or program menu)
- The display and message files used by display file (`*DSPF`) menus
- The programs used by program (`*PGM`) menus
- The current (`CURLIB`) and product (`PRDLIB`) libraries associated with the menu
- The text describing the menu object

Changing Menu Attributes

The Change Menu (`CHGMNU`) command can be used to change the attributes of a menu object without having to re-create the object. The attributes which can be changed are:

- The current (`CURLIB`) and product (`PRDLIB`) libraries for all menu types

- The descriptive text for all menu types
- The display and message files used by display file (*DSPF) menus
- The programs used by program (*PGM) menus

Deleting Menus

The Delete Menu (DLTMNU) command can be used to delete menu objects from a library. The DLTMNU command can be used to delete only the menu object. Referenced display and message files (used by display file menus) and programs (used by program menus) can also be deleted.

DLTMNU is a *generic* command. For example, all menus in a library called OELIB could be deleted using the command, `DLTMNU OELIB/*ALL`.

As another example, if only those menus in OELIB whose names started with ACC were to be deleted, the command, `DLTMNU OELIB/ACC*` could be used.

Chapter 10. Using User-Defined Data Streams

Instead of having the system control and process the 5250 display data stream, you can control and process it. To do so, you must use the USRDFN keyword in the DDS for a display file. The data is sent to the display station using a normal output operation that uses the name of the record format containing the USRDFN keyword. When input data is received after the output operation, your program must determine through the input record area what was received from the display station.

Note: You should be careful when using this support because error conditions can cause an apparent OS/400 malfunction.

When you use the USRDFN keyword at the record level, the format does not contain any fields. Therefore, the buffer length of the file defaults to the length of the longest normal record or 100 (whichever is greater). If the user-defined data stream is longer than this default buffer length, you should perform the following steps to obtain a larger buffer length:

- Define an externally described file, and create the program using this file and a record format in that file. The format should not have response indicators defined for it. This includes file-level indicators that are spread to all record formats. Any fields in the format should be defined with a field use of *both* (input and output).
- Create a second file and specify LVLCHK(*NO). The second file should have two record formats:
 - A format with the same name as the format in the first file and which contains the USRDFN keyword.
 - A format with one field in it. The length of this field must be as long as the longest user-defined data stream that is to be sent to the screen.
- When you run the program, override the first file with the second display file.

Information about 5250 Display Data Streams

For information about coding 5250 display data streams, see the 5250 Display Data Stream, see the *IBM 5250 Information Display System Functions Reference Manual*.

Understanding Display Station Differences

If you use user-defined data streams, you should be aware of the following differences between local display stations (those attached to the display station controller) and remote display stations (those attached to remote display station controllers).

- For local display stations, a start-of-header order length greater than 11 causes the negative response hex 1005012B to be sent. No negative response is sent for remote display stations.
- For local display stations, do not accept more than four field control words for each input-field definition. More than four causes the negative response hex 10050130 to be sent. No negative response is sent for remote display stations.

- For local display stations, self-check fields can be as long as 33 bytes for signed numeric fields and 32 bytes for all other fields. If the length is exceeded, the status response hex 00000287 is sent to the user when he or she tries to exit the self-check field. For remote display stations, all fields can be 33 bytes.
- Two forms of the Request Maintenance Statistics command are supported for remote display stations: (1) requests that the error log area be reset, and (2) requests that the error log area not be reset. For local display stations, the error log area is always reset.

Understanding User-Defined Data Stream Limitations

The output record area for a user-defined record format must contain the following in the order specified:

1. Display-station-specific information (required by the system), which causes the system to send the display-station-specific data stream to the display station.
2. Display-station-specific data stream, which is sent to the display station.

The USRDFN keyword is specified at the record format level and excludes for that record format most other functions such as the use of indicators and all field-related functions. However, the display file can contain other record formats not containing the USRDFN keyword, and the record formats can be used in any order by a program. When you use such a display file, you should be aware of the following:

- When the system write routine recognizes a user-defined request, it disregards all previous requests to the display. At the completion of the user-defined request, the system assumes that a single record format is on the screen and that this is the record format containing the USRDFN keyword. All erasing, all resetting, and unlocking of the keyboard is your responsibility. The next I/O request can be another user-defined request or a normal field-level request.
- A normal field-level request after a user-defined request is handled as follows:
 - If the OVERLAY keyword is not specified, the screen is erased before the request is run.
 - If the OVERLAY keyword is specified, only the portion of the display needed (entire lines) is erased.
 - The 5250 format buffer is reset, which means that all input fields are changed to output-only fields.

The system assumes that only this record format exists on the screen. All previous requests are disregarded.

- Help specifications are allowed in user-defined record formats.
- When the USRDFN keyword is specified in a record format, no fields can be defined for that record format. The only valid keywords are:

File Level	Record Format Level
KEEP	ALTNAME
OPENPRT	HELP
PASSRCD	HLPCLR
PRINT	HLPRTN
	INVITE
	PRINT

File Level	Record Format Level
	TEXT

- The user-defined data stream can alter the CFnn and CAnn keys and the location of the message line in the display. However, display station support assumes they are the same as when they were last set.
- All display files that contain user-defined data streams should be opened as both input and output files. This is because read and write commands in the data stream are not dependent on write and read requests.

The output data stream should start with an escape character hex 04 and be followed by a clear unit hex 40 or write to display command hex 11.

The output buffer must include information needed to send and receive the appropriate line controls. The buffer format for a 5250 display station is:

Byte	Contents
0-1	Send data length (in hexadecimal), defines the output data stream length
2-3	Receive data length (in hexadecimal), defines the maximum input data length
4	Requested function Hex 51 Send (WP mode) Hex 53 Send/Receive (WP mode) Hex 61 Send (3270 data stream) Hex 63 Send/Receive (3270 data stream) Hex 71 Send Hex 73 Send/Receive
5-n	Output data stream

- The 3270 Model 4 display station supports a display size of 43 lines by 80 columns. If you have a 3270 Model 4 display station, you can use function codes 61 and 63 to write to all 43 lines.
- For 3270 Model 4 display stations that are using function code 61 or 63, the system displays status messages on line 43. Any data that is on line 43 when a status message is displayed is replaced by the status message.
- If you are using function code 61 or 63 and press the key that is defined as the System Request key, the key is returned to the application program instead of displaying the System Request menu. If you need access to the system request function when using function code 61 or 63, you can define the Attention key to display the System Request menu. Before starting the application that uses function codes 61 and 63, specify:

```
SETATNPGM SET(*ON) PGM(QSYS/QWSSYSRQ)
```

When the Attention key is pressed, the System Request menu is displayed.

This support prohibits the use of a read operation except after a write-read(nowait) operation. A write-read operation that sends a read command and specifies the receive data length performs the operation normally performed with a read request. The write-read function can be performed by doing one of the following:

Operation	RPG/400	COBOL/400	Control Language
Write-read(wait)	EXFMT		SNDRCVF WAIT(*YES)
Write-read(nowait)	WRITE with INVITE, READ	WRITE with INVITE, READ	SNDRCVF WAIT(*NO)

Both the write-read(wait) and the write-read(nowait) operations are a combination of a write operation and a read operation to the same record format. When using the write-read(wait) operation, control does not return to the program until input is received from the display device. The write-read(nowait) operation is used to send a request for input to a display device and return to the program without waiting for the input to arrive. This allows a program to request input from one or more devices, and continue processing without waiting for any of the devices to respond. For each I/O request, you must make sure that the function byte and the send depth actually reflect the data stream sent. The receive length must be long enough to accommodate all data returned by the display station. If any of these is wrong, unexpected or unacceptable functions may happen. For example, if the function byte indicates a send to the display station and the data stream specifies a read modified command, the system sends the data stream to the display station and no read is performed.

On input operations, the input buffer of the program contains the data received from the display station. For example, when a read modified completes, the input buffer contains an aid identification (AID) byte and the cursor address followed by each changed field. Each changed field is preceded by the buffer address order and field location on the screen.

All AID bytes are accepted by display station support for user-defined data streams. If the Print key is pressed, the system attempts to perform the print function.

All write and write-read operations must specify the record format name. A read operation that specifies the name of a record format that contains the USRDFN keyword and is not one of the appropriate read operations for the display station causes an exception to be issued.

Each request to a 5250 display station can contain more than one command. Each command must be requested using the appropriate system operation identified as follows:

Operation	Output Buffer Send Length (Bytes 0–1)	Output Buffer Receive Length (Bytes 2–3)	Output Buffer Request Function (Byte 4)	Output Buffer Command (Bytes 5–n)
Write	nn	0	71 (Send)	Clear unit Clear format table Write to display Write error line Restore Roll Copy

Operation	Output Buffer Send Length (Bytes 0–1)	Output Buffer Receive Length (Bytes 2–3)	Output Buffer Request Function (Byte 4)	Output Buffer Command (Bytes 5–n)
Write-Read	nn	nn	73 (Send/Receive)	Clear unit Clear format table Write to display Write error line Restore Roll Read input fields Read MDT fields Read immediate Save

Chapter 11. Passing Data between Programs

You can use the system I/O operations to pass data between programs both in the same routing step of a job or across routing steps.

Passing Data in the Same Routing Step in a Job

To pass data between programs in the same routing step, you can either share the file between the programs, or you can use the KEEP and ASSUME DDS keywords to share a file between programs. The programs must open the same file and the file must be designated as a shared file. (See “Sharing Display Files in the Same Job” on page 3-50.) Because the programs share the file, the read operations are performed as described under “Reading Input from the Display” on page 3-33 and “Understanding How the System Reads Input from the Display” on page 3-40.

You can also use the KEEP and ASSUME keywords to pass data between programs. The data is written to the display by the first program, and used from the display by the second.

You can use the KEEP keyword to keep data on the display for review after the program has ended, or you can use it to pass data between programs.

Normally, when a file is closed, the current display is cleared. However, you can control this by using the KEEP keyword. If a record that is on the display when the file is closed has the KEEP keyword specified, the system saves the name of the first such record to support passing data. Using this keyword alone, you cannot support processing of passed data, you must also use the ASSUME keyword in the display file opened by the next program.

The ASSUME keyword causes a read operation to a specific record format name to be valid when no preceding write operation to that record format name (or any other record format) has occurred since the display file was opened. The following shows a typical example of what happens when the ASSUME keyword is specified:

1. Program PGM1 issues a write operation to the record format PGM1ANY in the display file DSPFIL1 and calls program PGM2. PGM1ANY specifies the LOCK keyword.
2. PGM2 opens DSPFIL2 and issues a read operation to record format PGM2ANY. The ASSUME keyword is specified. Input data is read from the display and processed by record format PGM2ANY.

Records from record formats having the ASSUME keyword specified cannot overlay one another on the display. In addition, all records must have at least one field that is displayed.

When the system reads assumed records from the display, only fields whose modified data tags (MDTs) are on are returned. (This assumes that either the DSPATR(MDT) keyword was specified for the field on the last output operation or the user has typed in the field.) When the ASSUME keyword is in effect, the data returned to the program is as follows:

- For input-only and output/input fields with their MDTs on, the changed data is returned.

- For other input-capable fields, blanks are returned for character fields and zeros are returned for numeric fields.

In addition, only those fields received whose line and position on the display match the field of an assumed record are processed. The data is processed using the field descriptions in the assumed record, independent of how the fields were written to the display.

For the 5250 display station, the first write operation or write-read operation after the file is opened sends a CA and CFnn key specification to the display station. Because there is no write operation after an open when using the ASSUME keyword, the CFnnkey specification remains as it was left by the last application. The CA and CFnnkey specification in this file will not be used until after the first write operation to the file.


After the file is opened and the first write operation is issued, the display will be erased if the OVERLAY keyword is not specified. When the OVERLAY keyword is specified, all input-capable fields on the display become output-only fields. After the first write operation, assumed records cannot be read by a program.

Fields not received from the assumed records on the display are returned to the user program as follows:

Field	Initialized To
Field with DFT keyword used	Value specified in DFT keyword
Character field (no DFT keyword)	Blanks
Numeric field (no DFT keyword)	Zero
Hidden field	Zero

Passing Data between Routing Steps in a Job

The following example shows the steps used in passing display data between programs in different routing steps. Note the use of the KEEP, ASSUME, and PASSRCD keywords. Programs PGM1 and PGM2 are user programs started by the subsystem SBS using different routing entries. PGM1 and PGM2 run in different routing steps but are both contained in the job 000618/QUSER/WSN01.



RV2W044-2

- 1** The user signs on and SBS starts a routing step based on the routing data. The first program in the routing step is PGM1.
- 2** PGM1 opens the display file DSPFIL1.
- 3** PGM1 interacts with the user and issues the following before ending:
 - A write operation to DSPFIL1 with the record format name PGM2RD. The KEEP keyword is specified in the record format PGM2RD.

- A close operation to DSPFIL1. The information displayed on WSN01 is not cleared because the KEEP keyword is specified in record format PGM2RD.

PGM1 then ends by issuing a RRTJOB command specifying routing data that will cause SBS to call PGM2.

- 4** SBS starts a new routing step based on the data supplied by PGM1 in the RRTJOB command.
- 5** PGM2 opens the display file DSPFIL2.
- 6** PGM2 performs a read operation to DSPFIL2 with or without the record format name PGM2ANY. If the record format name is not specified, the system tries to use the record format PGM2RD to process the data because the KEEP keyword was specified (in step 5). To do so, record format PGM2RD must exist in DSPFIL2, but it does not have to be identical to record format PGM2RD in DSPFIL1; only the fields that are required by PGM2 must be identical. (If a field is returned from the display station for which no field description exists in PGM2ANY, the field is ignored. If the field description requires validation and the data received fails the validity check, PGM2 reissues a read operation to allow the current user to correct the data.) If a record format is not specified or if record format PGM2RD does not exist in DSPFIL2 or does not have the ASSUME keyword specified, the data passed to the display station via the KEEP keyword cannot be processed. (The ASSUME keyword must be specified for the record format used to process passed data.)
- 7** PGM2 processes the data and issues a close operation to DSPFIL2, which clears the display.

When PGM2 ends, its routing step ends and the display returns to the control of SBS which shows the sign-on display.

Chapter 12. Waiting for Input from a Display File, an ICF File, and a Data Queue

You can use data queues for a program that waits for data on a display file, an ICF file, and a data queue at the same time (in any combination). When you specify the DTAQ parameter for the following commands:

- Create Display File (CRTDSPF) command
- Change Display File (CHGDSPF) command
- Override with Display File (OVRDSPF) command
- Create ICF File (CRTICFF) command
- Change ICF File (CHGICFF) command
- Override ICF File (OVRICFF) command

you can indicate a data queue that will have entries placed on it when any of the following occurs:

- An enabled command key or Enter key is pressed from an invited display station.
- Data becomes available from an invited ICF session.

By using the IBM-supplied QSNDDTAQ program, jobs running on the system can also place entries on the same data queue as the one specified in the DTAQ parameter.

An application program uses the IBM-supplied QRCVDTAQ program to receive each entry placed on the data queue and then processes the entry based on whether it was placed there by a display file, by an ICF file, or by the QSNDDTAQ program. For a display file, the application then issues a read or read-from-invited devices operation to receive the data. For more information on the QRCVDTAQ function and syntax, and examples of waiting on one or more files and a data queue, refer to the *CL Programmer's Guide*.

The display file and ICF file entry that is put on the data queue is 80 characters long and contains the field attributes described in Table 12-1. Therefore, the data queue that is specified using the commands listed above must have a length of at least 80 characters.

Entries placed on the data queue by jobs using QSNDDTAQ are defined by the user.

Table 12-1 (Page 1 of 2). Display File and ICF File Entry Field Attributes

Position	Data Type	Meaning
1 through 10	Character	The type of file that placed the entry on the data queue. This field will have one of two values: *ICFF (ICF file) *DSPF (display file) If the job receiving the data from the data queue has only one display file or one ICF file open, then this is the only field that needs to be used to determine what type of entry has been received from the data queue.

Table 12-1 (Page 2 of 2). Display File and ICF File Entry Field Attributes


Position	Data Type	Meaning
11 through 12	Binary	Unique identifier for the file. The value of the identifier is the same as the value in the open feedback area for the file. This field should be used by the program receiving the entry from the data queue only if more than one file with the same name is placing entries on the data queue.
13 through 22	Character	The name of the display or ICF file. This is the name of the file actually opened, after all overrides have been processed, and is the same as the file name found in the open feedback area for the file. This field should be used by the program receiving the entry from the data queue only if more than one display file or ICF file is placing entries on the data queue.
23 through 32	Character	The library where the file is located. This is the name of the library, after all overrides have been processed, and is the same as the library name found in the open feedback area for the file. This field should be used by the program receiving the entry from the data queue only if more than one display file or ICF file is placing entries on the data queue.
33 through 42	Character	The program device name, after all overrides have been processed. This name is the same as that found in the program device definition list of the open feedback area. For file type *DSPF, this is the name of the display station where the command or Enter key was pressed. For file type *ICFF, this is the name of the program device where data is available. This field should be used by the program receiving the entry from the data queue only if the file that placed the entry on the data queue has more than one device or session invited prior to receiving the data queue entry.
43 through 80	Character	Reserved

Chapter 13. Using Alternative Character Sets and Code Pages

In multinational environments, data in one national character set may need to be displayed or entered on display stations that support another national character set. This is particularly true of characters with accents and other characters with diacritical marks (such as c with a cedilla, n with a tilde, and u with an umlaut). In this section, these characters are called **extended alphabetics**.

For example, assume that a physical file on the system contains data in the Basic French character set, and includes an é (e with an acute accent). In the Basic French character set, this character is hex C0. The data could have been entered on a display station that can handle the character or could have been sent to this system from another system over a communications line.


Note: On some display stations, extended alphabetics can be entered on the keyboard (by pressing Cmd, then the key to its right with two diacritical marks on it, then the 2 hexadecimal digits that represent that character).



When the hex C0 is sent to a display station that does not recognize hex C0 as é, the hex C0 is not displayed as é. For example, a display station that recognizes the U.S. basic characters displays hex C0 as { (a left brace). A reasonable character to substitute for é would be e, which is code point 85. To do this, the hex C0 must be translated to hex 85 for display on a U.S. basic display station.

You can use character translation to cause the hex C0 to be translated to an unaccented e (hex 85). With the IBM-supplied translate tables, the system can translate most extended alphabetics, but not all. If an extended alphabetic character does not have a clearly preferable equivalent, the system translates the character to a (-) hyphen.

System Has Characters Not Normally Displayed on the Device: The case of an output/input field shows how character translation occurs at a display station.



Assume that a record in a physical file contains a field with the value Renée. An application program reads the record from the physical file, and writes a record containing the data to the display file. In the DDS for the display file, the output/input field in which Renée appears has the Character Identifier (CHRID) keyword specified.¹ This keyword asks the system to perform character translation if needed. Character translation is needed if the CHRID parameter value for the display file differs from the CHRID parameter value for the display station. In this case, character translation is needed because the display file has CHRID(288 297), which is the basic French code page and character set, and the device description has CHRID(101 37), which is the basic U.S. code page and character set.

When displaying the data, the system translates the hex C0 to hex 85, and Renee appears on the display.

On input, one of the following occurs:

- If the modified data tag (MDT) is turned on for the field (this happens when the user types into the field or if the DSPATR(MDT) keyword is in effect for the field) the contents of the field (with the translated character hex 85) is returned to the program.
- If the modified data tag (MDT) is not turned on for the field, the saved contents of the field (with original, untranslated, data) is returned to the program.

Device Passes Characters Not Displayed on the System: If the user can enter data not normally displayed on the system (for instance, a user on a French-language display station in Montreal dials up a remote line to a system in Toronto with display stations that cannot display extended alphabets), no change occurs when the data is sent to the system. The program can read data from the French-language display station and write it to a physical file. However, when another user on the Toronto system displays data from the physical file, the system attempts to translate the data for the display station that cannot display extended alphabets.

Specifying Character Translation for Fields

Character translation occurs only if the CHRID parameter value in the display file is different from the CHRID parameter value in the device description.

1. The CHRID parameter on the display file is set by the CHRID parameter on the CRTDSPF, CHGDSPF, or OVRDSPF command. The CHRID parameter can have one of the following values:

*DEVD (the default): Use the CHRID parameter specified on the device description on which the application is currently running. No character translation occurs. Any CHRID keywords specified in the DDS are ignored.

*SYSVAL: Use the character set and code page specified in the system value QCHRID on which the application is currently running. Specify the CHRID keyword in the DDS for the display file fields that will need translation. Constants are not translated.

*JOBCCSID: Use the character set and code page specified by the job. This allows named fields and unnamed (constant) fields to be automatically

¹ If *JOBCCSID is specified by the CHRID parameter on the CRTDSPF, CHGDSPF, or OVRDSPF commands, the DDS keyword CHRID is ignored. For more information, see the description for *JOBCCSID in "Specifying Character Translation for Fields."

translated when the job CCSID or the display file CCSID does not match the device description CCSID. If the job CCSID does not match the device description CCSID, named fields are translated from the job CCSID to the device description CCSID on output and conversely on input. If the display file CCSID does not match the device description CCSID, data in the display file is translated from the display file CCSID to the device description CCSID on output. When *JOBCCSID is specified, the DDS CHRID keyword is ignored. Use the No Coded Character Set Identifier (NOCCSID) keyword on named and unnamed fields that you do not want translated.

Character set and code page: Use the character set and code page specified. See Table 13-1 on page 13-5 for the list of valid values.


- The CHRID parameter on the device description is set by the CHRID parameter on the Create Device Description Display (CRTDEVDSP) or Change Device Description Display (CHGDEVDSP) command. This parameter can have one of the following values:

- *SYSVAL: Use the character set and code page specified in the system value QCHRID.
- *KBDTYPE: Use the character set and code page specified in the keyboard language prompt (KBDTYPE). This value corresponds to the country keyboard language identifier.

Character set and code page: Use the character set and code page specified. See Table 13-1 on page 13-5 for the list of valid values.


If the CHRID parameter values are different, the system uses a translation table in library QUSRSYS to convert the data. Different translation tables are used for output and input. The name of the translation table used is derived from parts of the CHRID parameter values for the display file and device description, as follows:

On Output:



Translation Table Used: Q297101037

On Input:



Translation Table Used: Q037288297

RV2W038-3

IBM supplies a number of tables in library QUSRSYS to handle translation among the most frequently used combinations of character sets and code pages. If you need to tailor the way characters are translated, you can create your own table in library QUSRSYS, using the Create Table (CRTTBL) command to do the translation. To determine what translation tables are available to use, look in the QUSRSYS library for object type *TBL.

Determining the Character Identifier (CHRID) Value for Your Display

The CHRID value specified should be based on the attributes of the display station. The table below shows CHRID values that are appropriate for each display station keyboard type. For some display stations, you do not need to specify the KBDTYPE parameter, but the KBDTYPE value for the equivalent keyboard can be used to determine the CHRID value for the display station:

Table 13-1. CHRID Values

Language/Country	Keyboard Type (KBDTYPE)	Limited CHRID	Full CHRID
International and US ASCII	INB	103 038	697 500
Multinational	AGI BLI CAI DMI FAI FNI FQI ICI INI ITI JEI NEI NWI PRI SFI SGI SPI SSI SWI UKI USI		697 500
Arabic	CLB		235 420
Austria/Germany	AGB	265 273	697 273
Belgium Multinational	BLI		697 500
Canada/French	CAB	277 260	341 260
Cyrillic	CYB		960 880
Denmark/Norway	DMB NWB	281 277	697 277
Finland/Sweden	FNB SWB	285 278	697 278
France	FAB FQB	288 297	697 297
Greece	GKB		218 423
Hebrew	NCB		941 424
Iceland	ICB		697 871
Italy	ITB	293 280	697 280
Japan/English	JEB	297 281	697 281
Japan/Kanji	JKB (For Personal System/55*, 5295 and 3477-J display stations)		332 290
Japan/Katakana	KAB (For 5251, 5291, 5292, and 3180 Katakana display stations)		332 290
Korean	KOB		933 833
Latin 2	ROB		959 870
Netherlands	NEB		697 037
Portugal	PRB	301 037	697 037
Simplified Chinese	RCB		936 836
Spain	SPB	305 284	697 284
Spanish Speaking	SSB	309 284	697 284
Switzerland/French Multinational	SFI		697 500
Switzerland/German Multinational	SGI		697 500
Thai	THB		938 838
Traditional Chinese	TAB		101 037
Turkey	TKB		965 905
United Kingdom/English	UKB	313 285	697 285
United States/English	USB	101 037	697 037
Countries of the former Yugoslavia	YGI		959 870

Chapter 14. Improving System Performance with Displays

System performance is improved by doing the following:

- Minimizing the number of bytes sent and received when designing a display. For example, to reduce the number of fields on an application display:
 - Split a display with many fields into more than one display.
 - Consider removing fields which were added to help with development, testing, or problem reporting.
- Taking advantage of the system functions that reduce the number of bytes sent to and received from the display station. This chapter describes some of these system functions.

Deferring the Write Operation for a Display File

The DFRWRT parameter on the Create Display File (CRTDSPF) or Change Display File (CHGDSPF) command allows you to delay the writing of data to the display until needed. Deferring the write operation is useful when the final display shown at the display station is formed by several record formats being written to the display.

Using DFRWRT(*YES) on a display file improves systems performance in some cases.

More information on the Defer Write parameter can be found in “Deferring the Write Operation Until a Read Request is Made” on page 3-26.

Designating the Primary Screen Size for a Display File

Normally, the display files are set up for a 24 by 80 screen (default size). The DSPSIZ keyword specifies which display sizes are valid for a file and indicates which sizes are the primary and secondary screen sizes. (The primary screen size is the first or only DSPSIZ value.) On the DSPSIZ keyword, the screen size can be specified as *DS3, *DS4, 24 80, or 27 132. For example, DSPSIZ (24 80) specifies a screen size of 24 by 80.

The screen size designated as the primary screen size should be the one with which the display file will most often be used. A performance benefit will be realized by coding the DSPSIZ keyword in this manner. Additional processing is performed when the actual screen size is the secondary screen size.

Writing Only One Page of Subfile Records at a Time

A technique to improve performance when you are using a multiple page subfile is to write only one page of subfile records at a time but use the OS/400 support to roll through the subfile. To do this, you need to define the ROLLUP keyword in DDS with a response indicator and also use the SFLRCDNBR keyword. In your program, you would write the records needed to fill one subfile page and then display that page. When the user wants to see more records, he or she presses the Roll Up key. The program then writes another page of records to the subfile,

places the relative record number of a record from the second page into the SFLRCDNBR field, and displays the record.

The second page of subfile records is now displayed, and if the user presses the Roll Down key, the roll down is handled by the system. If the user presses the Roll Up key while the first page is displayed, the system will also handle the roll up. The program is notified only when the user attempts to roll up beyond the records currently in the subfile. The program would then handle any additional roll up requests in the same manner as for the second page. When you use this technique, the subfile appears to be more than one page because of the use of the roll keys. Yet, you can maintain good response time because the program only fills one subfile page before writing it to the display.

Sharing an Open Data Path (ODP) for the Same Job

OS/400 data management support offers a close level of sharing within a job that allows more than one program to share the same path to the data or display station. By specifying *YES for the SHARE parameter on the Create Display File (CRTDSPF) command, the Change Display File (CHGDSPF) command, and the override file commands, more than one program can share the file status, positions, and storage area. Performance is improved by reducing the amount of main storage the job needs and the time it takes to open and close the file.

Note: To use SHARE(*YES) to improve performance, you need to define many record formats within the display file. However, the program may not use all the record formats in the display file, even though the program has work storage allocated for all the record formats defined in the display file. This causes the PAG storage associated with the job to be larger, which can adversely affect performance.

More information about sharing open data paths is found in “Sharing Display Files in the Same Job” on page 3-50.

Sending Records with Input Fields to the Display in Order

Records containing input fields should be sent to the display station in the order in which they appear on the display. This technique provides better performance than if record formats with input fields are sent randomly or in some other order.

Overlapping and Not Deleting Repeatedly Sent Records

You can use the CLRL(*NO) keyword to prevent an overlapped record from being deleted when the overlapping record is written to the display. If you use this keyword, any records being displayed that are to be overlapped are not deleted from the screen; the new record overlays them entirely or partially. There is a performance advantage to using CLRL(*NO) if you have a display that contains constants and data that is repeatedly sent to the screen. By sending the constants as a separate format and using CLRL(*NO) for the format containing only the data, you can reduce the time required to send the record format to the display.

The use of the PUTOVR keyword causes only those fields for which the OVRDTA or OVRATR keyword have been specified to be sent to the display when a subsequent write or write-read operation is issued to the same record format.

You can also use the OVERLAY keyword to clear only that portion of the display affected by the record format being written.

You can use ERASEINP to improve response time by causing the display to clear fields instead of requiring blanks to be sent to the display. If the fields erased at the display do not have their modified data tags set on for the next read operation, data is returned for those fields from the input save area. This is data saved by the system from the previous return of the field from the display station.

You can use the INZINP keyword at the record level with ERASEINP(*ALL) and PUTOVR to initialize the input save area without sending data for the cleared fields to the display.

Restoring the Display

When *YES is specified for the Restore Display (RSTDSP) parameter, an image of the current display is saved when the display is suspended. When the display file is activated again, the saved image is used to restore the display to its appearance before being suspended.

The RSTDSP(*YES) parameter *must* be specified for the following keywords. If the parameter is not specified, data on the display can be lost if the file is suspended.

- CLRL
- OVERLAY
- PUTOVR
- PUTRETAIN
- ERRMSG
- ERRMSGID

If none of the previous keywords are used, you can improve performance by specifying *NO for the RSTDSP parameter.

Defining Command Attention Keys Rather Than Command Function Keys

Command attention (CAnn) keys return only the indication of the key pressed and not data. Command function (CFnn) keys cause all input data to be returned. If you only need to detect a function key and do not need to return data from the display, define keys as command attention keys.

Using the Invite Operation

The invite operation, specified by the INVITE keyword, allows the program to be responsive to various display station and system events. The invite operation also allows the program to process between the last WRITE and READ operations.

Using Windows

DDS-described windows may improve performance because they only affect the portion of the display where they are placed.

Part 3. Programming Application Displays Using Panel Groups

Chapter 15. Improving Productivity with User Interface Manager	15-1
Increasing User Productivity	15-1
Increasing Application Programmer Productivity	15-1
What to Consider before Using UIM Instead of Data Description Specifications (DDS)	15-1
 Chapter 16. Introduction to the User Interface Manager	16-1
Overview of UIM	16-1
What the UIM Supports	16-1
What Is a Panel Group	16-2
What Is a Menu	16-2
Creating Objects	16-3
Elements Within a Panel Group	16-3
Using the UIM Language Tags	16-3
Using Dialog Commands	16-4
Using Control Language (CL) Commands	16-5
Using an Application Programming Interface (API)	16-5
Defining a Menu Object Using UIM	16-6
Creating a Menu Panel	16-6
Required Tags for a Menu Panel	16-8
Source for Example Menu	16-9
Defining a Panel Group Object Using UIM	16-13
Creating a List Panel	16-13
Required Tags for a List Panel	16-17
Source for Example List Panel	16-18
Application Programming for a List Panel	16-26
Creating a Confirmation List Panel	16-27
Required Tags for a Confirmation List Panel	16-28
Source for Example Confirmation Panel	16-28
Automatic Confirmation Processing	16-31
Application Programming for Confirmation Processing	16-32
Creating a Data Presentation Panel	16-32
Required Tags for a Data Presentation Panel	16-35
Source for Example Data Presentation Panel	16-36
Application Programming for a Data Presentation Panel	16-47
Data Entry Panel	16-50
Creating a Panel with a Menu Bar	16-51
Required Tags for a Panel with a Menu Bar	16-53
Source for Example Panel with a Menu Bar	16-54
Application Programming for a Menu Bar Panel	16-64
 Chapter 17. Details of Using User Interface Manager	17-1
Opening a UIM Application	17-1
Defining Dialog Variables	17-1
Restrictions on Using Dialog Variables	17-2
Dialog Variable Error Messages	17-3
Providing Field Values for a Display Panel Using Dialog Variables	17-4
Using Variable Pool Services	17-4
Character Set and Code Page Considerations	17-5

Displaying	17-5
Printing	17-5
Managing a List	17-6
Defining a List	17-6
Initializing a List	17-6
Displaying a List	17-7
Updating a List	17-7
Removing and Inserting an Entry from a List	17-7
Controlling List Entries on a List Display	17-8
Improving Interactive Response Time for a List Display	17-9
Using Action Lists and Selection Lists	17-9
Using Action Lists	17-9
Using Selection Lists	17-10
Using Selection Characters	17-11
Managing Panel Functions	17-11
Scrolling Support	17-12
Defining Scrollable Areas	17-12
Defining Function Key Scrolling	17-12
Scrolling and Error Conditions	17-13
Scrolling a List Area	17-13
Scrolling a Menu Area	17-13
Scrolling an Information Area	17-13
Scrolling Data Item Groups	17-14
Defining Contextual Help	17-14
Command Line Restrictions	17-16
Command Line Interpretation	17-16
Entering Commands That Are Too Long	17-17
Defining Function Keys	17-17
Formatting Function Keys	17-17
Handling Function Keys and VARUPD Value	17-18
Panel Formatting Concepts	17-19
When Panel Formatting Is Performed	17-19
Application Control of Panel Formatting	17-20
Limits of the Panel Formatter	17-21
Folding Up Multiple Panels When EXIT Is Requested	17-21
Folding Up a List Panel	17-23
Adding a Pop-Up Window over Another Panel	17-24
Using Menu Bars	17-24
Differences Between Pull-Down Menus and Pop-Up Windows	17-25
Using Pop-Up Windows	17-27
Defining Application Windows	17-27
Adding and Removing Windows	17-28
Using the Command Line in a Window	17-29
UIM as a Request Processor Program When Displaying a Panel	17-30
Printing Concepts	17-30
Printing a Print Head Panel	17-32
Printing a Print Panel	17-32
Using Blank Lines for Separating	17-33
Fonts and Highlighting	17-33
Printing the Trailer	17-33
Defining Prolog Areas	17-33
Defining Header Areas	17-33
Using the Page-Eject Function During Printing	17-34
Sharing and Overriding Printer Files	17-34

Printing Double-Byte Character Set (DBCS) Considerations	17-34
--	-------

Chapter 15. Improving Productivity with User Interface Manager

Using the user interface manager (UIM) can improve user and application programmer productivity.

Increasing User Productivity

The UIM controls the panel's appearance and assures consistency with panels developed by IBM. This gives an application a consistent user interface which increases user productivity.

Increasing Application Programmer Productivity

Application programmer productivity is increased by using the UIM to create panels. The application programmer can describe the contents of a panel without specifying all the details. The format of the panel's elements is handled automatically by the UIM. For more information on the panel elements that UIM handles, see "What the UIM Supports" on page 16-1.

Using the UIM language tags allows the application programmer to "link" an option number or function key to a specific command or program. Then, when a user selects an option or presses a function key, the UIM automatically handles running the command or program. The UIM also handles scrolling through a multiple-page panel. The Major Command Groups menu is an example of a multiple-page panel.

What to Consider before Using UIM Instead of Data Description Specifications (DDS)

The UIM and DDS each use a different source language to create interactive displays. Display functions in interactive applications can be built using DDS, a combination of DDS and UIM, or only UIM. With DDS, the application programmer can customize display screens, and with UIM, the display screens are automatically formatted resulting in a consistent appearance. In addition, the UIM performs more dialog management functions than DDS, so using UIM results in less application programming.

The UIM supports the following types of display screens (or panels). Each one can be scrollable or nonscrollable:

- List
- Menu
- Information
- Data entry

For more information on creating these display screens, see Chapter 16, "Introduction to the User Interface Manager" on page 16-1.

Consider the following before using UIM:

- If you are creating a new application, the UIM simplifies making display screens standard.

- If you are rewriting an old application, evaluate the effort involved to rewrite the display screens versus the productivity benefits already described. In some cases, conversion to UIM may not be warranted unless a major redesign or rewrite of an application is required for other reasons.
- Because UIM was designed for 525x nonprogrammable workstations, using UIM does not appreciably simplify converting an application oriented to a programmable workstation except by ensuring standard display screens.
- If an application program makes extensive use of database files, UIM does not refer to database files as DDS does.
- Using UIM to create data panels should be for low frequency and low volume output/input. Nonscrollable data entry applications with high frequency and volume of interactions should consider using display files created from DDS for the best performance.

For additional factors to consider when using UIM, see “Choosing between Panel Groups, Documents, and Records for Help” on page 18-2.

Chapter 16. Introduction to the User Interface Manager

This chapter gives an introduction to the user interface manager (UIM) that IBM uses to develop the AS/400 panels. It explains what the UIM provides to make creating and managing panels easy and also gives the panels the look of an AS/400 panel.

For detailed information on the UIM, see Chapter 17, "Details of Using User Interface Manager" on page 17-1.

Overview of UIM

The OS/400 UIM is a part of the system that allows you to define panels and dialogs for your application and provides the following support:

- A tag-based language for describing data and panels.
- A compiler to create panel group objects and menu objects using the tag-based language.
- A set of application programming interfaces (APIs) to use as panel group objects to display and print panels.
- The UIM also provides the following functions:
 - Dialog commands for screen management
 - Contextual online help
 - InfoSeeker
 - Pop-up windows
 - Menu bars
 - Command line for entering CL commands
 - Tailoring of the contents of a panel for different users or environments
 - Fast paths through menu networks
 - Double-byte character set (DBCS) languages
 - Bidirectional (BIDI) language support

UIM supports common panel types, such as menus, information displays, list displays, and entry displays. When all display types and interfaces are consistent, users adapt more quickly to new applications.

UIM applications can coexist with and share the requester display device with other open display files that are not under UIM control. However, a UIM panel and a DDS-defined record format cannot appear on the display at the same time. When a UIM panel replaces a DDS panel or vice versa, the system suspends operations of one file or panel group and restores the display as needed.

What the UIM Supports

When you design a panel, the UIM provides the correct placement and format of many panel elements, such as:

- Panel name
- Panel title
- Separator lines
- Column headings

- Entry fields
- Command line
- Message line
- Function keys
- Pop-up windows
- Menu bars
- Pull-down menus

In addition, the UIM provides the following support:

- Correct placement of the cursor

The user interface style has several rules for positioning the cursor which UIM supports.

- Cursor-sensitive help information

Depending on where the cursor is located when the Help key is pressed, the user interface style has rules for what type of help information is displayed.

- Scrolling
- Fast paths through menu networks
- National language considerations to make translating easier
- Windows for help information and application panels
- 132-column panels
- Left-to-right and right-to-left (bidirectional) national language formatting
- Hypertext links
- Control over left-to-right and right-to-left orientation of text
- Ability to create online help information

What Is a Panel Group

A **panel** is a visual presentation of data on the screen. A **panel group** is an object that contains a collection of display formats, print formats, or help information. The system-recognized identifier for the object type is *PNLGRP.

For detailed information on the panel group (PNLGRP) language tag, see “PNLGRP (Panel Group)” on page A-136.

What Is a Menu

A **menu** is an object that contains the definition of a panel which contains one or more options. The user can select an option from the panel in order to start using a program or command, or to go to another menu. The system-recognized identifier for the object type is *MENU.

The OS/400 program provides the GO command to display a menu. Therefore, no application program is necessary to display and handle the user interaction for a menu.

You can define the following types of menus using the Create Menu (CRTMNU) command.

- *DSPF** An existing display file (*DSPF) and message file (*MSGF) are used to display the menu.

- *PGM** The OS/400 program calls an application-defined program to display the menu. The program is responsible for displaying the menu to the user and processing options requested by the user.
- *UIM** The menu object is created using a member in a source file that contains a description of the menu. The source describes the menu using the UIM tags.

This chapter discusses how to create a *UIM type of menu. For information on how to create a *DSPF or *PGM type of menu, see Chapter 9, “Creating and Accessing Menus Using Display Files” on page 9-1.

Creating Objects

The UIM creates and changes the following objects:

- Panel group objects
- Menu objects
- Search index objects

The panel group and menu objects contain panel definitions and online help information. A menu object (*MENU), which contains a panel group definition, is created using the TYPE(*UIM) parameter on the Create Menu (CRTMNU) command. The panel group and menu objects are created using a tag-based language that specifies definitions for UIM elements.

The UIM creates search index objects that contain search terms extracted from online help information. A search index object makes it more efficient for a user to locate specific online information using InfoSeeker.

Elements Within a Panel Group

The tag-based language used to define the panels, menus, and online help also supports definitions of symbolic elements that include the following:

- Variable classes
- Data elements that can be accessed through the UIM application programming interface (API), such as dialog variables and lists
- Variable records that define buffers passed by application programs
- Conditional expressions that must be true if certain processing is to take place
- Key lists containing the definition of function keys
- Menu bars containing the definition of one or more pull-down menus
- Panel definitions containing one or more areas to present data, information, lists, and menus
- Online help text modules

Using the UIM Language Tags

The language tags are an easy-to-use function for defining panels. Using the language tags helps application programmers create consistent appearing panels. For more information on the language tags, see Appendix A, “UIM Panel Group Definition Language” on page A-1.

Using Dialog Commands

Dialog commands are special functions, recognized only by the UIM, that allow the user to navigate through the panels.

Following is a list of the dialog commands and the functions they perform:

ACTIONS	Alternates the cursor position between the panel and the menu bar; removes, if shown, a pull-down menu from the panel.
CALL	Calls an application program to perform a function.
CANCEL	Backs up one panel (returns to the previous panel).
CHGVIEW	Changes the displayed view of a list by switching defined sets of columns to be shown.
CMD	Submits an AS/400 CL command (or System/36 environment OCL command) to the system for processing.
CMDLINE	Displays a pop-up window with a command line.
DSPHELP	Displays a module of help text.
ENTER	Initiates processing of an action; submits panel input for processing.
EXIT	Returns the user from a group of displays or menus.
EXTHelp	Displays the <i>extended</i> help text for the panel.
HELP	Displays help information for the panel, based on the position of the cursor.
HELPHELP	Displays information about how to use the help facilities.
HELPIDX	Initiates the InfoSeeker function for the application to allow the user to make a search request.
HOME	Displays the initial (home) menu of the job.
KEYSHELP	Displays the help for the function keys shown on the displayed panel.
MENU	Displays a subsequent menu as a result of selecting a menu item or pressing a function key.
MOREKEYS	Displays an additional set of active function keys and their descriptions; used when all keys cannot be shown at once.
MOVETOP	Moves a cursor-selected line to the top of the scrollable information area.
MSG	Displays a message on the message line.
PAGEDOWN	Pages (scrolls) <i>forward</i> by one panel.
PAGEUP	Pages (scrolls) <i>backward</i> by one panel.
PRINT	Prints all the information shown on the current display.
PROMPT	Prompts (seeks input) for commands, action list options, or entry fields.
PULLDOWN	Displays the pull-down menu for the first choice shown on the menu bar.
RETRIEVE	Retrieves and displays the previously entered command.
RETURN	Returns control (and a return value) to an application for processing.

Note: To provide the Refresh/Redisplay function for an application, use the RETURN dialog command.

For detailed information on the dialog commands, see Appendix B, "UIM Dialog Commands."

Using Control Language (CL) Commands

The following CL commands are used to work with panel groups, menus, and InfoSeeker:

- ADDSCHIDX (Add Search Index Entry)
- CHGMNU (Change Menu)
- CHGSCHIDX (Change Search Index)
- CRTMNU (Create Menu)
- CRTPNLGRP (Create Panel Group)
- CRTSCHIDX (Create Search Index)
- DLTMNU (Delete Menu)
- DLTPNLGRP (Delete Panel Group)
- DLTSCHIDX (Delete Search Index)
- DSPMNUA (Display Menu Attributes)
- GO (Go to Menu)
- RMV SCHIDX (Remove Search Index Entry)
- STRSCHIDX (Start Search Index)
- WRKSCHIDX (Work Search Index Entry)

For detailed information on the CL commands, see the *CL Reference*.

Using an Application Programming Interface (API)

The UIM provides several API services. The service calls to the UIM consist of the following:

- Application services
- Variable pool services
- List services
- Display services
- Print services

The application services consist of the following:

- Open Display Application (QUIOPNDA)
- Open Print Application (QUIOPNPA)
- Close Application (QUICLOA)

The variable pool services consist of the following:

- Get Dialog Variable (QUIGETV)
- Put Dialog Variable (QUIPUTV)

The list services consist of the following:

- Add List Entry (QUIADDLE)
- Add List Multiple Entries (QUIADDLM)
- Get List Entry (QUIGETLE)
- Get List Multiple Entries (QUIGETLM)
- Update List Entry (QUIUPDLE)
- Remove List Entry (QUIRMVLE)
- Delete List (QUIDLTL)
- Set List Attributes (QUISETLA)
- Retrieve List Attributes (QUIRTVLA)

The display services consist of the following:

- Display Panel (QUIDSPP)

- Display Help (QUHDSPH)
- Add Pop-up Window (QUIADDPW)
- Remove Pop-up Window (QUIRMVPW)
- Set Screen Image (QUISETSC)

The print services consist of the following:

- Print Panel (QUIPRTP)
- Add Print Application (QUIADDPWA)
- Remove Print Application (QUIRMVPA)

For details on the APIs, see the *System Programmer's Interface Reference*.

Defining a Menu Object Using UIM

Using the UIM, you can create a *UIM type of menu object. The menu object contains the definition of a menu panel with one or more options. To create a *UIM type of menu, do the following.

1. Create a member in a source physical file.
2. Enter the UIM tag source to describe the menu using a source editor, such as the Source Entry Utility (SEU). An example menu exists in member T0011MN2 in file QATTUIM in library QUSRTOOL. You can copy this example to use as a template to create your own menu.
3. Use the Create Menu (CRTMNU) command to create the menu object using the tag source as input. Here is an example of using the CRTMNU command.

```
CRTMNU MENU(MYLIB/MYMENU) TYPE(*UIM) SRCFILE(MYLIB/QMNUSRC)
```

The source member defaults to the name of the menu being created.

Creating a Menu Panel

The panel shown in Figure 16-1 on page 16-7 is an example menu. If you need more information on creating help for a menu area, see "Help in a Menu Area" on page 19-4.

T0011MN2 **1** Example Menu **2** **3** System: RCHAS767

Select one of the following: **4**

1. Work with members in a file **5**
 2. Work with record definitions

Selection or command **6**

====> _____

F3=Exit F4=Prompt F9=Retrieve F12=Cancel **7**
 (C) COPYRIGHT YOUR COMPANY NAME HERE, 1992. **8**

Figure 16-1. An Example Menu

The reference numbers in the example menu do not appear on the display. They are shown for illustration purposes and also appear in the UIM tag source shown in “Source for Example Menu” on page 16-9. These reference numbers show the portions of the source which define text and information that appear on the menu.

- 1** The panel identifier is defined by declaring the UIM-defined Z-variable, ZMENU, using the VAR tag and specifying the Z-variable to be used as the panel identifier on the PANELID attribute of the PANEL tag.
- 2** The panel title is defined as text following the period of the PANEL tag.
- 3** The system name is shown because the TOPSEP=SYSNAM attribute was specified on the PANEL tag.
- 4** The top instruction line is defined as text following the period of the top instruction (TOPINST) tag.
- 5** Each option on the menu is defined using the menu item (MENU) tag. The option number is defined using the OPTION attribute and the text following the option number is defined as text following the MENU tag.
- 6** The command line is defined using the command line (CMDLINE) tag. The command line prompt text is defined as text following the CMDLINE tag. The UIM automatically provides the arrow (====>) for every command line.

An option line can be defined by using the option line (OPTLINE) tag instead of the CMDLINE tag. In this case, the user enters option numbers, but is not allowed to enter system commands.
- 7** Each function key is defined using a key list item (KEYI) tag. The text, including the function key name, is defined as text following the period of the KEYI tag.

All function keys for a panel are defined by placing the KEYI tags between a key list (KEYL) and EKEYL tag. The name specified on the NAME attribute of the KEYL tag is also specified on the KEYL attribute of the PANEL tag.

Some function keys, such as the Enter key, do not have text specified for the KEYI tag. In this case, no text appears on the display. However, all function keys must be defined using the KEYI tag so the UIM knows what action is assigned for each key and what help module should be displayed when help is displayed for the function keys.

- 8** The copyright message is defined as text following the period of the copyright (COPYR) tag. The copyright message is displayed once when the user initially sees the menu. The message is not shown when the menu is redisplayed after processing an option or command.

This example menu is not defined as scrollable because it contains only two options. If you need to define a scrollable menu, change SCROLL=NO to SCROLL=YES on the MENU tag and add one menu item (MENUI) tag for each additional menu option. You also need to define a new help module for each menu option.

Required Tags for a Menu Panel

Figure 16-2 shows the required tags for creating a UIM menu panel. For an example of the required and optional tags, see "Source for Example Menu" on page 16-9.

Note: The tags in Figure 16-2 require attributes. These attributes are not shown. Without these attributes, the example in Figure 16-2 will not compile. For a description of the required attributes for these required tags, see Appendix A, "UIM Panel Group Definition Language."




Figure 16-2. Required UIM Tags for a Menu Panel

Source for Example Menu

This is a listing of the tag source for the menu shown in Figure 16-1 on page 16-7. The entire source can be found in member T0011MN2 in source file QATTUIM in library QUSRTOOL.

```
. * -----
. *
. * Beginning of menu source.
. *
. * Enable access to OS/400 index search when help is displayed for
. * this menu.
. * -----
:PNLGRP    SCHIDX=qhss1
           DFTMSGF=t0011msgf2
           SUBMSGF=t0011msgf2.

. *
. * -----
. * Copyright statement appears when the menu is initially displayed.
. * -----
:COPYR.    8
(C) COPYRIGHT YOUR COMPANY NAME HERE, 1992.
. *
. * -----
. * UIM Z-variable to be used as the panel identifier
. * -----
:VAR       NAME=ZMENU.    1
. *
. * -----
. * Define keys for the menu
. * -----
:KEYL      NAME=menukeys  7
           HELP=key|.
:KEYI      KEY=F1
           HELP=helpf1
           ACTION=HELP.
:KEYI      KEY=F3
           HELP=exit
           ACTION='EXIT SET'
           VARUPD=NO.
F3=Exit    7
:KEYI      KEY=F4
           HELP=prompt
           ACTION=PROMPT.
F4=Prompt
:KEYI      KEY=F9
           HELP=retrieve
           ACTION=RETRIEVE.
F9=Retrieve
:KEYI      KEY=F12
           HELP=cancel
           ACTION='CANCEL SET'
           VARUPD=NO.
F12=Cancel
:KEYI      KEY=F24
           HELP=morekeys
           ACTION=MOREKEYS.
F24=More keys
:KEYI      KEY=ENTER
           HELP=enter
           ACTION=ENTER.
:KEYI      KEY=HELP
           HELP=help
```

```

ACTION=HELP.
:KEYI    KEY=HOME
        HELP=home
        ACTION=HOME.
:KEYI    KEY=PAGEDOWN
        HELP=pagedown
        ACTION=PAGEDOWN.
:KEYI    KEY=PAGEUP
        HELP=pageup
        ACTION=PAGEUP.
:KEYI    KEY=PRINT
        HELP=print
        ACTION=PRINT.
:EKEYL.
.*
.* -----
.* Define Example Menu panel
.* -----
:PANEL    NAME=xmpmenu
        HELP='menu/help'
        KEYL=menukeys
        ENTER='MSG CPD9817 QCPFMSG'
        PANELID=ZMENU
        TOPSEP=SYSNAM.
Example Menu
.*
.* -----
.* Define the menu area
.* -----
:MENU     DEPTH='*'
        SCROLL=NO
        BOTSEP=SPACE.
:TOPINST.Select one of the following:
.*
.* -----
.* Specify the action to be taken for each option
.* -----
:MENUI    OPTION=1
        ACTION='CMD ?t0011cm2'
        HELP='menu/option1'.
Work with members in a file
.*
:MENUI    OPTION=2
        ACTION='CMD ?t0011cm3'
        HELP='menu/option2'.
Work with record definitions
.*
:EMENU.
.*
.* -----
.* Use a command line and allow commands and option numbers
.* -----
:CMDLINE  SIZE=LONG.
Selection or command
.*
:EPANEL.
.*
.* -----
.* Define help modules for the menu panel
.* -----
:HELP     NAME=keyl.
Function Keys - Help
:XH3.Function keys

```

```

:EHLP.
.*
:HELP      NAME=helpf1.
:PARML.
:PT.F1=Help
:PD.
Provides additional information about using the display or a
specific field on the display.
:EPARML.
:EHLP.
.*
:HELP      NAME=exit.
:PARML.
:PT.F3=Exit
:PD.
Ends the current task and returns to the display from which the
task was started.
:EPARML.
:EHLP.
.*
:HELP      NAME=prompt.
:PARML.
:PT.F4=Prompt
:PD.
Provides assistance in entering or selecting a command.
:EPARML.
:EHLP.
.*
:HELP      NAME=retrieve.
:PARML.
:PT.F9=Retrieve
:PD.
Displays the last command you entered on the command line and
any parameters you included. Pressing this key once, shows the
last command you ran. Pressing this key twice, shows the
command you ran before that and so on.
:EPARML.
:EHLP.
.*
:HELP      NAME=cancel.
:PARML.
:PT.F12=Cancel
:PD.
Returns to the previous menu or display.
:EPARML.
:EHLP.
.*
:HELP      NAME=morekeys.
:PARML.
:PT.F24=More keys
:PD.
Shows additional function keys.
:EPARML.
:EHLP.
.*
:HELP      NAME=enter.
:PARML.
:PT.Enter
:PD.
Submits information on the display for processing.
:EPARML.
:EHLP.
.*
:HELP      NAME=help.

```

```

:PARML.
:PT.Help
:PD.
Provides additional information about using the display.
:EPARML.
:EHELP.
.*
:HELP      NAME=home.
:PARML.
:PT.Home
:PD.
Goes to the menu that was shown after you signed on the system.
This menu is either the initial menu defined in your user
profile or the menu you requested from the Sign-On display.
:EPARML.
:EHELP.
.*
:HELP      NAME=pagedown.
:PARML.
:PT.Page Down (Roll Up)
:PD.
Moves forward to show additional information for this display.
:EPARML.
:EHELP.
.*
:HELP      NAME=pageup.
:PARML.
:PT.Page Up (Roll Down)
:PD.
Moves backward to show additional information for this display.
:EPARML.
:EHELP.
.*
:HELP      NAME=print.
:PARML.
:PT.Print
:PD.
Prints information currently shown on the display.
:EPARML.
:EHELP.
.*
:HELP      NAME='menu/help'.
Example Menu - Help
:P.
The Example Menu shows an example of a menu created using the UIM.
:XH3.
How to Use a Menu
:P.
To select a menu option, type the option number and press Enter.
:P.
To run a command, type the command and press Enter. For assistance
in selecting a command, press F4 (Prompt) without typing anything.
For assistance in entering a command, type the command and press F4
(Prompt). To see a previous command you entered, press F9
(Retrieve).
:P.
To go to another menu, use the Go to Menu (GO) command. Type GO
followed by the menu ID, then press the Enter key. For example, to
go to the User Tasks (USER) menu, type GO USER and press the Enter
key. The menu ID is shown in the upper left corner of the menu.
For assistance in entering the GO command, type GO and press F4
(Prompt). If you do not know the entire menu name you can use a
generic name. For example, GO US* will show a list of all menus
that start with US.

```



```

:EHELP.
.*
:HELP      NAME='menu/option1'.
Option 1 - Help
:XH3.Option 1. Work with members in a file
:P.
Select this option to work with the members in a file. You will be
prompted for the name of the file.
:EHELP.
.*
:HELP      NAME='menu/option2'.
Option 2 - Help
:XH3.Option 2. Work with record definitions
:P.
Select this option to work with record definitions for a file.
You will be prompted for the name of the file.
:EHELP.
.*
.*
.*
.* -----
.* End of menu source
.* -----
:EPNLGRP.

```

Defining a Panel Group Object Using UIM

Using the UIM, you can create a panel group object. The panel group object can contain the definitions for dialog variables, lists, panels and help modules. To create a panel group object, do the following.

1. Create a member in a source physical file.
2. Enter the UIM tag source to describe the panel group using a source editor such as the Source Entry Utility (SEU). An example panel group exists in member T0011PN2 in file QATTUIM in library QUSRTOOL. You can copy this example to use as a template to create your own panel group.
3. Use the Create Panel Group (CRTPNLGRP) command to create the panel group object using the tag source as input. Here is an example of using the CRTPNLGRP command.

```
CRTPNLGRP PNLGRP(MYLIB/MYPNLGRP) SRCFILE(MYLIB/QPNLSRC)
```

The source member defaults to the name of the panel group being created.

Creating a List Panel

Any of the "Work with..." panels are list panels. In this example, the Work with File Members panel is used. Defining the list panel is similar to defining a subfile in DDS, but the UIM determines the appearance of the panel.

The panel shown in Figure 16-3 on page 16-14 shows an example of a mixed panel with a list area. The panel is mixed because it contains two types of areas: a data presentation area at the top and a list area at the bottom.

The data presentation area at the top consists of the fields which identify the file and library name. The list area begins with the instruction line, *Type options, press Enter* and ends with the scroll information (*More...*).

In this example, the panel contains a special type of list area called an action list. An action list is a list which contains an option column. The user types in allowed option numbers to perform actions against the object represented by the entry in the list. If you need more information on creating list panel help, see "Help in a List Area" on page 19-3.

Work with File Members 1

File XXXXXXXX F4 for list 2
 Library XXXXXXXX library, *CURLIB, *LIBL

Type options, press Enter. 3
 3=Copy 4=Remove 5=Display 7=Reorganize 8=Member description 4
 9=Clear

Opt	Member	Type	Text
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX
-	XXXXXXXXXX	XXXXXXXXXX	XX

7 More...

Parameters for options 3 and 5 or command 8
 ===> _____
 F3=Exit F4=Prompt F9=Retrieve F11=Display names only F12=Cancel 9

Figure 16-3. Example List Panel

The panel shown in Figure 16-4 on page 16-15 is an alternate view shown when the user presses F11 (Display names only) on the panel shown in Figure 16-3. The alternate view shown here uses a multiple-column layout. The panel is divided into four layout columns of equal size. The *Opt* and *Member* columns appear in each layout column. The alternate view shows four times as many list entries as the original view, but does not show the *Type* and *Text* columns for each entry.

Work with File Members 1

File XXXXXXXXX F4 for list 2
Library XXXXXXXXX library, *CURLIB, *LIBL

Type options, press Enter. 3
3=Copy 4=Remove 5=Display 7=Reorganize 8=Member description 4
9=Clear

Opt	Member	Opt	Member	Opt	Member	Opt	Member	5
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	7 More...
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	
-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	-	XXXXXXXXXX	

Parameters for options 3 and 5 or command 8
====>

F3=Exit F4=Prompt F9=Retrieve F11=Display descriptions F12=Cancel 9

Figure 16-4. Example of Alternate View of List

The reference numbers in the example panel do not appear on the display. They are shown for illustration purposes and also appear in the UIM tag source shown in “Source for Example List Panel” on page 16-18. These reference numbers show which portions of the source define text and information which appears on the panel.

- 1 The panel title is defined as text following the period of the display panel (PANEL) tag.
- 2 The text for the file and library name is defined as text following the period of the data item (DATAI) tag. The file name and library name are dialog variable values. Each dialog variable is defined using the variable definition (VAR) tag. The name of the dialog variable is specified on the VAR attribute of the DATAI tag. The possible choices text for each input field is defined as text following the period of the data item choices (DATAC) tag.

The file name and library are formatted as a qualified object name because GRPSEP=QINDENT is specified on the data group (DATAGRP) tag which surrounds the two DATAI tags.

The dialog variables for the file name and library name are defined using the VAR tags at A and B, respectively, shown on page 16-19.
- 3 The instruction line is defined as text following the period of the top instruction (TOPINST) tag.
- 4 Each list option is defined using the list action (LISTACT) tag. The text, including the option number with the equal sign, is defined as text following the period of the LISTACT tag.
- 5 The column heading for each column is defined as text following the period of the list column (LISTCOL) tag. The VAR attribute of the LISTCOL tag identifies the name of the dialog variable whose value is displayed under the column heading.

The dialog variable name specified, must be defined using the VAR tag. The dialog variable name must also be specified on the VARS attribute of the list definition (LISTDEF) tag for the list appearing in the panel.

The dialog variables for the option, member name, member type, and description text are defined using the VAR tags at **C**, **D**, **E**, and **F**, respectively, shown on page 16-19.

The names of these variables also appear in the VARS attribute of the LISTDEF tag at **G** shown on page 16-21. The name of the list definition must be specified on the LISTDEF attribute of the list area (LIST) tag at **H**, shown on page 16-24.

- 6** The extended action entry that appears immediately below the column headings is defined by specifying EXTACT=YES on the LIST tag. Each column which has an input field in the extended action entry must specify EXTACT=YES on the LISTCOL tag.

The extended action entry allows the user to perform actions without having to scroll to a specific entry in the list.

Each list option defined by the LISTACT tag, specifies whether the action is allowed to be performed against the extended action entry, the list entries appearing below the extended action entry, or both. This specification is made using the ACTFOR attribute of the LISTACT tag.

- 7** The scroll information, More... and Bottom, are shown because the list area is defined as scrollable because the SCROLL attribute defaults to YES on the LIST tag.

- 8** The command line is defined using the command line (CMDLINE) tag. The command line prompt text is defined as text following the period of the CMDLINE tag. The UIM automatically provides the arrow (==>) for every command line.

The command line can be used to enter parameters for list options. Before processing list options, the UIM places the contents of the command line into a dialog variable. The dialog variable can be:

- Substituted into a CL command specified as the action to perform on a LISTACT tag
- Used by an exit program specified as the action to perform on the LISTACT tag
- Used by the application program when it is performing the actions for the list

The dialog variable used to contain parameters from the command line is defined using the VAR tag at **I**, shown on page 16-20. It is also specified on the PARMS attribute of the list area (LIST) tag at **J**, shown on page 16-24. The UIM places the contents of the command line in the dialog variable specified by the PARMS attribute before beginning list option processing.

Then the dialog variable is used as a substitution variable in a command string on a LISTACT tag at **K**, shown on page 16-24.

- 9** Each function key is defined using the key list (KEYL) tag. The text, including the function key name, is defined as text following the period of the KEYI tag.

All function keys are defined by placing the KEYI tags between the key list

(KEYL) and EKEYL tags. The name specified on the NAME attribute of the KEYL tag is also specified on the KEYL attribute of the PANEL tag.

Some function keys, such as Enter, do not have text specified for the KEYI tag. In this case, no text appears on the display. However, all function keys must be defined using the KEYI tag so the UIM knows what action is assigned to each key and what help module to use when help is displayed for the function keys.

Required Tags for a List Panel

Figure 16-5 shows the required tags for creating a UIM list panel. For an example of the required and optional tags, see “Source for Example List Panel” on page 16-18.

Note: The tags in Figure 16-5 require attributes. These attributes are not shown. Without these attributes, the example in Figure 16-5 will not compile. For a description of the required attributes for these required tags, see Appendix A, “UIM Panel Group Definition Language.”




Figure 16-5. Required UIM Tags for a List Panel

Source for Example List Panel

This is a partial listing of member T0011PN2 in source file QATTUIM in library QUSRTOOL.

```
. * -----
. *
. * Beginning of panel group source.
. *
. * Enable access to OS/400 index search when help is displayed from
. * panels in this panel group.
. * -----
:PNLGRP    SCHIDX=qhss1
          DFTMSGF=t0011msgf2
          SUBMSGF=t0011msgf2.

. *
. * The import tag specifies that all help is to be found
. * in panel group T0011HL2 searching the library list.
:IMPORT    NAME='*'
          PNLGRP=t0011h12.

. *
. * -----
. * Define all variable classes
. * -----
. * -----
. * Option
. * Note: Need WIDTH=1 to preserve column alignment on confirmation panel.
:CLASS     NAME=optc1
          BASETYPE='ACTION'
          WIDTH=1.
:ECLASS.

. * -----
. * Object name
:CLASS     NAME=namec1
          BASETYPE='OBJNAME 10'.
:ECLASS.

. * -----
. * Library name
:CLASS     NAME=libc1
          BASETYPE='OBJNAME 10'.

:TL.
:TI        VALUE=' '*LIBL' '*LIBL
:TI        VALUE=' '*CURLIB' '*CURLIB
:ETL.
:ECLASS.

. * -----
. * File attribute
:CLASS     NAME=attrc1
          BASETYPE='CHAR 10'
          CASE=UPPER.
:ECLASS.

. * -----
. * Descriptive text
:CLASS     NAME=textc1
          BASETYPE='IGC 50'
          SUBST=QUOTED.
:ECLASS.

. * -----
. * Source type
:CLASS     NAME=srctypc1
          BASETYPE='CHAR 10'.
:ECLASS.
:
:
Additional CLASS tags in member T0011PN2 are not shown here
:
```

```

.* -----
.* Command line parameters
:CLASS    NAME=parmc1
          BASETYPE='CHAR 255'.
:ECLASS.

.* -----
.* Exit program specification for CALL dialog command
:CLASS    NAME=exitc1
          BASETYPE='CHAR 130'.
:ECLASS.

.* -----
.* View number
:CLASS    NAME=vwnumc1
          BASETYPE='BIN 15'.
:ECLASS.

.* -----
.* Classes for pad variables in variable record definitions.
:CLASS    NAME=pad1c1
          BASETYPE='CHAR 1'.
:ECLASS.
:CLASS    NAME=pad2c1
          BASETYPE='CHAR 2'.
:ECLASS.
:CLASS    NAME=pad10c1
          BASETYPE='CHAR 10'.
:ECLASS.
:CLASS    NAME=pad13c1
          BASETYPE='CHAR 13'.
:ECLASS.
:CLASS    NAME=pad48c1
          BASETYPE='CHAR 48'.
:ECLASS.
:CLASS    NAME=pad50c1
          BASETYPE='CHAR 50'.
:ECLASS.

.* -----
.* Define all dialog variables
.* -----
.* -----
.* Variables for file and library
.* -----
.* -----
.* File name
:VAR      NAME=file A
          CLASS=namec1.
.* -----
.* Library name
:VAR      NAME=lib B
          CLASS=libc1.
.* -----
.* attributes
:VAR      NAME=fattr
          CLASS=attrc1.
.* -----
.* -----
.* Variables for list of members
.* -----
.* -----
.* option for list of members
:VAR      NAME=mopt C

```

```

        CLASS=optcl.
.* -----
.* Object name
:VAR      NAME=mbr D
        CLASS=namecl.
.* -----
.* member type
:VAR      NAME=mtype E
        CLASS=attrcl.
.* -----
.* Descriptive text
:VAR      NAME=mtext F
        CLASS=textcl.
        :
        Additional VAR tags in member T0011PN2 are not shown here
        :
.*
.* -----
.* Variable for command line parameters
.* -----
.*
.* Command line parameters
:VAR      NAME=parms I
        CLASS=parmcl.
.*
.* -----
.* Variables for specifying CALL/exit programs
.* -----
.*
.* Program to call for all UIM exits
:VAR      NAME=exitpgm
        CLASS=exitcl.
.*
.* -----
.* Variables for controlling list views
.* -----
.*
.* View number for list of members
:VAR      NAME=mbrview
        CLASS=vwnumcl.
        :
        Additional VAR tags in member T0011PN2 are not shown here
        :
.*
.* -----
.* Variables for padding in variable record definitions.
.* Padding is needed in variable records so the layout
.* of the record matches a list format returned from
.* an API. The pad variables are used as placeholders for
.* variables not used in the API format or for reserved space
.* in the API format.
.* -----
:VAR      NAME=pad1
        CLASS=pad1cl.
:VAR      NAME=pad2
        CLASS=pad2cl.
:VAR      NAME=pad10
        CLASS=pad10cl.
:VAR      NAME=pad13
        CLASS=pad13cl.
:VAR      NAME=pad48
        CLASS=pad48cl.
:VAR      NAME=pad50

```



```

CLASS=pad50cl.

.*
.* -----
.* Define a variable record for file, library and file attribute
.* -----
:VARRCD  NAME=filelib
        VARS='file lib fattr'
        NOGET='fattr'
        .

.*
.* -----
.* Define a variable record for exit program
.* -----
:VARRCD  NAME=exitprog
        VARS='exitpgm'
        .

.*
.* -----
.* Define a variable record for list of members.
.* The layout of this record is designed to match the
.* List Database File Members API (QUSLMBR) format name MBRL0200.
.* -----
:VARRCD  NAME=mbrl0200
        VARS='mbr mtype pad13 pad13 mtext'
        NOPUT='pad13'
        NOGET='mtype pad13 mtext'
        .

:
Additional VARRCD tags in member T0011PN2 are not shown here
:

.*
.* -----
.* Define a list of members
.* -----
:LISTDEF NAME=mbrlist
        VARS='mopt mbr mtype mtext'
        MSGID=USR0101.
        .

:
Additional LISTDEF tags in member T0011PN2 are not shown here
:

.*
.* -----
.* Define all conditions
.* -----
.* -----
.* Condition for physical files
:COND    NAME=pf
        EXPR='fattr="PF          "'.
.* -----
.* Conditions for views of members list
:COND    NAME=mbrview1
        EXPR='mbrview=0'.
:COND    NAME=mbrview2
        EXPR='mbrview=1'.
        .

:
Additional COND tags in member T0011PN2 are not shown here
:

.*
.* -----
.* Define truth table to specify that mbrview1 and mbrview2
.* are mutually exclusive conditions
.* This will cause UIM to reserve only one line of function

```

```

.* keys on the work with members panel
.* -----
:TT      NAME=mbrtt
          CONDS='mbrview1 mbrview2'.
:TTROW   VALUES=' 1      0  '.
:TTROW   VALUES=' 0      1  '.
:ETT.
:
Additional TT tags in member T0011PN2 are not shown here
:
:
All MBAR tags in member T0011PN2 are not shown here
:
.*
.*
.* -----
.* Define keys for work with members panel
.* -----
:KEYL    NAME=mbrkeys 9
          HELP=keyl.
:KEYI    KEY=F1
          HELP=helpf1
          ACTION=HELP.
:KEYI    KEY=F3
          HELP=exit
          ACTION='EXIT SET'
          VARUPD=NO.

F3=Exit
:KEYI    KEY=F4
          HELP=prompt
          ACTION=PROMPT
          PRIORITY=30.

F4=Prompt
:KEYI    KEY=F9
          HELP=retrieve
          ACTION=RETRIEVE
          PRIORITY=35.

F9=Retrieve
:KEYI    KEY=F11
          HELP=mbrviewname
          ACTION=CHGVIEW
          PRIORITY=25
          COND=mbrview1.

F11=Display names only
:KEYI    KEY=F11
          HELP=mbrviewdesc
          ACTION=CHGVIEW
          PRIORITY=25
          COND=mbrview2.

F11=Display descriptions
:KEYI    KEY=F12
          HELP=cancel
          ACTION='CANCEL SET'
          VARUPD=NO.

F12=Cancel
:KEYI    KEY=F24
          HELP=morekeys
          ACTION=MOREKEYS.

F24=More keys
:KEYI    KEY=ENTER
          HELP=enter
          ACTION=ENTER.
:KEYI    KEY=HELP
          HELP=help

```

```

        ACTION=HELP.
:KEYI    KEY=PAGEDOWN
        HELP=pagedown
        ACTION=PAGEDOWN.
:KEYI    KEY=PAGEUP
        HELP=pageup
        ACTION=PAGEUP.
:KEYI    KEY=PRINT
        HELP=print
        ACTION=PRINT.
:EKEYL.
:
Additional KEYL tags in member T0011PN2 are not shown here
:
.*
.*
.* -----
.* Define Work with Members panel
.* -----
:PANEL    NAME=wrkmbr
        HELP='wrkmbr/'
        KEYL=mbrkeys 9
        TT=mbrtt
        ENTER='RETURN 500'
        TOPSEP=SPACE.
Work with File Members 1
.*
.* -----
.* Define a data presentation area to display the
.* library/file name whose members are listed.
.* -----
:DATA     DEPTH=3
        SCROLL=NO
        LAYOUT=1
        BOTSEP=SPACE
        COMPACT
        .
.* -----
.* Divide the layout width into two columns.
.* The first column is for the prompt text with leader dots.
.* The second column is for the variable values.
:DATACOL  WIDTH=22.
:DATACOL  WIDTH=12.
:DATACOL  WIDTH='*'.
.* -----
.* Display qualified file name
:DATAGRP  GRPSEP=QINDENT
        HELP='wrkmbr/filelib'
        COMPACT
        .
:DATAI    VAR=file 2
        USAGE=INOUT
        PROMPT='CALL exitpgm'
        .
File
:DATAC.F4 for list
:DATAI    VAR=lib
        USAGE=INOUT
        .
Library
:DATAC.library, *CURLIB, *LIBL
:EDATAGRP.
.*
:EDATA.

```

```

.*
.* -----
.* Define the list area
.* -----
:LIST      DEPTH='*' 7
           LISTDEF=mbrlist H
           ACTOR=UIM
           EXTACT=YES 6
           MAXHEAD=4
           MAXACTL=3
           VIEW=mbrview
           PARMS=parms J
           BOTSEP=SPACE.
:TOPINST.Type options, press Enter. 3
.*
.* -----
.* Specify the action to be taken for each option
.* -----
:LISTACT   OPTION=3
           ACTFOR=BOTH 6
           NOCMD=PROMPT
           NOEXT=PROMPT
           HELP='wrkmbr/cpyf'
           ENTER='CMD CPYF ?*FROMFILE(&lib./&file.)'
           ENTER=' ?*FROMMBR(&mbr.) &parms.' K
           PROMPT='CMD ?CPYF ?*FROMFILE(&lib./&file.)'
           PROMPT=' ?*FROMMBR(&mbr.) &parms.' K
           EXTENTER='CMD ?CPYF ?*FROMFILE(&lib./&file.)'
           EXTENTER=' ??FROMMBR(&mbr.) &parms.' K
           EXTPROMPT='CMD ?CPYF ?*FROMFILE(&lib./&file.)'
           EXTPROMPT=' ??FROMMBR(&mbr.) &parms.' K
3=Copy 4
.*
:LISTACT   OPTION=4
           ACTFOR=LISTE
           HELP='wrkmbr/rmvm'
           ENTER='CMD RMVM FILE(&lib./&file.) MBR(&mbr.)'
           PROMPT='CMD ?RMVM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'
           USREXIT='CALL exitpgm'.
4=Remove
.*
:LISTACT   OPTION=5
           COND=pf
           ACTFOR=BOTH
           NOEXT=PROMPT
           HELP='wrkmbr/dsppfm'
           ENTER='CMD DSPPFM FILE(&lib./&file.) MBR(&mbr.) &parms.'
           PROMPT='CMD DSPPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.) &parms.'
           EXTPROMPT='CMD DSPPFM ?*FILE(&lib./&file.) ??MBR(&mbr.) &parms.'.
5=Display
.*
:LISTACT   OPTION=7
           COND=pf
           ACTFOR=BOTH
           HELP='wrkmbr/rgzm'
           ENTER='CMD RGZPFM FILE(&lib./&file.) MBR(&mbr.)'
           PROMPT='CMD ?RGZPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'.
7=Reorganize
.*
:LISTACT   OPTION=8
           ACTFOR=BOTH
           HELP='wrkmbr/dspfd'
           ENTER='CALL exitpgm'

```

```

        PROMPT='CALL exitpgm'.
8=Member description
.*
:LISTACT  OPTION=9
        COND=pf
        ACTFOR=LISTE
        HELP='wrkmbbr/clrm'
        ENTER='CMD CLRPFM FILE(&lib./&file.) MBR(&mbr.)'
        PROMPT='CMD ?CLRPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'.

9=Clear
.*
.*
.* -----
.* Define the columns and headings to display
.* -----
:LISTCOL  VAR=mopt
        USAGE=INOUT
        EXTRACT=YES 6
        HELP='wrkmbbr/option'
        MAXWIDTH=6.

Opt 5
:LISTCOL  VAR=mbr
        USAGE=OUT
        EXTRACT=YES
        HELP='wrkmbbr/mbr'
        MAXWIDTH=10.

Member
:LISTCOL  VAR=mtype
        USAGE=OUT
        HELP='wrkmbbr/type'
        MAXWIDTH=10.

Type
:LISTCOL  VAR=mtxt
        USAGE=OUT
        HELP='wrkmbbr/text'
        MAXWIDTH='*'.

Text
.*
.* -----
.* Define multiple views for F11 to toggle between
.* -----
:LISTVIEW COLS='mopt mbr mtype mtxt'.
:LISTVIEW COLS='mopt mbr' layout=4.
.*
:ELIST.
.*
.* -----
.* Use a command line and allow parameters to be given
.* -----
:CMDLINE  SIZE=SHORT. 8
Parameters for options 3 and 5 or command
.*
:EPANEL.
:
Additional PANEL tags in member T0011PN2 are not shown here
:
.*
.* -----
.* End of panel group source
.* -----
:EPNLGRP.

```

Application Programming for a List Panel

An example of an application program to display the list panel shown in Figure 16-3 on page 16-14 can be found in member T0011CP2 in source file QATTSYSC in library QUSRTOOL. This is a C/400 program which calls the appropriate UIM application programming interfaces (APIs) to display the panel.

To write a program in any language to display the example list panel, the program should do the following:

1. Call the Open Display Application (QUIOPNDA) API to open the panel group. The panel group must already be created using the Create Panel Group (CRTPNLGRP) command.

2. Set up a buffer containing the values for the following dialog variables:

FILE A CHAR 10 variable which is the name of the file.

LIB A CHAR 10 variable which is the name of the library where the file resides.

FATTR A CHAR 10 variable which is the file attribute of the file. This variable is used to condition on list options which are only allowed for physical files.

3. Call the Put Dialog Variable (QUIPUTV) API to change the contents of the dialog variables using variable record FILELIB and the buffer initialized in the previous step.

4. Set up a buffer containing a value for the following dialog variable:

EXITPGM A CHAR 130 variable which identifies the extended program model (EPM) environment and entry point to be called as a UIM exit program. For non-EPM languages, such as RPG and Cobol, this BASETYPE attribute of the CLASS tag used to define the EXITPGM dialog variable must be changed to a CHAR 20 dialog variable.

For information on how this dialog variable must be set, see the description of the CALL dialog command in Appendix B, "UIM Dialog Commands" on page B-1.

5. Call the Put Dialog Variable (QUIPUTV) API to change the contents of the dialog variable using variable record EXITPROG and the buffer initialized in the previous step.

6. Create a user space that will receive a list of members in a file using the Create User Space (QUSCRTUS) API. The members in a file are retrieved using the List Database File Members (QUSLMBR) API. If the application programming language supports pointers, use the Retrieve Pointer to User Space (QUSPTRUS) API to obtain a pointer to the contents of the user space. This lets the application program directly manipulate the data. Otherwise, use the Retrieve User Space (QUSRTVUS) API to obtain the contents of the user space. For a description of these APIs, see the *System Programmer's Interface Reference*.

7. For every member in the file to be displayed, do the following. A list of the members in a file can be retrieved using the List Database File Members (QUSLMBR) API. For a description of this API, see the *System Programmer's Interface Reference*.

- a. Set up a buffer containing values for the following dialog variables:

MBR	A CHAR 10 variable which is the member name.
MTYPE	A CHAR 10 variable which is the member type.
PAD13	A CHAR 13 reserved space in the buffer.
PAD13	A CHAR 13 reserved space in the buffer.
MTEXT	A CHAR 50 variable which is the descriptive text for the member.

Note: The layout of this buffer is designed to match the layout of the entries in the user space returned by the QUSLMBR API using the MBRL0200 format. Therefore, instead of setting up a buffer, the application program can pass the buffer as it exists in the user space.

The two PAD13 variables are used to tell the UIM to ignore two variables in the MBRL0200 format returned by the QUSLMBR API. The variables are the creation date and time and the last source change data and time.

- b. Call the Add List Entry (QUIADDLE) API to add a list entry to the list named MBRLIST using variable record MBRL0200 and the buffer initialized in the previous step.
8. Call the Display Panel (QUIDSPP) API to display panel WRKMBR. The UIM returns control to the application when one of the following occurs:
 - The user presses the Enter key without typing any list options or a command on the command line. The program variable passed as the function requested parameter to the QUIDSPP API is set to 500. This is done because ENTER='RETURN 500' is specified on the PANEL tag which defines the WRKMBR panel.
 - The user presses the F12 (Cancel) key. The program variable passed as the function requested parameter to the QUIDSPP API is set to -8. This is the value defined for the CANCEL dialog command.
 - The user presses the F3 (Exit) key. The program variable passed as the function requested parameter to the QUIDSPP API is set to -4. This is the value defined for the CANCEL dialog command.
 9. Call the Close Application (QUICLOA) API to close the UIM application. This frees up the system resources used by the UIM application.

Creating a Confirmation List Panel

Options on an action list panel that perform destructive operations should use a confirmation panel to allow the user to confirm or cancel the request before it is performed. A confirmation panel should be provided for actions such as *4=Remove* and *9=Clear* shown in the example panel in Figure 16-3 on page 16-14.

An example of a confirmation panel is shown in Figure 16-6 on page 16-28. This confirmation panel is used when the user types option 4 on the panel shown in Figure 16-3 on page 16-14.

[illegible]

Figure 16-6. Example Confirmation List Panel

The confirmation panel appears similar to the action list panel with the following exceptions:

- The instructions tell the user to confirm or cancel the option.
- The displayed list is for output only. The user cannot change any of the option numbers.
- The F3 (Exit) key is not allowed from a confirmation panel.
- There is no command line on a confirmation panel.

When the user presses the F11 key to change to a different view, the view of the action list panel is changed when it is redisplayed. This is done because the same dialog variable is specified on the VIEW attribute of the LIST tag for both the action list panel and the confirmation panel.

Required Tags for a Confirmation List Panel

The required tags for a confirmation list panel are basically the same as those required for a list panel which are described in Figure 16-5 on page 16-17. However, the LISTACT tag is not required.

Source for Example Confirmation Panel

To define this confirmation panel, additional source needs to be added to the source shown in “Source for Example List Panel” on page 16-18. The following are excerpts from member T0011PN2 in source file QATTUIM in library QUSRTOOL. First, a new list definition needs to be made. This list definition contains a copy of the list entries being confirmed. The confirmation list contains the same dialog variables as are contained in the list of members. The following list definition (LISTDEF) tag should be placed after the LISTDEF tag at **G**, shown on page 16-21.


```

.*
.* -----
.* Define a list of members for confirmation panels
.* -----
:LISTDEF NAME=mbrconf
          VARS='mopt mbr mtype mtext'.

```

Next, function keys need to be defined for the confirmation panel. Confirmation panels should not allow F3 (Exit). The following key list (KEYL) tag should be placed after the KEYL tag, shown in “Source for Example List Panel” on page 16-18.

```

.*
.* -----
.* Define keys for confirm remove of members
.* -----
:KEYL     NAME=mconfkeys
          HELP=keyl.
:KEYI     KEY=F1
          HELP=helpf1
          ACTION=HELP.
:KEYI     KEY=F11
          HELP=altview
          ACTION=CHGVIEW
          COND=mbrview1.
F11=Display names only
:KEYI     KEY=F11
          HELP=altview
          ACTION=CHGVIEW
          COND=mbrview2.
F11=Display descriptions
:KEYI     KEY=F12
          HELP=cancel
          ACTION='CANCEL SET'
          VARUPD=NO.
F12=Cancel
:KEYI     KEY=F24
          HELP=morekeys
          ACTION=MOREKEYS.
F24=More keys
:KEYI     KEY=ENTER
          HELP=enter
          ACTION=ENTER.
:KEYI     KEY=HELP
          HELP=help
          ACTION=HELP.
:KEYI     KEY=PAGEDOWN
          HELP=pagedown
          ACTION=PAGEDOWN.
:KEYI     KEY=PAGEUP
          HELP=pageup
          ACTION=PAGEUP.
:KEYI     KEY=PRINT
          HELP=print
          ACTION=PRINT.
:EKEYL.

```

The confirmation panel needs to be defined. The following source should be placed after the EPANEL tag, shown in “Source for Example List Panel” on page 16-18.

```
. *
. * -----
. * Define panel for confirm remove of members from WRKMBR panel
. * -----
: PANEL      NAME=confrmmv
              HELP='confrmmv/'
              KEYL=mconfkeys
              TT=mbrrtt
              ENTER='RETURN 100'
              TOPSEP=space.
Confirm Remove of Members
. *
. * -----
. * Define a data presentation area to display the
. * library/file name whose members are listed.
. * -----
: DATA      DEPTH=3
              SCROLL=NO
              LAYOUT=1
              BOTSEP=SPACE
              COMPACT
              .

. * -----
. * Divide the layout width into two columns.
. * The first column is for the prompt text with leader dots.
. * The second column is for the variable values.
: DATACOL    WIDTH=22.
: DATACOL    WIDTH='*'.
. * -----
. * Display qualified file name
: DATAGRP    GRPSEP=QINDENT
              HELP='wrkmbr/filelib'
              COMPACT
              .
: DATAI     VAR=file
              USAGE=OUT
              .
File
: DATAI     VAR=lib
              USAGE=OUT
              .
Library
: EDATAGRP.
. *
: EDATA.
. *
. * -----
. * Define the list area
. * -----
: LIST       DEPTH='*'
              MAXHEAD=4
              LISTDEF=mbrconf
              VIEW=mbrview.
: TOPINST.Press Enter to confirm your choices for 4=Remove.
: TOPINST.Press F12 to return to change your choices.
. *
. * -----
. * Define the columns of the list
. * -----
: LISTCOL    VAR=mopt
```

```

        USAGE=OUT
        HELP='confrvm/option'
        MAXWIDTH=6.

Opt
:LISTCOL  VAR=mbr
          USAGE=OUT
          HELP='wrkmbr/mbr'
          MAXWIDTH=10.

Member
:LISTCOL  VAR=mtype
          USAGE=OUT
          HELP='wrkmbr/type'
          MAXWIDTH=10.

Type
:LISTCOL  VAR=mtext
          USAGE=OUT
          HELP='wrkmbr/text'
          MAXWIDTH='*'.

Text
.*
.* -----
.* Define multiple views for F11 to toggle between
.* -----
:LISTVIEW COLS='mopt mbr mtype mtext'.
:LISTVIEW COLS='mopt mbr' layout=4.
.*
:ELIST.
:EPANEL.

```

Automatic Confirmation Processing

The UIM provides support to automatically perform confirmation processing. This support is available when the UIM is in control of processing list options by specifying `ACTOR=UIM` on the `LIST` tag that defines the action list.

To have the UIM perform confirmation processing for a list option, specify the name of the confirmation panel on the `CONFIRM` attribute of the list action (`LISTACT`) tag that defines the option to be confirmed. The following UIM source shows the `LISTACT` tag for option 4 with the `CONFIRM` attribute specifying the name of the confirmation panel.

```

.*
:LISTACT  OPTION=4
          ACTFOR=LISTE
          HELP='wrkmbr/rvm'
          CONFIRM=confrvm
          ENTER='CMD RMVM FILE(&lib./&file.) MBR(&mbr.)'
          PROMPT='CMD ?RMVM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'
          USREXIT='CALL exitpgm'.

4=Remove
.*

```

For more information about defining a confirmation panel using the `CONFIRM` attribute, see “`LISTACT` (List Action)” on page A-88.

When the UIM processes list options and finds an option with the `CONFIRM` attribute specified, the UIM does the following:

1. Deletes the list specified on the `LISTDEF` attribute of the `LIST` tag in the confirmation panel.

2. Finds all entries in the action list with an option number the same as the option number being confirmed, and copies these entries to the confirmation list.
3. Displays the confirmation panel.
4. Remembers that the option number has been confirmed by the user if the user presses the Enter key. The confirmed options are processed in the order they appear in the action list. No further confirmation processing is done for this option number until the user types the option number for additional entries in the action list.
5. Stops processing list options, if the user presses the F12 (Cancel) key, and redisplay the action list panel showing the first entry with the option number that was not confirmed.

Application Programming for Confirmation Processing

When ACTOR=UIM is specified on the LIST tag in the action list panel, there is no application programming needed because the UIM performs all confirmation processing.

When ACTOR=CALLER is specified on the LIST tag in the action list panel, the application program that processes the list options should perform confirmation processing similar to the UIM processing as described in “Automatic Confirmation Processing” on page 16-31.

Creating a Data Presentation Panel

Data presentation panels are used to display user data or allow input of user data in connection with an option on a list panel. When data input/output is scrollable and low in frequency and volume, UIM simplifies creating consistent data presentation panels.

The following shows the coding to create the Display Member Description display from the Work with File Members display.

The panel shown in Figure 16-7 on page 16-33 shows an example of a data presentation panel. This panel is shown as a result of using option 5 on the panel shown in Figure 16-3 on page 16-14.

This panel contains two data presentation areas. The first area is using a vertical layout with two layout columns. This area shows the file, library, and member name. The second area also uses a vertical layout, but only one layout column. This area shows the detail information for the member identified in the first area. If you need more information on creating help for a data presentation panel, see “Help in a Data Area” on page 19-6.

Display Member Description 1

File	XXXXXXXXXX	Member	XXXXXXXXXX 2
Library	XXXXXXXXXX		
Type of file	PF		3
Remote file	No		
Allow ODP sharing	Yes		
Source type	XXXXXXXXXX		
Last source change date and time	11/11/11 11:11:11		
Creation date and time	11/11/11 11:11:11		
Change date and time	11/11/11 11:11:11		
Number of records	11111111		
Deleted records	11111111		
Data space size	11111111		
Access path size	11111111		

4 More...

F3=Exit F12=Cancel 5

Figure 16-7. Example Data Presentation Panel

The second area is defined as a scrollable area because there are more items to show than will fit on a display at one time. The UIM automatically handles scrolling when the user presses the Page Up (Rolldown) or Page Down (Rollup) keys. When the Page Down operation is performed, the contents of the second data presentation area is replaced with the next set of items to show. This results in the panel shown in Figure 16-8 on page 16-34.

Notice that the contents of the first area remain the same when the second area is scrolled. The scroll operation only applies to one area of the panel based on the location of the cursor. Also, because the first area is not defined as scrollable, the scroll operation does not apply to that area even when the cursor position is within the area.

Display Member Description 1			
File	XXXXXXXXXX	Member	XXXXXXXXXX 2
Library	XXXXXXXXXX		
Save date and time	11/11/11	11:11:11	3
Restore date and time	11/11/11	11:11:11	
Expiration date and time	11/11/11	11:11:11	
Number of days used	11111111		
Date last used	11/11/11		
Use reset date	11/11/11		
Text	XX		
XXXXXXXXXX			
F3=Exit F12=Cancel 5			4 Bottom

Figure 16-8. Example Data Presentation Panel after Scrolling

The reference numbers in the example panel do not appear on the display. They are shown for illustration purposes and also appear in the UIM tag source shown in “Source for Example Data Presentation Panel” on page 16-36. These reference numbers show which portions of the source define text and information which appears on the panel.

- 1** The panel title is defined as text following the period of the display panel (PANEL) tag.
- 2** In the first data area, the text for the file, library, and member name is defined as text following the period of the data item (DATAI) tag. The file, library, and member names are dialog variable values. Each dialog variable is defined using the variable definition (VAR) tag. The name of the dialog variable is specified on the VAR attribute of the DATAI tag.

The file name and library are formatted as a qualified object name because GRPSEP=QINDENT is specified on the data group (DATAGRP) tag which surrounds the two DATAI tags.

The dialog variables for the file name and library name and member name are defined using the VAR tags at **A**, **B**, and **C**, respectively, shown on page 16-38.

This data presentation area is defined by specifying LAYOUT=2 on the DATA tag that defines the area. This is shown at **D** on page 16-43.

- 3** In the second data area, the text for each item is defined as text following the period of the DATAI tag. The value for each item is a dialog variable value. Each dialog variable is defined using the VAR tag. The name of the dialog variable is specified on the VAR attribute of the DATAI tag.

Several items in the area show date and time values. This is done by specifying the dialog variable for the date value on the VAR attribute of the DATAI tag and specifying the dialog variable for the time value on the VAR attribute of the data item extender (DATAIX) tag.

The date and time dialog variables are defined by specifying `BASETYPE=DATE` and `BASETYPE=TIME` on the class definition (`CLASS`) tag used to define the variables. This is shown at **E** on page 16-37. The UIM formats the date and time variables according to the date format and separator attributes and the time separator attribute of the job.

- 4** The scroll information, More... and Bottom, is shown because the list area is defined as scrollable. `SCROLL=YES` is specified on the `DATA` tag.
- 5** Each function key is defined using the key list item (`KEYI`) tag. The text, including the function key name, is defined as text following the period of the `KEYI` tag.

All function keys are defined by placing the `KEYI` tags between the key list (`KEYL`) and `EKEYL` tags. The name specified on the `NAME` attribute of the `KEYL` tag is also specified on the `KEYL` attribute of the `PANEL` tag.

Some function keys, such as Enter, do not have text specified for the `KEYI` tag. In this case, no text appears on the display. However, all function keys must be defined using the `KEYI` tag so the UIM knows what action is assigned to each key and what help module to use when help is displayed for the function keys.

Required Tags for a Data Presentation Panel

Figure 16-9 on page 16-36 shows the required tags for creating a UIM data presentation panel. For an example of the required and optional tags, see “Source for Example Data Presentation Panel” on page 16-36.

Note: The tags in Figure 16-9 on page 16-36 require attributes. These attributes are not shown. Without these attributes, the example in Figure 16-9 on page 16-36 will not compile. For a description of the required attributes for these required tags, see Appendix A, “UIM Panel Group Definition Language.”




Figure 16-9. Required UIM Tags for a Data Presentation Panel

Source for Example Data Presentation Panel

This is a partial listing of the member T0011PN2 in source file QATTUIM in library QUSRTOOL.

```

.* -----
.*
.* Beginning of panel group source.
.*
.* Enable access to OS/400 index search when help is displayed from
.* panels in this panel group.
.* -----
:PNLGRP    SCHIDX=qhss1
           DFTMSGF=t0011msgf2
           SUBMSGF=t0011msgf2.
.*
.* The import tag specifies that all help is to be found
.* in panel group T0011HL2 searching the library list.
:IMPORT    NAME='*'
           PNLGRP=t0011h12.
.*
.* -----
.* Define all variable classes
.* -----
.* -----
.* Option

```



```

.* Note: Need WIDTH=1 to preserve column alignment on confirmation panel.
:CLASS      NAME=optc1
            BASETYPE='ACTION'
            WIDTH=1.
:ECLASS.

.* -----
.* Object name
:CLASS      NAME=namec1
            BASETYPE='OBJNAME 10'.
:ECLASS.

.* -----
.* Library name
:CLASS      NAME=libc1
            BASETYPE='OBJNAME 10'.

:TL.
:TI          VALUE='*LIBL'.*LIBL
:TI          VALUE='*CURLIB'.*CURLIB
:ETL.
:ECLASS.

.* -----
.* File attribute
:CLASS      NAME=attrc1
            BASETYPE='CHAR 10'
            CASE=UPPER.
:ECLASS.

.* -----
.* Descriptive text
:CLASS      NAME=textc1
            BASETYPE='IGC 50'
            SUBST=QUOTED.
:ECLASS.

.* -----
.* Source type
:CLASS      NAME=srctypc1
            BASETYPE='CHAR 10'.
:ECLASS.

.* -----
.* Date
:CLASS      NAME=datec1 E
            BASETYPE='DATE'.

:TL.
:TI VALUE='          '.
:TI VALUE='0000000'.
:ETL.
:ECLASS.

.* -----
.* Time
:CLASS      NAME=timec1 E
            BASETYPE='TIME'.

:TL.
:TI VALUE='          '.
:TI VALUE='000000'.
:ETL.
:ECLASS.

.* -----
.* Yes or No flag class
:CLASS      NAME=yesnoc1
            BASETYPE='CHAR 1'
            WIDTH=3.

:TL.
:TI VALUE='0'.No
:TI VALUE='1'.Yes
:ETL.
:ECLASS.

```

```

.* -----
.* Type of file
:CLASS    NAME=typfc1
          BASETYPE='CHAR 1'
          WIDTH=2.

:TL.
:TI VALUE='"0"'.PF
:TI VALUE='"1"'.LF
:ETL.
:ECLASS.
.* -----
.* Binary 31
:CLASS    NAME=bin31
          BASETYPE='BIN 31'.
:ECLASS.
:
Additional CLASS tags in member T0011PN2 are not shown here
:
.* -----
.* Classes for pad variables in variable record definitions.
:CLASS    NAME=pad1c1
          BASETYPE='CHAR 1'.
:ECLASS.
:CLASS    NAME=pad2c1
          BASETYPE='CHAR 2'.
:ECLASS.
:CLASS    NAME=pad10c1
          BASETYPE='CHAR 10'.
:ECLASS.
:CLASS    NAME=pad13c1
          BASETYPE='CHAR 13'.
:ECLASS.
:CLASS    NAME=pad48c1
          BASETYPE='CHAR 48'.
:ECLASS.
:CLASS    NAME=pad50c1
          BASETYPE='CHAR 50'.
:ECLASS.
.*
.* -----
.* Define all dialog variables
.* -----
.*
.* -----
.* Variables for file and library
.* -----
.*
.* File name
:VAR      NAME=file A
          CLASS=namecl.
.* -----
.* Library name
:VAR      NAME=lib B
          CLASS=libcl.
.* -----
.* attributes
:VAR      NAME=fattr
          CLASS=attrcl.
.* -----
.*
.* -----
.* Variables for list of members
.* -----
.* -----

```

```

.* option for list of members
:VAR      NAME=mopt
          CLASS=optcl.

.* -----
.* Object name
:VAR      NAME=mbrc C
          CLASS=namecl.

.* -----
.* member type
:VAR      NAME=mtype
          CLASS=attrcl.

.* -----
.* Descriptive text
:VAR      NAME=mtext
          CLASS=textcl.

.*
.* -----
.* Variables for member description
.* -----
.* -----
.* Source type
:VAR      NAME=mbrsrc
          CLASS=srctypcl.

.* -----
.* Creation date
:VAR      NAME=mbrcrtdat
          CLASS=datecl.

.* -----
.* Creation time
:VAR      NAME=mbrcrttim
          CLASS=timecl.

.* -----
.* Member last source change date
:VAR      NAME=mbrschgdat
          CLASS=datecl.

.* -----
.* Member last source change time
:VAR      NAME=mbrschgtim
          CLASS=timecl.

.* -----
.* Member remote source file indicator
:VAR      NAME=mbrsrcfil
          CLASS=yesnocl.

.* -----
.* Member remote file indicator
:VAR      NAME=mbrremote
          CLASS=yesnocl.

.* -----
.* Member type of file
:VAR      NAME=mbrtypf
          CLASS=typfcl.

.* -----
.* Member ODP sharing
:VAR      NAME=mbrdpsshr
          CLASS=yesnocl.

.* -----
.* Member current number of records
:VAR      NAME=mbrcurrrec
          CLASS=bin31.

.* -----
.* Member number of deleted records
:VAR      NAME=mbrdltrec
          CLASS=bin31.

.* -----

```

```

.* Member data space size
:VAR      NAME=mbrspcsiz
          CLASS=bin31.
.* -----
.* Member access path size
:VAR      NAME=mbracpsiz
          CLASS=bin31.
.* -----
.* Number of database file members
:VAR      NAME=mbrdbfmbrs
          CLASS=bin31.
.* -----
.* Member change date.
:VAR      NAME=mbrchgdat
          CLASS=datecl.
.* -----
.* Member change time
:VAR      NAME=mbrchgtim
          CLASS=timecl.
.* -----
.* Member dave date
:VAR      NAME=mbrsavidat
          CLASS=datecl.
.* -----
.* Member save time
:VAR      NAME=mbrsavtim
          CLASS=timecl.
.* -----
.* Member restore date
:VAR      NAME=mbrrstdat
          CLASS=datecl.
.* -----
.* Member restore time
:VAR      NAME=mbrrsttim
          CLASS=timecl.
.* -----
.* Member expiration date
:VAR      NAME=mbrexpdatt
          CLASS=datecl.
.* -----
.* Member expiration time
:VAR      NAME=mbrexptim
          CLASS=timecl.
.* -----
.* Member number of days used
:VAR      NAME=mbrdysuse
          CLASS=bin31.
.* -----
.* Member date last used
:VAR      NAME=mbrlastuse
          CLASS=datecl.
.* -----
.* Member use reset date
:VAR      NAME=mbrresetdat
          CLASS=datecl.
.* -----
:
Additional VAR tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Variables for padding in variable record definitions.
.* Padding is needed in variable records so the layout
.* of the record matches a list format returned from

```

```

.* an API. The pad variables are used as placeholders for
.* variables not used in the API format or for reserved space
.* in the API format.
.* -----
:VAR      NAME=pad1
          CLASS=pad1c1.
:VAR      NAME=pad2
          CLASS=pad2c1.
:VAR      NAME=pad10
          CLASS=pad10c1.
:VAR      NAME=pad13
          CLASS=pad13c1.
:VAR      NAME=pad48
          CLASS=pad48c1.
:VAR      NAME=pad50
          CLASS=pad50c1.
:
:
The first VARRCD tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define a variable record for list of members.
.* The layout of this record is designed to match the
.* List Database File Members API (QUSLMBR) format name MBRL0200.
.* -----
:VARRCD   NAME=mbrl0200
          VARS='mbr mtype pad13 pad13 mtext'
          NOPUT='pad13'
          NOGET='mtype pad13 mtext'
          .
.*
.* -----
.* Define a variable record for member description.
.* The layout of this record is designed to match the
.* Retrieve Member Description API (QUSRMBRD) format name MBRD0200.
.* -----
:VARRCD   NAME=mbrd0200
          VARS='pad48 mbrsrc mbrcrtdat mbrcrttim mbrschgdat'
          VARS='mbrschgtim pad50 mbrsrcfil mbrremote mbrtypf'
          VARS='mbrodpshr pad2 mbrcurrrec mbrdltrrec mbrspcsiz'
          VARS='mbracpsiz mbrdbfmbrr mbrchgdat mbrchgtim mbrsavgdat'
          VARS='mbrsavgtim mbrstddat mbrsttim mbrexpdat mbrxptim'
          VARS='mbrdysuse mbrlastuse mbrsetdat'
          NOPUT='pad48 pad50 pad2'
          NOGET='pad48 pad50 pad2'
          .
:
:
Additional VARRCD tags in member T0011PN2 are not shown here
:
:
All LISTDEF tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define all conditions
.* -----
.* -----
.* Condition for physical files
:COND     NAME=pf
          EXPR='fattr="PF          "'
:
:
Additional COND tags in member T0011PN2 are not shown here
:

```

```

.* -----
.* Condition for source files
:COND      NAME=srcpf
           EXPR='mbrsrcfil="1"'.
.* -----
.* Condition for member in a physical file
:COND      NAME=mbrpf
           EXPR='mbrtypf="0"'.
.* -----
.* Condition for member in a logical file
:COND      NAME=mbrlf
           EXPR='mbrtypf="1"'.
:
Additional COND tags in member T0011PN2 are not shown here
:
:
All TT tags in member T0011PN2 are not shown here
:
:
All MBAR tags in member T0011PN2 are not shown here
:
:
The first KEYL tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define basic key for panels without a command line
.* or multiple views.
.* -----
:KEYL      NAME=basickeys 5
           HELP=keyl.
:KEYI      KEY=F1
           HELP=helpf1
           ACTION=HELP.
:KEYI      KEY=F3
           HELP=exit
           ACTION='EXIT SET'
           VARUPD=NO.
F3=Exit
:KEYI      KEY=F12
           HELP=cancel
           ACTION='CANCEL SET'
           VARUPD=NO.
F12=Cancel
:KEYI      KEY=F24
           HELP=morekeys
           ACTION=MOREKEYS.
F24=More keys
:KEYI      KEY=ENTER
           HELP=enter
           ACTION=ENTER.
:KEYI      KEY=HELP
           HELP=help
           ACTION=HELP.
:KEYI      KEY=PAGEDOWN
           HELP=pagedown
           ACTION=PAGEDOWN.
:KEYI      KEY=PAGEUP
           HELP=pageup
           ACTION=PAGEUP.
:KEYI      KEY=PRINT
           HELP=print

```

```

        ACTION=PRINT.
:EKEYL.
:
The first PANEL tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define Display Member Description panel
.* -----
:PANEL      NAME=dspmbr
            HELP='dspmbr/'
            KEYL=basickkeys 5
            ENTER='RETURN 500'
            TOPSEP=SPACE.
Display Member Description 1
.*
.* -----
.* Define a data presentation area to display the
.* library/file and member name whose description is displayed.
.* -----
:DATA      DEPTH=3
            SCROLL=NO
            LAYOUT=2 D
            BOTSEP=SPACE
            COMPACT
            .

.* -----
.* Divide the layout width into two columns.
.* The first column is for the prompt text with leader dots.
.* The second column is for the variable values.
:DATACOL   WIDTH=22.
:DATACOL   WIDTH='*'.
.* -----
.* Display qualified file name
:DATAGRP   GRPSEP=QINDENT
            HELP='dspmbr/filelib'
            COMPACT
            .
:DATAI     VAR=file 2
            USAGE=OUT
            .
File
:DATAI     VAR=lib 2
            USAGE=OUT
            .
Library
:EDATAGRP.
.* -----
.* Display member name
:DATAI     VAR=mbr 2
            HELP='dspmbr/mbr'
            USAGE=OUT
            .
Member
.*
:EDATA.
.*
.* -----
.* Define a data presentation area to display the
.* member definition.
.* -----
:DATA      DEPTH='*'
            SCROLL=YES 4
            LAYOUT=1

```

```

BOTSEP=SPACE
.
.* -----
.* Divide the layout width into two columns.
.* The first column is for the prompt text with leader dots.
.* The second column is for the variable values.
:DATACOL  WIDTH=35.
:DATACOL  WIDTH='*'.
.* -----
.* Display information about the file
:DATAGRP  GRPSEP=NONE
          COMPACT
.
.* -----
.* Display type of file
:DATAI    VAR=mbrtypf 3
          HELP='dspmbr/mbrtypf'
          USAGE=OUT
.
Type of file
.* -----
.* Display remote file
:DATAI    VAR=mbrremote
          HELP='dspmbr/mbrremote'
          USAGE=OUT
.
Remote file
.* -----
.* Display ODP sharing
:DATAI    VAR=mbrodpshr
          HELP='dspmbr/mbrodpshr'
          USAGE=OUT
.
Allow ODP sharing
:EDATAGRP.
.* -----
.* Display information only if file is a source file
:DATAGRP  GRPSEP=NONE
          COMPACT
          COND=srcpf
.
.* -----
.* Display source type
:DATAI    VAR=mbrsrc
          HELP='dspmbr/mbrsrc'
          USAGE=OUT
.
Source type
.* -----
.* Display last source change date and time
:DATAI    VAR=mbrschgdat
          HELP='dspmbr/mbrschgdt'
          USAGE=OUT
.
Last source change date and time
:DATAIX   VAR=mbrschgtim
          USAGE=OUT
.
:EDATAGRP.
.* -----
.* Display create and change information
:DATAGRP  GRPSEP=NONE
          COMPACT

```



```

.* -----
.* Display creation date and time
:DATAI  VAR=mbrcrtdat
        HELP='dspmbr/mbrcrtdt'
        USAGE=OUT
.
Creation date and time
:DATAIX VAR=mbrcrttim
        USAGE=OUT
.
.* -----
.* Display change date and time
:DATAI  VAR=mbrchgdat
        HELP='dspmbr/mbrchgdt'
        USAGE=OUT
.
Change date and time
:DATAIX VAR=mbrchgtim
        USAGE=OUT
.
:EDATAGRP.
.* -----
.* Display information about the size of the member
:DATAGRP GRPSEP=NONE
        COMPACT
.
.* -----
.* Display current records for physical file member
:DATAI  VAR=mbrcurrec
        COND=mbrpf
        HELP='dspmbr/mbrcurrec'
        USAGE=OUT
.
Number of records
.* -----
.* Display current index entries for logical file member
:DATAI  VAR=mbrcurrec
        COND=mbrlf
        HELP='dspmbr/mbrcurrec'
        USAGE=OUT
.
Number of index entries
.* -----
.* Display deleted records
:DATAI  VAR=mbrdltrec
        HELP='dspmbr/mbrdltrec'
        USAGE=OUT
.
Deleted records
.* -----
.* Display data space size for physical file member
:DATAI  VAR=mbrspcsiz
        COND=mbrpf
        HELP='dspmbr/mbrspcsiz'
        USAGE=OUT
.
Data space size
.* -----
.* Display access path size
:DATAI  VAR=mbracpsiz
        HELP='dspmbr/mbracpsiz'
        USAGE=OUT

```

```

      .
Access path size
.* -----
.* Display database file members for logical file member
:DATAI  VAR=mbrdbfmbrrs
        COND=mbrlf
        HELP='dspmbr/mbrdbfmbrrs'
        USAGE=OUT
      .

Number of database file members
:EDATAGRP.
.* -----
.* Display save restore information
:DATAGRP GRPSEP=NONE
        COMPACT
      .

.* -----
.* Display save date and time
:DATAI  VAR=mbrsavdat 3
        HELP='dspmbr/mbrsavdt'
        USAGE=OUT
      .

Save date and time
:DATAIX  VAR=mbrsavtim 3
        USAGE=OUT
      .

.* -----
.* Display restore date and time
:DATAI  VAR=mbrrstddat
        HELP='dspmbr/mbrrstddt'
        USAGE=OUT
      .

Restore date and time
:DATAIX  VAR=mbrrsttim
        USAGE=OUT
      .

:EDATAGRP.
.* -----
.* Display expiration date
:DATAI  VAR=mbrexpdat
        HELP='dspmbr/mbrexpdt'
        USAGE=OUT
      .

Expiration date and time
:DATAIX  VAR=mbrexpitim
        USAGE=OUT
      .

.* -----
.* Display usage information
:DATAGRP GRPSEP=NONE
        COMPACT
      .

.* -----
.* Display number of days used
:DATAI  VAR=mbrdysuse
        HELP='dspmbr/mbrdysuse'
        USAGE=OUT
      .

Number of days used
.* -----
.* Display date last used
:DATAI  VAR=mbrlastuse
        HELP='dspmbr/mbrlastuse'
        USAGE=OUT

```

```

      .
Date last used
.* -----
.* Display use reset date
:DATAI   VAR=mbrresetdat
          HELP='dspmbr/mbrresetdat'
          USAGE=OUT
      .

Use reset date
:EDATAGRP.
.* -----
.* Display text description
:DATAI   VAR=mtext
          HELP='dspmbr/text'
          USAGE=OUT
      .

Text
.*
:EDATA.
.*
:EPANEL.
:
Additional PANEL tags in member T0011PN2 are not shown here
:
.*
.* -----
.* End of panel group source
.* -----
:EPNLGRP.

```

Application Programming for a Data Presentation Panel

An example of an application program to display the data presentation panel shown in Figure 16-7 on page 16-33 can be found in member T0011CP3 in file QATTSYSC in library QUSRTOOL. This is a C/400 program which calls the appropriate UIM application programming interfaces (APIs) to display the panel. This program is called by the UIM to process option 5 (Display) from the example list panel shown in Figure 16-3 on page 16-14.

To write a program in any language to display the example data presentation panel, the program should do the following:

1. If the program is not called by the UIM to process option 5 from the example list panel shown in Figure 16-3 on page 16-14, the program should first do the following. For example, this would be the case if the user could display the member description directly by using a CL command.
 - a. Call the Open Display Application (QUIOPNDA) API to open the panel group. The panel group must already be created using the Create Panel Group (CRTPNLGRP) command.
 - b. Set up a buffer containing the values for the following dialog variables:

FILE	A CHAR 10 variable which is the name of the file.
LIB	A CHAR 10 variable which is the name of the library where the file resides.
FATTR	A CHAR 10 variable which is the file attribute of the file. This variable is used to condition on list options which are only allowed for physical files.

c. Call the Put Dialog Variable (QUIPUTV) API to change the contents of the dialog variables using variable record FILELIB and the buffer initialized in the previous step.

d. Set up a buffer containing values for the following dialog variables:

MBR A CHAR 10 variable which is the member name.

MTYPE A CHAR 10 variable which is the member type.

PAD13 A CHAR 13 reserved space in the buffer.

PAD13 A CHAR 13 reserved space in the buffer.

MTEXT A CHAR 50 variable which is the descriptive text for the member.

Note: The layout of this buffer is designed to match with the layout of the entries in the user space returned by the QUSLMBR API. Therefore, instead of setting up a buffer, the application program can pass the buffer as it exists in the user space.

e. Call the Put Dialog Variable (QUIPUTV) API to change the contents of the dialog variables using variable record MBRL0200 and the buffer initialized in the previous step.

Note: If the program is called by the UIM to process option 5 from the example list panel, the file name and library name were already set by the application program before displaying the list panel. Also, when the UIM performs list option processing, the MBR, MTYPE, and MTEXT dialog variables will already be set to the values from the list entry which calls the application program to process option 5.

2. Set up a buffer containing values for the following dialog variables:

PAD48 A CHAR 48 reserved space in the buffer.

MBRSRC A CHAR 10 variable which is the source type for the member.

MBRCRTDAT A CHAR 7 variable which is the creation date for the member in the form required for BASETYPE=DATE dialog variables.

MBRCRTTIM A CHAR 6 variable which is the creation time for the member in the form required for BASETYPE=TIME dialog variables.

MBRSCHGDAT A CHAR 7 variable which is the source changed date for the member in the form required for BASETYPE=DATE dialog variables.

MBRSCHGTIM A CHAR 6 variable which is the source changed time for the member in the form required for BASETYPE=TIME dialog variables.

PAD50 A CHAR 50 reserved space in the buffer.

MBRSRCFIL A CHAR 1 variable indicating whether or not the member is in a source file ("0"=no, "1"=yes).

MBRREMOTE A CHAR 1 variable indicating whether or not the member is in a remote file ("0"=no, "1"=yes).

MBRTYPE	A CHAR 1 variable indicating whether the member is in a physical or logical file ("0"=physical "1"=logical).
MBRODPSHR	A CHAR 1 variable indicating whether or not ODP sharing is allowed for the member ("0"=no, "1"=yes).
PAD2	A CHAR 2 reserved space in the buffer.
MBRCURREC	A BINARY 4 variable containing the number of records in the member.
MBRDLTREC	A BINARY 4 variable containing the number of deleted records in the member.
MBRSPCSIZ	A BINARY 4 variable containing the size of the space for the member.
MBRACPSIZ	A BINARY 4 variable containing the access path size for the member.
MBRDBFMBS	A BINARY 4 variable containing the number of database file members for this logical file member.
MBRCHGDAT	A CHAR 7 variable which is the last changed date for the member in the form required for BASETYPE=DATE dialog variables.
MBRCHGTIM	A CHAR 6 variable which is the last changed time for the member in the form required for BASETYPE=TIME dialog variables.
MBRSAVDAT	A CHAR 7 variable which is the date the member was last saved in the form required for BASETYPE=DATE dialog variables.
MBRSAVTIM	A CHAR 6 variable which is the time the member was last saved in the form required for BASETYPE=TIME dialog variables.
MBRRSTDAT	A CHAR 7 variable which is the date the member was last restored in the form required for BASETYPE=DATE dialog variables.
MBRRSTTIM	A CHAR 6 variable which is the time the member was last restored in the form required for BASETYPE=TIME dialog variables.
MBREXPDAT	A CHAR 7 variable which is the date of expiration for the member in the form required for BASETYPE=DATE dialog variables.
MBREXPTIM	A CHAR 6 variable which is the time of expiration for the member in the form required for BASETYPE=TIME dialog variables.
MBRDYSUSE	A BINARY 4 variable containing the number of days the member has been used.
MBRLASTUSE	A CHAR 7 variable which is the date the member was last used in the form required for BASETYPE=DATE dialog variables.

MBRRSETDAT A CHAR 7 variable which is the date the use information was reset for the member in the form required for BASETYPE=DATE dialog variables.

Note: The layout of this buffer is designed to match with the layout of the data returned by the Retrieve Member Description (QUSRMBRD) API using format name MBRD0200. Therefore, instead of setting up a buffer, the application program can pass the buffer as it is returned by the API.

3. Call the Put Dialog Variable (QUIPUTV) API to change the contents of the dialog variables using variable record MBRD0200 and the buffer initialized in the previous step.
4. Call the Display Panel (QUIDSPP) API to display panel WRKMBR. The UIM returns control to the application when one of the following occurs:
 - The user presses the Enter key without typing any list options or a command on the command line. The program variable passed as the function requested parameter to the QUIDSPP API is set to 500. This is done because ENTER='RETURN 500' is specified on the PANEL tag which defines the WRKMBR panel.
 - The user presses the F12 (Cancel) key. The program variable passed as the function requested parameter to the QUIDSPP API is set to -8. This is the value defined for the CANCEL dialog command.
 - The user presses the F3 (Exit) key. The program variable passed as the function requested parameter to the QUIDSPP API is set to -4. This is the value defined for the CANCEL dialog command.
5. If the program is not called by the UIM to process option 5 from the example list panel shown in Figure 16-3 on page 16-14, the program should do the following.
 - a. Call the Close Application (QUICLOA) API to close the UIM application. This frees up the system resources being used by the UIM application.

Data Entry Panel

A data entry panel is a form of data presentation panel where the user is allowed to enter new values for one or more of the dialog variables displayed. The USAGE attribute of the data item (DATAI) and data item extender (DATAIX) tags defines whether or not the user is allowed to enter a new value for the dialog variable displayed by the tag.

When USAGE=INOUT is specified, the user is allowed to enter a new value for the dialog variable. For data areas using a vertical layout, the leader dots following the descriptive text for the item end with a period instead of a colon. A colon is used for data items which do not allow input.

When the UIM returns control from the Display Panel (QUIDSPP) API and the function requested parameter contains the value specified for the RETURN dialog command on the ENTER attribute of the display panel (PANEL) tag, the application program uses the Get Dialog Variable (QUIGETV) API to retrieve the values for the dialog variables changed by the user.

All choices for a menu bar are defined by placing the MBARC tags between the menu bar (MBAR) and EMBAR tags. The name specified on the NAME attribute of the MBAR tag is also specified on the MBAR attribute of the PANEL tag.

- 2** Each option in the pull-down menu is defined using the pull-down field choice (PDFLDC) tag. The option number is defined using the OPTION attribute and the text following the option number is defined as text following the period of the PDFLDC tag.

All choices for a pull-down menu are defined by placing the PDFLDC tags between the pull-down field (PDFLD) and EPDFLD tags. The PDFLDC and EPDFLD tags are placed between a MBARC and EMBARC tag.

- 3** An accelerator key description shown along the right side of the pull-down menu is defined as text following the period of the PDACCEL tag. An accelerator is a key which performs the same function as an option in a pull-down menu. The PDACCEL tag is placed immediately after the PDFLDC tag for the option to which the accelerator applies.

From this panel, the application user can perform operations against entries in the list using either of the following methods:

- When the user selects entries in the list and presses the Enter key, the UIM displays the pull-down menu for the member choice in the menu bar. This is done because SELECT=PULLDOWN is specified on the PANEL tag shown at **A** on page 16-62.

When the user selects option 3, 4, 5, 7, 8 or 9 from the pull-down menu, the UIM performs the action defined for that option once for each list entry selected by the user. The UIM does this because ACTFOR=LIST is specified on the PDFLDC tag at **B** on page 16-58. The UIM makes these options unavailable when the users displays the pull-down menu without selecting any entries in the list.

When the user selects option 90 from the pull-down menu, the UIM returns control to the application program that displayed the panel. The UIM does this because ACTFOR=PANEL is specified on the PDFLDC tag at **C** on page 16-59. Because EXIT is specified for the ACTION attribute on the PDFLDC tag, the UIM returns control to the calling program with an indication that the user requested Exit.

- When the user types option numbers next to the desired list entries and presses the Enter key, the UIM performs the action for each option. The UIM does this because ACTOR=UIM is specified on the list area (LIST) tag at **D** on page 16-63 and a list action (LISTACT) tag at **E** on page 16-63 specifies the action for the UIM to perform for each option number.

Note that in this case, no text is shown on the panel describing the option numbers for the list. This is because no text is specified following the period of the LISTACT tags. The primary interface defined for this panel is to select entries in the list and then choose an action from a pull-down menu. The list option numbers are available as a faster alternative for more experienced users. Although the list option numbers do not appear on the panel, they are described in the help shown when the Help key is pressed with the cursor positioned in the input column of the list.

For this example, the actions for the option numbers in the pull-down menu are the same as the actions for the option numbers that can be entered in the list.

This design is recommended for a consistent user interface, but the UIM does not prevent the application developer from defining an action in a pull-down menu that is different from the action for a list option with the same option number.

Required Tags for a Panel with a Menu Bar

Figure 16-11 shows the required tags for creating a UIM panel with a menu bar. For an example of the required and optional tags, see “Source for Example Panel with a Menu Bar” on page 16-54.

Note: The tags in Figure 16-11 require attributes. These attributes are not shown. Without these attributes, the example in Figure 16-11 will not compile. For a description of the required attributes for these required tags, see Appendix A, “UIM Panel Group Definition Language.”




Figure 16-11. Required UIM Tags for a Panel with a Menu Bar

Source for Example Panel with a Menu Bar

This is a partial listing of member T0011PN2 in source file QATTUIM in library QUSRTOOL.

```
. * -----
. *
. * Beginning of panel group source.
. *
. * Enable access to OS/400 index search when help is displayed from
. * panels in this panel group.
. * -----
:PNLGRP   SCHIDX=qhss1
          DFTMSGF=t0011msgf2
          SUBMSGF=t0011msgf2.

. *
. * The import tag specifies that all help is to be found
. * in panel group T0011HL2 found by searching the library list.
:IMPORT   NAME='*'
          PNLGRP=t0011hl2.

. *
. * -----
. * Define all variable classes
. * -----
. * -----
. * Option
. * Note: Need WIDTH=1 to preserve column alignment on confirmation panel.
:CLASS    NAME=optcl
          BASETYPE='ACTION'
          WIDTH=1.

:ECLASS.

. * -----
. * Object name
:CLASS    NAME=namecl
          BASETYPE='OBJNAME 10'.

:ECLASS.

. * -----
. * Library name
:CLASS    NAME=libcl
          BASETYPE='OBJNAME 10'.

:TL.
:TI       VALUE=' '*LIBL' '*LIBL
:TI       VALUE=' '*CURLIB' '*CURLIB
:ETL.
:ECLASS.

. * -----
. * File attribute
:CLASS    NAME=attrcl
          BASETYPE='CHAR 10'
          CASE=UPPER.

:ECLASS.

. * -----
. * Descriptive text
:CLASS    NAME=textcl
          BASETYPE='IGC 50'
          SUBST=QUOTED.

:ECLASS.

. * -----
```

```

.* Source type
:CLASS    NAME=srctypcl
          BASETYPE='CHAR 10'.
:ECLASS.
:
Additional CLASS tags in member T0011PN2 are not shown here
:
.* -----
.* Command line parameters
:CLASS    NAME=parmc1
          BASETYPE='CHAR 255'.
:ECLASS.
.* -----
.* Exit program specification for CALL dialog command
:CLASS    NAME=exitcl
          BASETYPE='CHAR 130'.
:ECLASS.
.* -----
.* View number
:CLASS    NAME=vwnumcl
          BASETYPE='BIN 15'.
:ECLASS.
.* -----
.* Classes for pad variables in variable record definitions.
:CLASS    NAME=pad1cl
          BASETYPE='CHAR 1'.
:ECLASS.
:CLASS    NAME=pad2cl
          BASETYPE='CHAR 2'.
:ECLASS.
:CLASS    NAME=pad10cl
          BASETYPE='CHAR 10'.
:ECLASS.
:CLASS    NAME=pad13cl
          BASETYPE='CHAR 13'.
:ECLASS.
:CLASS    NAME=pad48cl
          BASETYPE='CHAR 48'.
:ECLASS.
:CLASS    NAME=pad50cl
          BASETYPE='CHAR 50'.
:ECLASS.
.*
.* -----
.* Define all dialog variables
.* -----
.*
.* -----
.* Variables for file and library
.* -----
.*
.* File name
:VAR      NAME=file
          CLASS=namecl.
.* -----
.* Library name
:VAR      NAME=lib

```

```

        CLASS=libcl.
.* -----
.* attributes
:VAR      NAME=fattr
        CLASS=attrcl.
.* -----
.*
.* -----
.* Variables for list of members
.* -----
.* -----
.* option for list of members
:VAR      NAME=mopt
        CLASS=optcl.
.* -----
.* Object name
:VAR      NAME=mbr
        CLASS=namecl.
.* -----
.* member type
:VAR      NAME=mtype
        CLASS=attrcl.
.* -----
.* Descriptive text
:VAR      NAME=mtext
        CLASS=textcl.
:
Additional VAR tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Variable for command line parameters
.* -----
.* -----
.* Command line parameters
:VAR      NAME=parms
        CLASS=parmcl.
.*
.* -----
.* Variables for specifying CALL/exit programs
.* -----
.* -----
.* Program to call for all UIM exits
:VAR      NAME=exitpgm
        CLASS=exitcl.
.*
.* -----
.* Variables for controlling list views
.* -----
.* -----
.* View number for list of members
:VAR      NAME=mbrview
        CLASS=vwnumcl.
:
Additional VAR tags in member T0011PN2 are not shown here
:

```

```

.*
.* -----
.* Variables for padding in variable record definitions.
.* Padding is needed in variable records so the layout
.* of the record matches a list format returned from
.* an API. The pad variables are used as placeholders for
.* variables not used in the API format or for reserved space
.* in the API format.
.* -----
:VAR      NAME=pad1
          CLASS=pad1cl.
:VAR      NAME=pad2
          CLASS=pad2cl.
:VAR      NAME=pad10
          CLASS=pad10cl.
:VAR      NAME=pad13
          CLASS=pad13cl.
:VAR      NAME=pad48
          CLASS=pad48cl.
:VAR      NAME=pad50
          CLASS=pad50cl.
.*
.* -----
.* Define a variable record for file, library and file attribute
.* -----
:VARRCD   NAME=filelib
          VARS='file lib fattr'
          NOGET='fattr'
          .
.*
.* -----
.* Define a variable record for exit program
.* -----
:VARRCD   NAME=exitprog
          VARS='exitpgm'
          .
.*
.* -----
.* Define a variable record for list of members.
.* The layout of this record is designed to match the
.* List Database File Members API (QUSLMBR) format name MBRL0200.
.* -----
:VARRCD   NAME=mbrl0200
          VARS='mbr mtype pad13 pad13 mtext'
          NOPUT='pad13'
          NOGET='mtype pad13 mtext'
          .
:
Additional VARRCD tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define a list of members
.* -----
:LISTDEF  NAME=mbrlist
          VARS='mopt mbr mtype mtext'

```

```

MSGID=USR0101.
:
Additional LISTDEF tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define all conditions
.* -----
.* -----
.* Condition for physical files
:COND      NAME=pf
           EXPR='fattr="PF      "'.
.* -----
.* Conditions for views of members list
:COND      NAME=mbrview1
           EXPR='mbrview=0'.
:COND      NAME=mbrview2
           EXPR='mbrview=1'.
:
Additional COND tags in member T0011PN2 are not shown here
:
:
All TT tags in member T0011PN2 are not shown here
:
.*
.* -----
.* Define menu bar for work with members panel
.* -----
:MBAR      NAME=mbarmbr 1
           HELP='mbarmbr/'
.
:MBARC     HELP='mbarmbr/member'
.
Member 1
:PDFLD.
:PDFLDC    OPTION=3
           ACTFOR=LIST B
           HELP='mbarmbr/cpyf'
           ACTION='CMD CPYF ?*FROMFILE(&lib./&file.)'
           ACTION=' ?*FROMMBR(&mbr.) &parms.'
.
Copy... 2
.*
:PDFLDC    OPTION=4
           ACTFOR=LIST
           HELP='mbarmbr/rmvm'
           ACTION='CMD RMVM FILE(&lib./&file.) MBR(&mbr.)'
.*
           CONFIRM=confrmvmb
           USREXIT='CALL exitpgm'
.
Remove...
.*
:PDFLDC    OPTION=5
           COND=pf
           ACTFOR=LIST
           HELP='mbarmbr/dsppfm'
           ACTION='CMD DSPPFM FILE(&lib./&file.) MBR(&mbr.) &parms.'

```

```

Display...
.*
:PDFLDC  OPTION=7
          COND=pf
          ACTFOR=LIST
          HELP='mbarmbr/rgzm'
          ACTION='CMD RGZPFM FILE(&lib./&file.) MBR(&mbr.)'

Reorganize
.*
:PDFLDC  OPTION=8
          ACTFOR=LIST
          HELP='mbarmbr/dspfd'
          ACTION='CALL exitpgm'

Member description...
.*
:PDFLDC  OPTION=9
          COND=pf
          ACTFOR=LIST
          HELP='mbarmbr/clrm'
.*
          CONFIRM=confcclrmmb
          ACTION='CMD CLRPFM FILE(&lib./&file.) MBR(&mbr.)'

Clear...
.*
:PDFLDC  OPTION=90
          ACTFOR=ANEL C
          HELP='mbarmbr/exit'
          ACTION='EXIT SET'
          VARUPD=NO

Exit
:PDACCEL.F3 3
:EPDFLD.
:EMBARC.
.*
:MBARC   HELP='mbarmbr/view'

View
:PDFLD.
:PDFLDC  OPTION=1
          ACTFOR=ANEL
          HELP='mbarmbr/view2'
          AVAIL=mbrview1
          ACTION=CHGVIEW

Names only
:PDACCEL.F11
:PDFLDC  OPTION=2
          ACTFOR=ANEL
          HELP='mbarmbr/view1'
          AVAIL=mbrview2
          ACTION=CHGVIEW

Names and descriptions
:PDACCEL.F11

```

```

:EPDFLD.
:EMBARC.
.*
:MBARC    HELP='mbarmbr/help'
.
Help
:PDFLD.
:PDFLDC   OPTION=1
          ACTFOR=PANEL
          HELP='mbarmbr/helphelp'
          ACTION=helphelp
.
Help for help...
:PDFLDC   OPTION=2
          ACTFOR=PANEL
          HELP='mbarmbr/exthelp'
          ACTION=exthelp
.
Extended help...
:PDFLDC   OPTION=3
          ACTFOR=PANEL
          HELP='mbarmbr/keyshelp'
          ACTION=keyshelp
.
Keys help...
:PDFLDC   OPTION=4
          ACTFOR=PANEL
          HELP='mbarmbr/helpidx'
          ACTION=helpidx
.
Help index...
:PDFLDC   OPTION=5
          ACTFOR=PANEL
          HELP='mbarmbr/about'
          ACTION='DSPHELP about'
.
About...
:EPDFLD.
:EMBARC.
:EMBAR.
:
:
The first KEYL tags in member T0011PN2 are not shown here
:
.*
.*
.* -----
.* Define keys for work with members panel with a menu bar
.* The keys are the same but some do not have descriptions
.* -----
:KEYL     NAME=mbrkeysmb
          HELP=keyl.
:KEYI     KEY=F1
          HELP=helpf1
          ACTION=HELP.
:KEYI     KEY=F3
          HELP=exit
          ACTION='EXIT SET'

```



```

VARUPD=NO.
F3=Exit
:KEYI      KEY=F4
           HELP=prompt
           ACTION=PROMPT
           PRIORITY=30.
F4=Prompt
:KEYI      KEY=F9
           HELP=retrieve
           ACTION=RETRIEVE
           PRIORITY=35.
F9=Retrieve
:KEYI      KEY=F10
           HELP=actions
           ACTION=ACTIONS
           PRIORITY=40.
F10=Actions
:KEYI      KEY=F11
           HELP=mbrviewname
           ACTION=CHGVIEW
           COND=mbrview1.
:KEYI      KEY=F11
           HELP=mbrviewdesc
           ACTION=CHGVIEW
           COND=mbrview2.
:KEYI      KEY=F12
           HELP=cancel
           ACTION='CANCEL SET'
           VARUPD=NO.
F12=Cancel
:KEYI      KEY=F24
           HELP=morekeys
           ACTION=MOREKEYS.
F24=More keys
:KEYI      KEY=ENTER
           HELP=enter
           ACTION=ENTER.
:KEYI      KEY=HELP
           HELP=help
           ACTION=HELP.
:KEYI      KEY=PAGEDOWN
           HELP=pagedown
           ACTION=PAGEDOWN.
:KEYI      KEY=PAGEUP
           HELP=pageup
           ACTION=PAGEUP.
:KEYI      KEY=PRINT
           HELP=print
           ACTION=PRINT.
:EKEYL.
:
Additional KEYL tags in member T0011PN2 are not shown here
:
:
The first PANEL tags in member T0011PN2 are not shown here
:

```

```

.*
.*
.* -----
.* Define Work with Members panel with a menu bar to process options
.* -----
:PANEL      NAME=wrkmbrmbar
            HELP='wrkmbr/'
            MBAR=mbarmbr 1
            KEYL=mbrkeysmb
            ENTER='RETURN 500'
            SELECT=PULLDOWN A
            TOPSEP=SPACE.
Work with File Members
.*
.* -----
.* Define a data presentation area to display the
.* library/file name whose members are listed.
.* -----
:DATA      DEPTH=3
            SCROLL=NO
            LAYOUT=1
            BOTSEP=SPACE
            COMPACT
            .

.* -----
.* Divide the layout width into two columns.
.* The first column is for the prompt text with leader dots.
.* The second column is for the variable values.
:DATACOL   WIDTH=22.
:DATACOL   WIDTH=12.
:DATACOL   WIDTH='*'.
.* -----
.* Display qualified file name
:DATAGRP   GRPSEP=QINDENT
            HELP='wrkmbr/filelib'
            COMPACT
            .
:DATAI     VAR=file
            USAGE=INOUT
            CSRLOC=NO
            PROMPT='CALL exitpgm'
            .

File
:DATAC.F4  for list
:DATAI     VAR=lib
            USAGE=INOUT
            CSRLOC=NO
            .

Library
:DATAC.library, *CURLIB, *LIBL
:EDATAGRP.
.*
:EDATA.
.*
.* -----
.* Define the list area
.* -----
:LIST      DEPTH='*'

```

```

LISTDEF=mbrlist
ACTOR=UIM D
MAXHEAD=4
MAXACTL=3
VIEW=mbrview
PARMS=parms
BOTSEP=SPACE.

:TOPINST.Select members using /, press Enter.
.*
.* -----
.* Specify the action to be taken for each option
.* -----
:LISTACT OPTION=3 E
NOCMD=PROMPT
HELP='wrkmbr/cpyf'
ENTER='CMD CPYF ?*FROMFILE(&lib./&file.)'
ENTER=' ?*FROMMBR(&mbr.) &parms.'
PROMPT='CMD ?CPYF ?*FROMFILE(&lib./&file.)'
PROMPT=' ?*FROMMBR(&mbr.) &parms.'.

.*
:LISTACT OPTION=4
HELP='wrkmbr/rmvm'
.* CONFIRM=confrmvmb
ENTER='CMD RMVM FILE(&lib./&file.) MBR(&mbr.)'
PROMPT='CMD ?RMVM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'
USREXIT='CALL exitpgm'.

.*
:LISTACT OPTION=5
COND=pf
HELP='wrkmbr/dsppfm'
ENTER='CMD DSPPFM FILE(&lib./&file.) MBR(&mbr.) &parms.'
PROMPT='CMD DSPPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.) &parms.'.

.*
:LISTACT OPTION=7
COND=pf
HELP='wrkmbr/rgzm'
ENTER='CMD RGZPFM FILE(&lib./&file.) MBR(&mbr.)'
PROMPT='CMD ?RGZPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'.

.*
:LISTACT OPTION=8
HELP='wrkmbr/dspfd'
ENTER='CALL exitpgm'
PROMPT='CALL exitpgm'.

.*
:LISTACT OPTION=9
COND=pf
HELP='wrkmbr/clrm'
.* CONFIRM=confcclrmmb
ENTER='CMD CLRPFM FILE(&lib./&file.) MBR(&mbr.)'
PROMPT='CMD ?CLRPFM ?*FILE(&lib./&file.) ?*MBR(&mbr.)'.

.*
.*
.* -----
.* Define the columns and headings to display
.* -----
:LISTCOL VAR=mopt
USAGE=INOUT
HELP='wrkmbr/option'

```

```

MAXWIDTH=6.
:LISTCOL  VAR=mbr
          USAGE=OUT
          HELP='wrkmbr/mbr'
          MAXWIDTH=10.

Member
:LISTCOL  VAR=mtype
          USAGE=OUT
          HELP='wrkmbr/type'
          MAXWIDTH=10.

Type
:LISTCOL  VAR=mtxt
          USAGE=OUT
          HELP='wrkmbr/text'
          MAXWIDTH='*'.

Text
.*
.* -----
.* Define multiple views for F11 to toggle between
.* -----
:LISTVIEW COLS='mopt mbr mtype mtxt'.
:LISTVIEW COLS='mopt mbr' layout=4.
.*
:ELIST.
.*
.* -----
.* Use a command line and allow parameters to be given
.* -----
:CMDLINE  SIZE=SHORT.
Parameters for options 3 and 5 or command
.*
:EPANEL.
:
Additional PANEL tags in member T0011PN2 are not shown here
:
.*
.* -----
.* End of panel group source
.* -----
:EPNLGRP.

```

Application Programming for a Menu Bar Panel

An example of an application program to display the panel shown in Figure 16-10 on page 16-51 can be found in member T0011CP2 in source file QATTSYSC in library QUSRTOOL. This is a C/400 program which calls the appropriate UIM application programming interfaces (APIs) to display the panel.

The application program should do the processing described in “Application Programming for a List Panel” on page 16-26.

Chapter 17. Details of Using User Interface Manager

This chapter explains the structure of the OS/400 user interface manager (UIM) and provides an overview of its objects and functions.

Opening a UIM Application

An application program must first open a UIM application that uses the panel group to access dialog variables, lists, and panel definitions. An application is opened by the Open Display Application (QUIOPNDA) or Open Print Application (QUIOPNPA) APIs and closed by the Close Application (QUICLOA) API. A UIM application is managed much like an open file. It is meaningful only for a particular call for reclaim resources processing, and it is automatically closed as necessary by the reclaim resources function or by cleanup processing at the end of a job.

When an application is opened, UIM assigns each application an application handle. A **handle** is a variable that represents an object, an instance of an application using some function, or a processing session. This handle must be specified as an input parameter to all APIs that operate with the application. The same panel group object can be associated with more than one open application in the same job, but each application contains a completely independent set of dialog variables, active lists, and internal control information that define the state of the UIM application.

Defining Dialog Variables

A **dialog variable** is a UIM element that contains a value. This value can be referred to and updated by programs that use the open application and by the UIM when it performs functions such as displaying panels to the user.

The dialog variables contained in an open application are determined by the panel group object associated with the application. Dialog variables are defined using the variable definition (VAR) language tag in the source for a panel group. Special dialog variables defined by UIM have names that begin with the letter Z and are referred to as **Z-variables**. For more information on the VAR language tag, see "VAR (Variable Definition)" on page A-159. For more information on Z-variables, see "Dialog Variables Defined by UIM" on page A-159.

Every open application associated with a particular panel group object contains a complete set of all the dialog variables defined in the panel group, including whatever Z-variables are defined in the tag language for that panel group. The set of all dialog variables in an application is called the **variable pool** for the application. For more information on variable pools, see "Using Variable Pool Services" on page 17-4. The dialog variables are used to display panel field values that are not constant text. The dialog variables are also used to tailor the format of the panel using the condition definition (COND) tag. For more information on the COND tag, see "COND (Condition Definition)" on page A-25.

The definition of each dialog variable specifies a base data type value that controls both the form of the internal storage of the variable and its editing characteristics on the display. The following base type values are supported:

- Character

- IGC
- Graphic
- Binary (numeric)
- Packed and zoned decimal
- Date
- Time
- Action (list option or selection)
- Name
- Object name
- Pointer

The class definition (CLASS) language tag defines a class of dialog variables to be associated with a base data type, specific validity checking, and display value translation functions. Validity checking is done only for values entered by the user in an input field on a display. The validity checking is not done for values provided by an application program through an API. For more information on the CLASS tag, see “CLASS (Class Definition)” on page A-14.

A translation function allows the application program to operate with internal values. The values are automatically mapped by the UIM to and from specified character string values, when displayed or printed. An example of this is the months in a year. The application program reference the values 1 through 12, but the user sees only the names of the months on the display. For more information on the translation function, see “TL (Translation List)” on page A-152.

When the application is initially opened, every dialog variable in the application has an initial value. For dialog variables defined by the application programmer, the initial value is determined by the base type as follows:

Table 17-1. Initial Values of Dialog Variable

Dialog Variable	Initial Value
Numeric	0
Date and Time	0
Character	Single-byte blanks
IGC	Single-byte blanks
Graphic	Double-byte blanks
Pointer	Null
Z-variable	Defined by the definition of the variable (see “Defining Dialog Variables” on page 17-1)

Any dialog variable that is referenced without a set value is assigned the initial value, whether the reference is made by an application program or by the UIM.

Restrictions on Using Dialog Variables

A dialog variable *should not* be used for the value of more than one display item per panel as multiple input fields, because the results might be undesirable. This means that when used as input fields, no dialog variable should be named on multiple data item (DATAI), data item extender (DATAIX), or list column (LISTCOL) tags that are part of the same panel definition without conditioning. This ensures that the same dialog variable does not appear on the display in more than one place.

Because the variable pool exists until the application is closed, the UIM, and all programs that use the application, can determine the last value assigned to any dialog variable in the pool. Once the application program assigns the value of a dialog variable, it never needs to be assigned again as long as it does not need to be changed. Similarly, once an input value is accepted from the user and stored in a dialog variable, that value continues to be available until the variable is updated by either an application program or the user.

Dialog Variable Error Messages

The Put Dialog Variable (QUIPUTV) API allows an application program to state that a dialog variable is in error. When this happens, the field in error is highlighted and the cursor is positioned to the first input field that is in error. The application program reports the cause of the error and requests that the UIM display the messages to the user using the message reference key parameter of the Display Panel (QUIDSPP) API.

All variables in error in the open application are reset when the next dialog command is processed by the UIM. Exceptions to this are the Menu Bar Cursor Action (ACTIONS), Command Line (CMDLINE), Change View (CHGVIEW), HELP, Display More Function Keys (MOREKEYS), Move to Top (MOVETOP), PAGEUP, PAGEDOWN, Print Screen (PRINT), and Retrieve Command String (RETRIEVE) dialog commands. The error status for each dialog variable is reset when control returns from the Display Panel (QUIDSPP) API or when control is passed from the UIM to a program or command identified by a menu item, action list, pull-down choice, or function key item.

When a function key is pressed or a pull-down choice is selected that performs an action where VARUPD=YES was specified, ((see “KEYI (Key List Item)” on page A-72), and “PDFLDC (Pull-Down Field Choice)” on page A-131), the UIM validates the values of all entered (changed) input fields. If an error is found, the panel is displayed again with the fields in error highlighted and one or more messages is issued. The values of the dialog variable associated with the input fields are not changed until the user enters a correct value.

The application developer can specify that some function keys and pull-down choices operate without updating the variable pool by using VARUPD=NO. If control returns to the program that ran the QUIDSPP API for such a function, all values entered by the user are lost. If the requested function causes the UIM to call a program or system command, all input field values are stored internally by the UIM in such a way that they can be shown when control returns to the UIM and the panel is displayed again. These input values are stored locally for the panel being displayed. Any panel that is presented using the same open application by a program or command with VARUPD=NO specified, displays the values of all dialog variables as they exist in the variable pool. However, if VARUPD=YES is specified, the updated value is used instead of the stored value when control returns and the original panel is displayed again.

Providing Field Values for a Display Panel Using Dialog Variables

The tag language allows you to use dialog variables to provide field values for a display panel and substitution values for a CL command that is called by the UIM for a pull-down choice, menu choice, function key, or action list selection. Whenever a dialog variable is referred to in one of these ways, the internal value stored in the variable pool is converted to an external form determined by the editing rules for the variable base type and any translation list defined for the variable class.

When the external form of a dialog variable contains characters that are incorrect for a display device, the UIM converts the incorrect characters to hexadecimal 1F characters (■). When the external form of a dialog variable contains characters that are incorrect for a printer, the UIM converts the incorrect characters to the replacement characters in effect for the printer file, or to blanks when RPLUNPRT(*NO) is in effect for the printer file.

Incorrect display characters are characters with hexadecimal values equal to hexadecimal FF or less than 40, not including hexadecimal 00, 0E, and 0F. Incorrect printer characters are the same as the incorrect display characters, except that hexadecimal 00 is also incorrect. This conversion does not take place on variable values that have been translated with a translation list.

If the dialog variable that contained the incorrect characters is used as an input field and retrieved with the Get Dialog Variable (QUIGETV) API by the program, the incorrect characters might be changed to hexadecimal 3F. This occurs if the user modifies the field or presses the Help key.

When the UIM displays a panel, it retrieves the current value for all variable fields from the variable pool or from list entries. If the user types a value in an input field, the UIM validates and translates the value according to the CLASS attribute of the associated dialog variable, and then stores the value in the dialog variable or associated list entry. The application program can determine the value entered by the user by using the Get Dialog Variable (QUIGETV) or the Get List Entry (QUIGETLE) API to retrieve the dialog variable value.

Using Variable Pool Services

The Get Dialog Variable (QUIGETV) and Put Dialog Variable (QUIPUTV) APIs are the primary interfaces for application programs to retrieve and update dialog variables. When a dialog variable is updated, the attributes of the new value must match the base type of the dialog variable. When a dialog variable is retrieved, the value is always returned to the application program in the internal form specified by the base type of the dialog variable.

No data conversion or validity checking is done when variable values are retrieved or updated using the QUIGETV and QUIPUTV APIs. For more information on these APIs, see the *System Programmer's Interface Reference*.

Some of the dialog variables defined by UIM, referred to as Z-variables, can be retrieved but not modified. The tag language does not allow a variable with only read access to be used as an input field on a panel definition. The UIM returns an exception to an application program if it attempts to update such a Z-variable using the QUIPUTV API.

Character Set and Code Page Considerations

Data that is always stored in a specific character set and code page can be converted to another character set and code page when it is displayed or printed by the UIM. If your application has data that must be converted, do the following:

- Code CHRID=PNLGRP on the CLASS tag of the variables that need to be converted. See “CLASS (Class Definition)” on page A-14.
- On the CHRID parameter of the Create Panel Group (CRTPNLGRP) command that is used to create your panel, specify either (1) the number of the graphic character set and code page of your data, or (2) *JOBCCSID. For more information on the CRTPNLGRP command, see the *CL Programmer's Guide*.

Displaying

The UIM compares the character set and code page of the device to the character set and code page of the panel group. If they are different, then outbound and inbound conversion tables are used to convert the appropriate dialog variables. If a conversion table is not available, then the Open Display Application (QUIOPNDA) API sends a diagnostic message and continues.

Display operations for Arabic and Hebrew bidirectional panel groups, which have BIDI=LTR or BIDI=RTL specified on the panel group (PNLGRP) tag, are only allowed when the device is configured to use code page 420 or 424.

Printing

The UIM compares the character set and code page of the printer file to the character set and code page of the panel group. If they are different, an outbound conversion table is used to translate the appropriate dialog variables. If CHRID(*DEV) is specified for either the panel group or the printer file, no conversion of the dialog variables is done. If a translation table is not available, the Open Display Application (QUIOPNDA) or the Add Print Application (QUIADDPA) API sends a diagnostic message and continues.

When a printer file is printed on a printer device, the character set and code page of the printer file is compared to the character set and code page that is loaded in the printer. If they are different, all the printer file data, including the constant text from the UIM tags, is translated to the character set and code page of the printer.

To minimize the number of times that character set and code page translations takes place, specify the same CHRID value on both your printer file and your panel group.

Print operations for Arabic and Hebrew bidirectional panel groups, which have BIDI=LTR or BIDI=RTL specified on the panel group (PNLGRP) tag, must have code page 420 or 424 specified for the printer file. Also, any call to the QUIADDPA API for a bidirectional panel group must have the same code page specified for the printer file as is used by the display device.

Managing a List

A UIM list is a sequential set of list entries. Each entry contains a copy of the value for one or more dialog variables. The entries in a list can be presented to the user in a scrollable area of a display. The UIM provides application programming interfaces (API) that allow an application program to perform the following operations on lists:

- Add a new entry between any two entries in the list.
- Add an entry at the beginning or end of the list.
- Update the values in a list entry.
- Remove a list entry.
- Position the current entry pointer for the list to a specific entry; several position options are available.
- Set and retrieve list attributes that control UIM processing when the list is displayed.
- Delete an active list. (Remove all entries from a list and make the list inactive for the application.)

Defining a List

The definition for each list using the list definition (LISTDEF) language tag is specified in the source for the panel group object. Attributes of the list definition (LISTDEF) tag specify the name of the list and what dialog variables should be associated with the list (that is, what variable values are to be stored in each list entry). For more information on the LISTDEF tag, see “LISTDEF (List Definition)” on page A-98.

Each entry in a list contains a copy of the values of all dialog variables associated with the list. The values of the dialog variable are copied into a list entry when the entry is first added to the list using the Add List Entry (QUIADDLE) or Add List Multiple Entries (QUIADDLM) API, and whenever the entry is updated using the Update List Entry (QUIUPDLE) API. The values in a list entry can be copied into the corresponding dialog variables when the entry is retrieved using the Get List Entry (QUIGETLE) or Get List Multiple Entries (QUIGETLM) API.

Initializing a List

All UIM APIs for processing lists require the program to specify the list name on the list object definition (LISTDEF) tag in order to identify the target list for the operation. Each list defined in a panel group is either active or inactive for each open application using the panel group. Each list is initially inactive when an application is opened using the Open Display Application (QUIOPNDA) or Open Print Application (QUIOPNPA) API. A list becomes inactive when it is deleted using the Delete List (QUIDLTL) API. A list may be active in multiple different open applications using the same panel group. A list becomes active when the first entry is added to the list using the Add List Entry (QUIADDLE), or Add List Multiple Entries (QUIADDLM) API, or when the list attributes are set using the Set List Attribute (QUISETLA) API. The maximum size of a list is approximately 16MB. The maximum number of entries that can be added to a list is based on the size of each entry.

Displaying a List

When a panel containing a list area is displayed, entries from the list are used to build a display area that appears to the user as a table. Each list area is associated with one list definition (see “LIST (List Area)” on page A-80) and contains an independent selection of columns to display. For more information on the LISTCOL language tag, see “LISTCOL (List Column)” on page A-94. A list can be referred to by more than one list area. The list area allows one list to be presented on different panels within the same open application. If more than one list area exists in a panel definition, a different list must be used for each list area.

Use the LISTCOL tag to specify the specific values presented in a list area. A list area can present all the values in the associated list entries, or it can present only a subset of the values available in each list entry. The list area the user sees contains a row for each list entry and a column for each field specified in a LISTCOL tag in the definition of each view of the list area.

You can define a list area to present the values associated with only one list entry per display line or with multiple list entries per display line. When multiple entries are shown on each display line, the display is formatted in multiple layouts with entries presented in order from top to bottom within layout columns, and from left to right between layout columns. See “Example 2: List Area with Three Layout Columns” on page A-85.

Updating a List

Values of list entries are used to fill the display for all fields in the list area; see “LISTCOL (List Column)” on page A-94. The user can update any input fields on the display, including those in the list area. If the value specified by the user satisfies all validity checks for the associated dialog variable, the corresponding value in the list entry is updated with the value specified by the user.

The UIM APIs provided to retrieve, add, and update list entries all operate by using the dialog variables associated with the list. No support is provided to directly establish or change values of list entries without referencing dialog variables. Every time a list entry is retrieved, added, or updated, the entire set of values for dialog variables is copied to or from the list entry. When the UIM refers to or updates list entries, such as processing user options in an action list, it can also update values of dialog variables that correspond with the list columns.

Each entry inserted in a list is assigned an identifier, called a **list entry handle**, that uniquely identifies the entry within the active list until the entry is removed from the list. The identifier is meaningful only for a particular combination of open application, active list, and list entry instances. An identifier has no meaning in any other open UIM application, or even in the same application if the list or the entry is deleted and then created again. Undesirable results are possible if an identifier is used outside of this definition.

Removing and Inserting an Entry from a List

After an entry is removed from a list, it can no longer be accessed by the application program, and it does not appear even as a blank line in a list area on a panel. When a new entry is added to a list, the UIM can assign the same list entry handle for that entry that was used for an entry that was previously removed from the list. An identifier value has no relationship to the logical position of the entry within the sequence defined for the entries in the list.

The UIM maintains a current entry pointer for each active list to use as a reference point for list-entry operations. The list entry manipulation APIs support a list entry handle parameter. This parameter returns to the application program the identifier where the current entry pointer for the list was positioned at the end of the operation. The UIM sets the current entry point to:

- The entry just added by the Add List Entry (QUIADDLE) or Add list Multiple Entries (QUIADDLM) API
- The list entry requested by the Get List Entry (QUIGETLE) or Get List Multiple Entries (QUIGETLM) API, or left unchanged if the requested entry is not found or not available
- The entry that preceded the entry removed by the Remove List Entry (QUIRMVLE) API

The current entry point is unchanged by the Update List Entry (QUIUPDLE) API.

The Get List Entry (QUIGETLE), Get List Multiple Entries (QUIGETLM), and Remove List Entry (QUIRMVLE) APIs may set the current entry pointer position to either the top or bottom of the list. The top is the position that is always logically before the first entry in the list, and the bottom is the position that is always logically after the last entry in the list. Each of these positions has a special identifier value for the list entry handle, but because the top and bottom are not "real" entries, they cannot be updated or removed from the list. The application program receives an error if it attempts to insert an entry before the top of the list or after the bottom of the list.

Controlling List Entries on a List Display

The application program can control what list entry appears as the topmost entry in a list area on a panel by setting the display position attribute to a valid list entry handle before the Display Panel (QUIDSPP) API is run. For example, this function can be used to position to a particular list entry specified by the user. When the display position attribute is not set by the Set List Attributes (QUISETLA) API between the time the list is initialized and the first time the list is displayed, the UIM presents the first entry at the top of the list area in the panel. For more information on the Display Panel (QUIDSPP) API, see the *System Programmer's Interface Reference*.

The display position attribute is updated whenever the user moves to a new page of the list. Any time the application program removes the entry identified by the display position attribute, the display position attribute is automatically updated to refer to the entry preceding the one removed. If there is no entry before the one removed, the display position attribute is set to the top of the list, and the next display of the panel presents the first entry at the top of the list area in the panel.

When an entry is added or updated in a list, the error state of every dialog variable associated with the list is saved with the list entry. The processing described in "Defining Dialog Variables" on page 17-1 for dialog variables in error state is also used for list entry values that are in error state. This processing concerns how validation errors are detected by the UIM and how the VARUPD attribute of the key item (KEYI) and pull-down field choice (PDFLDC) tags affects updating list values.

Improving Interactive Response Time for a List Display

To improve interactive response for a list display, the UIM list processing allows an application program to build only part of a list before it is shown to the user. Because the UIM handles scrolling lists as part of displaying a panel, without returning to the program that ran the Display Panel (QUIDSPP) API, the application program must tell the UIM whether the entries in the list represent only the top, middle, or bottom part of the complete list. If the program calls the Set List Attribute (QUISETLA) API to set the list contents attribute to a value other than ALL, and if the user attempts to page to list entries that are available to the application but not yet added to the list, the UIM calls an application program to add more list entries. The application program is also called by the UIM as part of Get List Entry (QUIGETLE) or Get List Multiple Entries (QUIGETLM) API processing if the specified entry is not found but might exist in the part of the list that has not yet been added.

When a panel is displayed that contains a list area and the associated list is either not active or contains no entries, the user sees a blank list area and a message indicates that there are no entries in the list. However, if the list attributes are set to indicate that the list is not complete, an application program is called to add entries to the list. The panel is not displayed to the user until either enough entries are added to the list to present a full display page or the application program marks the list as complete at either the top or the bottom. The application program is called not only when the list is empty but any time there are not enough entries in an incomplete list to fill a list area on the panel.

Using Action Lists and Selection Lists

The UIM supports the following types of lists:

- Action list
- Selection list
- Output only list
- Input/output list

Using Action Lists

An **action list** is a list area where the user can type option numbers to perform actions against one or more entries in the list. The definition of the UIM list displayed as an action list must include a variable defined with BASETYPE=ACTION specified on the CLASS tag. This variable is referred to as the **action variable** of the list.

To define an action list area, the application developer must specify ACTOR=UIM or ACTOR=CALLER on the LIST tag. In addition, one LISTACT tag must be defined for each option number that can be entered by the user.

For an ACTOR=UIM action list, each LISTACT tag specifies the action the UIM performs when the user types the option number and presses the Enter key. The application developer can also define an action the UIM performs when the user presses a key assigned to the PROMPT dialog command. Two types of actions can be performed: run a CL command, or call a program. If the action to be performed is to run a CL command, an action-list exit program might be needed to update the list after the CL command has performed the function for the option. No interface between UIM and a CL command allows the program called by the CL command to obtain the application handle. Therefore, if the program called by the

CL command performs a change or delete operation, an action-list exit program is required to update the list.

For an ACTOR=CALLER action list, there is no specification of an action. When the user types the option number and presses the Enter key or a function key assigned to the PROMPT dialog command, the UIM returns control to the application program. The function requested parameter contains a value which indicates that the application program should perform the actions associated with the options selected by the user.

Having the UIM as the actor for the action list is the preferred method because of the following benefits:

- The UIM performs all actions entered by the user.
- The UIM automatically displays a confirmation panel for destructive actions, such as option 4 to delete an object. No application program code needs to be written to provide confirmation support.
- The UIM redisplay the action list panel in cases where an action does not complete successfully. When the UIM receives an escape message, the UIM redisplay the list with the cursor located on the option number. The option number is shown in error. When the Exit (F3) or Cancel (F12) function is requested from a panel displayed as a result of the list option, the UIM redisplay the panel as appropriate. For more information about the UIM processing a request for Exit and Cancel when displaying an action list, see “Folding Up a List Panel” on page 17-23.

When the application program is the actor for an action list, the above processing must be done by the application program.

When a panel contains an action list and a menu bar, pull-down choices can be defined within the menu bar which operate against each selected entry in the action list. When at least one pull-down choice is defined which operates against selected list entries, the UIM allows the user to select entries by typing a valid selection character. The user selects one or more entries in the list, selects a pull-down menu from the menu bar, and then selects a choice from the pull-down menu. The UIM performs the selected pull-down choice for each entry selected by the user.

Using Selection Lists

A **selection list** is a list area in which the user can type a selection character for one or more entries in the list. A selection list is defined to allow the user to select a single entry or multiple entries in the list.

A selection list can be used for the following purposes:

- Allow the user to select an object or value from a previously displayed entry field. This type of selection list is displayed when the user positions the cursor to an entry field and requests the PROMPT dialog command. The F4 key is recommended to be assigned to the PROMPT dialog command.
- Allow the user to select entries and then perform an action defined in a pull-down menu from the menu bar.

The definition of the UIM list displayed as a selection list must include a variable defined with BASETYPE=ACTION specified on the CLASS tag. This variable is referred to as the **action variable** of the list. When the user enters a valid

selection character for a list entry, the UIM sets the action variable for that entry to 1000. A value of 1000 for an action variable always indicates that the list entry is selected.

When a panel contains a selection list and a menu bar, pull-down choices can be defined within the menu bar which operate against each selected entry in the list. The user selects one or more entries in the list, selects a pull-down menu from the menu bar, and then selects a choice from the pull-down menu. The UIM performs the selected pull-down choice for each entry selected by the user.

Using Selection Characters

The user selects entries in an action list panel that contains a menu bar or a selection list panel by typing a slash (/), or country-designated selection character, in the option or selection field for the desired list entries. The country-designated selection character is determined for each panel group when the panel group is created. The UIM retrieves the first level text of message CPX5A0C. The first two characters of this message are stored in the panel group object. These characters are the allowed uppercase and lowercase country-designated selection characters for selection lists and multiple-choice selection fields defined in the panel group.

Managing Panel Functions

The UIM supports the following panel management functions:

- Scrolling
- Limiting user capabilities
- Defining contextual help
- Command line restrictions
- Defining function keys
- Formatting panels
- Folding up panels when exit is requested
- Folding up list panels
- UIM as a request processor when displaying a panel

All operations performed by the UIM are done in a single process called a routing step. It is the application developer's responsibility to consider the effects of things such as recursion, locks, and static storage, for each of the following functions:

- Function key action
- Menu or action list option
- Pull-down choice
- Exit program
- Command entered by the user on a command line

The UIM does not guarantee that the call-sensitive effects of programs and CL commands, such as overrides and the Set Attention Program (SETATNPGM) command, are preserved when commands are run from a panel in any of the ways listed above. The effect of any command that scopes its function to the program call that used the command might be lost by the time the next command or program is called. This is because the UIM call to the function that was scoped was destroyed in the interim.

Scrolling Support

The UIM supports page up and page down scrolling of all panel information, data presentation, list, and menu areas. Multiple scrollable areas can be defined on a single panel; the UIM imposes no order on them. However, using scrollable menus is discouraged because of usability.

No left-to-right scrolling of text is provided, but the Change View (CHGVIEW) dialog command for lists can be used to show more fields.

Defining Scrollable Areas

To use the UIM scroll function, the panel must have at least one scrollable area and have function keys defined to perform the PAGEUP and PAGEDOWN dialog commands. For more information on the PAGEUP and PAGEDOWN dialog commands, see Appendix B, "UIM Dialog Commands" on page B-1.

Panels with scrollable areas must have function keys assigned to the PAGEUP and PAGEDOWN dialog commands because the UIM does not automatically enable any function keys. Normally these are the Page Up and Page Down keys,¹ but if you use a function key, F7 and F8 are recommended. The UIM does not prevent assigning different function keys to the PAGEUP and PAGEDOWN dialog commands, but it does not allow assigning the engraved page keys to anything other than their implied functions which is page up and page down.

Scrolling status information is also managed by the UIM and is displayed at the bottom of each scrollable area.

The message line is under UIM control. A plus sign (+) on the message line indicates that more messages can be viewed by pressing the Page Down key. Because you can scroll a message area, the function keys for scrolling should always be defined.

Defining Function Key Scrolling

The UIM handles all scroll- and page-key functions for UIM-defined panels; these functions cannot be overridden by the application. However, you can define other function keys that work much like scroll keys.

When a function key assigned to the PAGEUP or PAGEDOWN dialog command is pressed, the UIM scrolls the appropriate amount for the panel type. This is always a "page," but the UIM tries to avoid having data item groups, menu item groups, and selection fields split across page boundaries.

The position of the cursor determines which area to scroll. If the cursor is not in a scrollable area (except for a pull-down menu), the scroll request applies to the topmost scrollable area on the display. If the cursor is in a scrollable area, the scroll request applies to that area. The bounds of the scrollable area are the top and bottom line of that area as defined by the menu area (MENU), data presentation area (DATA), list area (LIST), and information area (INFO) language tags. For more information on these language tags, see Appendix A, "UIM Panel Group Defi-

¹ On a 5250 keyboard, these are the Rolldown and Rollup keys respectively.

nition Language” on page A-1. Titles and instruction lines are part of the area but not part of the scrollable portion of the area.

The command line is not considered part of a scrollable area, but it may be associated with a particular area on the screen. For example, a panel with a scrollable menu area has a command line and it is associated with the menu. However, for scrolling purposes, the command line is not part of the area.

Scrolling and Error Conditions

The message line always exists and is always the last scrollable area on the screen so the scroll function keys must always be active.

When scrolling the message line, the UIM does not perform any validity checking or updating of the dialog variables. When scrolling any other area, validity checking or updating of the dialog variables is performed on all input fields on the screen. The scroll function is not performed if an error is found. All input and output fields on the screen must be correct before the scroll operation can proceed.

If a page key is pressed and the operation cannot be performed, a message is displayed. For example, a message is shown if a display is already at the top when the Page Up key is pressed. The alarm sounds when trying to scroll the message line past its top or bottom.

Scrolling a List Area

List processing allows an incomplete list to be displayed. If the Page Down key is pressed and the remainder of the incomplete list does not fill the list area, the UIM calls the specified application program that handles incomplete lists. This program adds additional entries to the list or marks the list as complete at the bottom, then the program returns to the UIM. The UIM knows an incomplete list by the setting of the contents attribute of lists on the Set List Attributes (QUISETLA) API. Once the list is complete, the UIM handles scrolling without application program intervention.

A list might be incomplete at both the top and bottom. If a list has missing information above the current location, pressing the Page Up key causes the same type of processing.

Scrolling a Menu Area

The UIM attempts to keep menu item groups together but splits the group if it does not fit in the defined area. Any individual menu item or text for a menu group must fit within the available scrollable space or the panel group is not created successfully.

Scrolling an Information Area

Using the Move to Top (MOVETOP) dialog command moves a cursor-selected line to the top of the scrollable information area. This allows the user to position the information in the most readable manner. For more information on the MOVETOP dialog command, see “MOVETOP (Move to Top)” on page B-11.

Scrolling Data Item Groups

The UIM keeps data item groups together if possible. A group is split only if it does not fit within a column of the data area. When a data item group is nested inside another data item group and the outer group must be split, the UIM still attempts to keep the inner groups together. If a selection field does not fit in a column of the data area, the panel group is not created.

Data presentation areas can also be presented in multiple columns and the columns are filled from left to right. Generally, scrollable data presentation areas should not be defined with a two-column layout because the usability is poor.

Defining Contextual Help

Contextual help is provided jointly by the UIM and the system help function. Using the tag language, a panel is defined to associate help modules with different areas on the screen. When the Help key is pressed, the UIM determines which help modules to display.

When defining a panel, the user can associate help text with the following areas:

- Entire panel
- Menu bar
- Menu bar choice
- Pull-down field choice
- Specific menu item
- Specific data item
- Specific data selection field
- Choice for data selection field
- Specific list column
- List column group
- Specific function key
- Specific option in an action list
- Data group
- Data area

When the Help key is pressed, the UIM displays the help text depending primarily on where the cursor is. The rules are as follows:

Cursor Position	Help Selection Rules
On a menu item	Help for that menu item is displayed.
In a list column	<p>Help for that column is displayed.</p> <p>The left and right boundaries of a column are defined by the left and right edge of the field or heading, whichever is greater, plus one blank on either side. The top and bottom boundaries of a column are defined by the first line of the heading or column group heading and the last line where a list entry may be displayed.</p> <p>Help can be associated with a list column group rather than the individual entries. In this case, positioning within the group gives help for the entire group regardless of the specific column the cursor is in. Boundaries of column groups are defined by the sum of the individual column boundaries plus any separators between columns of the group.</p> <p>If the column for which help is being displayed is the option column of an action list, the help displayed includes the help specified for the list column and the help specified for each active list action.</p>
On any line in the function-key-definition area	Help for all active function keys is displayed.
On a message line with a message displayed	Help for that message is displayed. Help for a message is provided by the Additional Message Information display. Help for a message does not use a help module in a panel group.
On a menu bar choice	Help for that menu bar choice and all currently active pull-down choices for that menu bar choice is displayed.
On a pull-down choice	Help for that pull-down choice is displayed.
In a pull-down input field	Help for the menu bar choice (see "On a menu bar choice" above) that the pull-down is associated with is displayed. If a valid pull-down choice is entered in the field, help for that pull-down choice is displayed.
On a command line	<p>The displayed help depends on the contents of the command line.</p> <p>If the command line is associated with a menu area and the command line contains a number, help for that menu item is displayed as if the cursor were placed on that menu item. Help is available for any active menu item regardless of whether it is displayed.</p> <p>If the command line is assumed to contain a command, help for that command is displayed.</p> <p>If the command line is being treated as a parameter line, extended panel help is displayed.</p> <p>If the command line is blank, extended panel help is displayed.</p>
On a data item	<p>If help is specified for the data item, that specific help is displayed.</p> <p>If no help was specified on the data item, the data item is part of a group, and if help was specified at the group level, then data group help is displayed.</p> <p>If no help was specified on the item, the data item is not part of a group, or if no group help was specified, and help was specified on the area, then area-level help is presented.</p>
On a data group heading	The same rules apply as when the cursor is on a data item. Help is presented for the lowest level (group, area, or extended panel).
In a data area	If help is available for the area, that level of help is displayed. Otherwise, extended panel help is displayed.
Any other position	If none of the above conditions are met, extended panel help is displayed. This is true whenever the cursor is on the title line, any instruction line, and most blank spaces. Whenever there is no specific help to display, extended help is displayed.

Although HELP for a specific action on a list option or function key is never displayed, help text is individually defined for them. This allows conditioning of active options and function keys. The displayed help describes only the active function keys or options.

Command Line Restrictions

The UIM allows two sizes for a command line:

- A short command line is one line
- A long command line is two lines

Depending on whether the command line is short or long, the UIM formats and displays the command line to occupy the one or two lines preceding the function key area. This position remains unchanged regardless of scrolling, item conditioning, or the number of list entries.

Command lines are defined by the command line (CMDLINE) language tag. For more information on the CMDLINE tag, see “CMDLINE (Command Line)” on page A-24. The UIM allows specifying this tag on any panel, but does not require it.

When a command line is defined for a panel, it is recommended that the F4 key be assigned to the PROMPT dialog command and the F9 key be assigned to the RETRIEVE dialog command. This allows the user to prompt for commands entered on the command line and to retrieve previously entered commands. For more information on dialog commands, see Appendix B, “UIM Dialog Commands” on page B-1, and for more information on defining function keys, see “KEYL (Key List)” on page A-74.

The UIM sometimes associates the command line with one area on the panel. If a menu area is present, the command line is associated with the menu area. If an action list is present, the command line is associated with the action list. If neither is present, the command line is not associated with an area on the panel. The UIM does not allow two menu areas, two action lists, or a combination of these within a single panel. Also, command lines and menu option lines are mutually exclusive. For more information on the option line (OPTLINE) tag, see “OPTLINE (Option Line)” on page A-118.

Command Line Interpretation

Command lines are used to select a menu option, to run OS/400 or System/36 Environment commands, and to specify parameters used in conjunction with options on an action list. The UIM selectively interprets the character strings entered on the command line.

Many dialog commands do not require any input on the command line. The following conditions assume the action is one requiring the UIM to know the command line contents. These actions are for the ENTER, HELP, and PROMPT dialog commands. For more information on the Enter, Help, and Prompt functions, see Appendix B, “UIM Dialog Commands” on page B-1.

- For a command line associated with a menu, the UIM examines the first non-blank set of characters. If it is composed of only digits (hexadecimal F0

through F9), the command line is assumed to select a menu item. Otherwise, the command line is treated as containing a command.

- For a command line associated with an action list, the command line is assumed to contain parameters if any option is selected on any action list entry. Otherwise, the command line is treated as if it contains a command.
- For a command line associated with a panel that contains neither a menu nor an action list, the command line is always assumed to contain a command.

Exactly what function is performed next depends on what function key is pressed. For details, see the descriptions of the ENTER, HELP, and PROMPT dialog commands.

Entering Commands That Are Too Long

Commands that are too long for the command line can still be submitted by prompting for them. If the command causes an exception, the command line is displayed with the current command contents. If the full command string is too long for the command line, the display shows as much as possible and replaces the last three characters on the displayed command line with ellipses (...) to indicate continuation. The UIM still maintains the full command string internally.

Any changes to the command line causes the UIM to discard the internal version and treat the changed command line as a new request. If no change is made and the command is prompted or submitted, the internal version is not reset and is submitted as the new command string. Modification is based on a character comparison of the command line contents.

Defining Function Keys

The UIM does not automatically enable function keys; the application developer is responsible for enabling the correct set of function keys and ensuring that the correct functions are assigned to each. Function keys are defined with the key list (KEYL) and key list item (KEYI) language tags. For more information on these language tags, see Appendix A, “UIM Panel Group Definition Language” on page A-1. The UIM requires that engraved keys be assigned to their dialog command equivalent. The Help, Enter, Page Up, Page Down, Print, and Home keys must be assigned their respective dialog commands. With the exception of the PRINT dialog command, this does not prevent assigning these dialog commands to other keys as well. For example, it is recommended that the HELP dialog command be assigned to the F1 key as well as the Help key. The PRINT dialog command can be assigned only to the Print key and cannot be conditioned.

F1 through F24 can be assigned to any of the dialog commands except PRINT and MOREKEYS. The MOREKEYS dialog command can be assigned only to F24.

Formatting Function Keys

When a panel is created, the UIM determines the worst-case display of function keys and their descriptions and then allocates one or two lines accordingly. Two lines is the maximum amount of room available to display function keys. Then this space is fixed. For example, if the UIM determines that two lines are required for a specific set of conditions, then two lines are always used, even if some conditions cause only one line of description for the function keys.

Handling Function Keys and VARUPD Value

The dialog command assigned to a function key determines the function of that particular key. For more information on handling function keys, see Appendix B, "UIM Dialog Commands" on page B-1.

Function keys that are inactive due to conditioning are treated as if they are not defined. If the user presses a function key that is not defined, a message is displayed to indicate that the key is not allowed. When help is displayed for the function key area, no help information is displayed for inactive keys.

When defining a function key, the VARUPD attribute of the key list item (KEYI) or pull-down field choice (PDFLDC) language tag defines whether dialog variables and list entry values should be updated with user entered values when the function key is pressed or when the pull-down choice is selected. If any fields on the panel fail validity checking, the action associated with the function key or pull-down choice is not performed.

Although most dialog commands have a predefined, unchangeable value for VARUPD, some dialog commands do not. When a function key is assigned to one of these dialog commands, processing of that request depends on the value of VARUPD.

When VARUPD=YES is specified, all values keyed in by the user must pass validity checks. If any values fail the validity checks, the following occurs:

- Any dialog variable that does not pass validity checking is not updated.
- The specified function is not performed.
- The general exit program for the panel, if specified, is not called.
- The UIM displays the same panel again with the appropriate error messages.

When VARUPD=NO is specified, the following occurs:

- No validity checking is performed and no dialog variables are updated.
- If specified, the general exit is called. This assumes that the dialog command to be performed is one for which the exit program is normally called.
- The specified function is performed unless the general exit program indicates that the UIM should not perform the function. For more information on exit programs, see the *System Programmer's Interface Reference*.

When VARUPD=NO is specified for a dialog command, which causes the UIM to return control to the application program, variable values entered by a user are not available to the application program. The values are stored for the panel and can be shown again by using the redisplay parameter of the Display Panel (QUIDSPP) API. For more information on this, see the *System Programmer's Interface Reference*. When VARUPD=NO is specified on the CMD and CALL dialog commands, the UIM saves the screen copies of dialog variables and uses them when the panel is displayed again after the specified action completes.

Note that when VARUPD=NO is specified on the CMD and CALL dialog commands, any modification of dialog variables or list entries causes the saved version to be lost. The saved version for any field is used if the underlying dialog variable has not changed since the field was saved. For lists, the saved version of a variable in a list entry is used unless one of the following occurs:

- Underlying list entry has changed

- List entry changed position on the screen
- List view has changed

If a change was made, the saved version is lost and a new displayed value is derived from the dialog variable or list entry.

For example, assume dialog variable VARX is present on panel PANELX and is modified by the user just before pressing a function key using the CALL dialog command where VARUPD=NO. If the target of that CALL dialog command modified VARX, the saved version is lost. When the UIM displays the panel again after the call returns, the displayed version of VARX is based on the modification. This allows actions, which are unrelated to the current panel, to be performed without requiring the panel contents to pass all validity checks. VARUPD=NO should not be used with CMD or CALL dialog commands if the intended action is to use the same panel or any of its associated dialog variables, lists, or conditioning dialog variables.

Panel Formatting Concepts

When formatting UIM panels, keep the following in mind:

- The application developer does not define the format of a panel in terms of rows and columns. Instead, the UIM interprets the descriptions of the tag language and then determines where to place each element in a panel. For example, the display panel (PANEL) tag contains a description of the panel title, but no explicit definition of where the title should be displayed. The UIM determines that the title should be centered within the panel width, intensified, and treated as mixed case. The same concept applies to all other areas of the panel, though most other examples are much more complex.
- The UIM performs as much formatting as possible when the panel group is created, but the actual placement for many panel elements is determined at run time. This allows the UIM to consider screen depth and other run-time circumstances. For example, the UIM allows menu items to be conditionally displayed. These conditions are evaluated when a panel is displayed, and the format of the menu area is based on the results.

When Panel Formatting Is Performed

There is a difference between panel formatting and panel contents. **Panel formatting** refers to the organization of the various areas on the panel. **Panel contents** refers to the values of fields as dictated by dialog variable contents.

Panel formatting takes place when the panel group is compiled and again at run time.

Most decisions are made when the panel group is compiled and the information is kept in the panel group object. Those formatting decisions that cannot be made when the panel group is compiled are made during Display Panel (QUIDSPP) API processing.

An example of this distinction is a data item that is conditioned. All details about the prompt text layout, number of leader dots, field position, and formatting of possible choices are performed when the panel is created.

At run time, the QUIDSPP API processing determines whether or not the item should be displayed by evaluating the conditions and builds an internal format. Within an application defined by the Open Display Application (QUIOPNDA) and Close Application (QUICLOA) APIs, each panel has only one internal format at any time. The internal format is built the first time the panel is displayed, and the format is kept for subsequent use until the application is closed.

This does not mean that the internal format cannot change within an application. Most of the internal format does not change, but some panel elements such as menu items, list actions, and function keys, are conditioned by the application. The effect of changes to these areas are evaluated each time the panel is displayed, and then the format is updated.

Because the UIM performs many functions, such as submitting commands and calling programs, before returning control to the application that called the QUIDSPP API, the specified panel can be presented to the user several times. Each time the panel is displayed, the UIM reevaluates the panel formatting. For example, pressing a function key causes an application program to be called. When the application program returns control to the UIM, the UIM displays the panel again, but only after checking to see if the application program changed the conditions that affected the internal format. For example, if the QUIDSPP API is called to display a panel with a menu area on it, and the application program changed a dialog variable affecting the conditioning of some of the menu items, when the UIM displays the menu area again, it reflects the changes.

Application Control of Panel Formatting

The language tags allows the application developer to control panel formatting in the following ways:

- By specifying part of the formatting, such as column widths, vertical versus horizontal presentation of data areas, and depths of the areas. These specifications are fixed when the panel is compiled and cannot be changed at run time by the application. This allows you to select alternate formatting techniques and it gives the UIM information that helps reduce run-time processing.
- By specifying run-time conditioning. Dialog variables can be used to condition menu items, menu item groups, action list options, function keys, data items, pull-down choices, data selection fields, selection field choices, and data item groups. In most cases, these conditions are evaluated every time a panel is displayed to determine what should be included in the display.

Conditioning can be based on any of the following:

- Application defined dialog variable.
- UIM defined dialog variable.
- Existence of an object on the system or the user's authority to an object on the system.
- User class of the application user.
- Conditioning can be based on the setting of a user profile, a user class, or the Limit User Capability (ZLMTCPB) dialog variable. For more information on dialog variables, see "Dialog Variables Defined by UIM" on page A-159.

For more information on defining conditions, see "COND (Condition Definition)" on page A-25.

The UIM allows additional control over conditioning. The panel definition can specify which conditions are evaluated only once, when first needed, or at all times. The purpose of this is primarily related to performance. Most items are conditioned on things that are or should be fixed when the panel is first displayed, such as a user profile and authorization. Specifying that these conditions be evaluated only once avoids unnecessarily evaluating the conditions.

Limits of the Panel Formatter

The UIM provides a formatter designed to handle most normal formatting requirements. However, the formatter is not always able to match the results of manual formatting because the formatter is constrained by the run-time environment and also must handle generalized input. An example of this is formatting descriptions of function keys. Manual formatting might include changing the wording to achieve the best alignment and balance. The UIM does not have the option of changing the text length or assuming a balanced set of lengths.

Generally, the closer information is packed on a panel, the less likely the UIM formatter can match what manual formatting might achieve.

Folding Up Multiple Panels When EXIT Is Requested

To support the ability of an application to fold up multiple panels and programs as part of processing a single exit request, the operating system maintains a flag for each job indicating whether or not exit is requested. This exit flag is used in combination with the user task parameter on the Display Panel (QUIDSPP) API to cause the exit request to fold up multiple panels.

There are two ways the application program can turn on the exit flag:

1. Specify the SET parameter on the EXIT dialog command. When the UIM performs the EXIT dialog command with the SET parameter, it turns on the job's exit flag. For more information on the EXIT dialog command, see Appendix B, "UIM Dialog Commands" on page B-1.
2. Set the UIM-defined variable ZEXIT to "1" using the Put Dialog Variable (QUIPUTV) API. By setting this Z-variable, the UIM turns on the job's exit flag. The UIM automatically turns off the exit flag when it begins processing actions.

Whenever the UIM regains control after performing a panel-defined action, such as submitting a command assigned to a function key or calling a program because a menu item is selected, the job's exit flag is checked. If the flag is on and the panel is displayed as an old user task (user task parameter on the QUIDSPP API), the UIM returns control to the calling application at that point. Also, the function-requested parameter of the QUIDSPP API contains an indication that the panel display ended due to the EXIT dialog command.

If the job's exit flag is off or the panel is displayed as a new user task, nothing special happens. The UIM turns off the exit flag and displays the panel again.

If the action performed is not panel-defined, for example, when a command is entered on the command line, the exit flag is always turned off, and the processing is not affected by whether the panel is displayed as a new or old user task.

An example of how the exit flag works follows; Figure 17-1 on page 17-22 illustrates the example. Assume that program PGMX, displays PANELX that has a function key assigned to the CALL dialog command. Assume also that the program that is called, PGMY, displays another panel called PANELY. Now assume that PANELX is displayed as an old user task, the function key is pressed, and PANELY is displayed. From PANELY, the user presses the function key assigned to the EXIT dialog command using the SET parameter and control returns to PGMY. When the EXIT dialog command is processed, the UIM turns on the exit flag. If PGMY now returns control to the UIM, the UIM returns control to PGMX with an indication that the EXIT dialog command was requested. In effect, two panels are bypassed via a single exit request.




Figure 17-1. Example of Job Exit Flag

If the function key on PANELY assigned to the EXIT dialog command does not use the SET parameter, the UIM displays PANELX again because the job's exit flag is not turned on.

For more information on APIs, see the *System Programmer's Interface Reference*.

Folding Up a List Panel

For panels displayed as a result of processing a list option on an action list panel, the CANCEL, EXIT and ENTER dialog commands should work as follows.

The operating system maintains a flag for each job indicating whether or not cancel is requested. This flag is similar to the flag described for exit processing; see “Folding Up Multiple Panels When EXIT Is Requested” on page 17-21. However, the cancel flag is not used to bypass more than one panel, and it is not used in conjunction with the user task parameter on the Display Panel (QUIDSPP) API.

There are two ways the application program can turn on the cancel flag:

1. Specify the SET parameter on the CANCEL dialog command. When the UIM performs the CANCEL dialog command with the SET parameter, it turns on the job's cancel flag. (For more information on the CANCEL dialog command with the set parameter, see Appendix B, “UIM Dialog Commands” on page B-1.)
2. Set the UIM defined variable, ZCANCEL, to "1" using the QUIPUTV API. By setting this Z-variable, the UIM turns on the job's cancel flag.

It is the application developer's responsibility to ensure that pressing the Cancel key stops processing of list actions and displays the action list panel again at the point where processing was stopped. If another panel can be displayed as a result of processing a list option, the job's cancel flag should be turned on when the Cancel key is pressed by specifying the SET parameter on the CANCEL dialog command. When the UIM performs action-list processing, it checks the cancel flag after each list action completes. When the UIM finds that the flag is on, it stops processing the remaining list options and displays the list again. The option field for the list entry just processed is cleared and the options of list entries whose action was not attempted are left in the list. The UIM only checks the cancel flag after processing a list action.

It is the application developer's responsibility to ensure that pressing the Exit key stops the processing of list actions and either redisplay the action list panel at the point where processing was stopped or exits the action list panel. If another panel can be displayed as a result of processing a list option, the job's exit flag should be turned on when the Exit key is pressed by specifying the SET parameter on the EXIT dialog command. When the UIM performs action list processing, it checks the exit flag after each list action completes. When the UIM finds that the flag is on, it stops processing the remaining list options and the following occurs:

- If the action list panel is displayed as a new user task, the panel is displayed again.
- If the action list panel is displayed as an old user task, the panel is not displayed again, and control is returned to the program that displayed the action list panel with a return function indicating EXIT was used.

In either case, the option field for the list entry just processed is cleared and the options of list entries whose action was not attempted are left in the list. The UIM also checks the job's exit flag when it gets control back after processing menu options, function keys and pull-down menu choices. For more information, see “Folding Up Multiple Panels When EXIT Is Requested” on page 17-21

It is the application developer's responsibility to ensure that pressing the Enter key continues the processing of list actions. When neither the cancel flag nor the exit flag is on, the next list action is processed.

Adding a Pop-Up Window over Another Panel

You can add pop-up windows over another panel in one of the following ways:

- Use the CALL dialog command to have the UIM call an application exit program so it can add and display the window. To achieve consistent results from the End Request (ENDRQS) command, this is the recommended design.
- Use the RETURN dialog command to have the UIM return to the program that displayed the underlying panel so it can add and display the window.

The UIM does not become a request processor program when displaying a panel in a pop-up window that has a menu or action list unless the panel also has a command line. This is true even when the window is displayed over a primary panel that has a command line, action list, or menu area.

When the UIM becomes a request processor program while displaying a full-screen panel, and the application is designed to use the CALL dialog command to add and display a pop-up window, the program stack contains the UIM request processor program for the full-screen panel. However, when the application is designed to use the RETURN dialog command to add and display a window, the program stack does not contain the UIM request processor program. Therefore, the ENDRQS command causes different results depending on the internal design of the application.

As a general guideline, you should avoid designing long-running functions that run as a result of a list option or menu option from a pop-up window, unless your program is a request processor at appropriate times.

If your program becomes a request processor program and displays one or more pop-up windows by using a design that relies on the RETURN dialog command, then the code needs to clean up the window stack if the function that displayed a window is canceled by the ENDRQS command. When this happens, the Remove Pop-up Window (QUIRMVPW) API must be called once for each window to be removed from the application window stack.

If your program becomes a request processor program and displays one or more pop-up windows by using a design that relies on the CALL dialog command, then the UIM cleans up the window stack automatically if the function that displayed a window is canceled by the ENDRQS command.

For more information on a request processor program, see the *CL Programmer's Guide*.

Using Menu Bars

A menu bar is located at the top of a panel and extends the entire width of the panel. Menu bars are allowed only on panels that are 24 by 80 bytes or 27 by 132 bytes and are not allowed within a pop-up window.

The menu bar contains a list of choices that users may request. The choices are listed horizontally on one to three lines with three blanks between all choices.

When a user selects a choice by pressing the Enter key, a pull-down menu is displayed directly below the menu bar. From this menu, the user may select one choice.

Each choice in a pull-down menu does one of the following:

- Performs an action against the panel or an area of the panel as a whole. In this case, the UIM performs the action once each time the choice is selected by the user.
- Performs an action against each entry selected in an action list or selection list on the panel. In this case, the UIM performs the action once for each selected list entry. The user selects an entry or an action on a selection list by entering a slash (/) or country-designated selection character next to the desired entry.

For more information on defining menu bars, see the following language tags in Appendix A, “UIM Panel Group Definition Language” on page A-1.

- PANEL (Display Panel)
- MBAR (Menu Bar)
- MBARC (Menu Bar Choice)
- PDFLD (Pull-down Field)
- PDFLDC (Pull-Down Field Choice)

Differences Between Pull-Down Menus and Pop-Up Windows

A pull-down menu visually appears similar to a pop-up window. While pull-down menus and pop-up windows overlay a portion of the underlying panel image, a pop-up window is a separate application panel and a pull-down menu is an extension of the panel which contains the menu bar.

Visually, a pull-down menu appears different from a pop-up window in the following ways:

- The separator line appearing below the menu bar is always used as the top border of the pull-down menu. The border for a pop-up window is never part of the underlying panel.
- A pull-down menu does not have a title. A pop-up window can have a title.
- A pull-down menu does not have function key descriptions and a pull-down menu never overlays the function key descriptions of the underlying panel. Pop-up windows usually have function key descriptions and a window can overlay the function key descriptions of the underlying panel.
- A pull-down menu does not have a message line and any messages displayed as a result of the user interacting with the pull-down menu appear in the message line of the underlying panel. A pop-up window always contains a message line and any messages displayed as a result of interaction with the pop-up window appear in the message line of the pop-up window.

Pull-down menus and pop-up windows also differ in how the user is allowed to interact with each. The differences are as follows:

- When a pull-down menu is displayed, pressing the cursor tab key moves the cursor to the first unselected choice within the menu bar. Press the tab key again to move the cursor to the next unselected choice, until the cursor is moved back to the pull-down menu. When a pop-up window is displayed, pressing the cursor tab key moves the cursor to the next input field defined

within the pop-up window. The tab key never moves the cursor outside the border of the pop-up window.

- When a pull-down menu is displayed, all the function keys defined for the underlying panel are active. Each function key performs the same function as if the pull-down menu was not displayed with the following exceptions:
 - The Enter key, or any other key assigned to the ENTER dialog command, is used to process the action assigned to the pull-down choice number selected by the user.
 - Any key assigned to the CANCEL dialog command causes the pull-down menu to be removed and the underlying panel to be redisplayed. Normally, F12 is the key assigned to the CANCEL dialog command.
 - The Page Down and Page Up keys, or any other key assigned to the PAGEDOWN or PAGEUP dialog commands, are not allowed when the cursor is within the pull-down menu.
 - Any key assigned to the PROMPT dialog command is not allowed when the cursor is within the pull-down menu. Normally, F4 is the key assigned to the PROMPT dialog command.

For cursor-sensitive function keys, the user is allowed to move the cursor outside the border of the pull-down menu and press the function key. In this case, the UIM removes the pull-down menu and processes the action assigned to the function key as if the pull-down menu was not displayed at the time the user pressed the function key. Cursor-sensitive function keys are any keys assigned to the dialog commands in the following table. The dialog commands in the table are usually assigned to the keys as shown.

Table 17-2. Cursor-Sensitive Function Keys Assigned to Dialog Commands

Dialog Command That May Have a Cursor-Sensitive Function Key Assigned	Dialog Command Is Usually Assigned to This Key
HELP	Help
PAGEDOWN	Page Down
PAGEUP	Page Up
MOVETOP (move to top)	F10
CHGVIEW (change view)	F11
PROMPT	F4

As an example, assume that a pull-down menu is displayed. If the user moves the cursor to a field in the underlying panel, outside the border of the pull-down menu, and presses the Help key, the UIM removes the pull-down menu and displays the contextual help defined for the field.

When a pop-up window is displayed, only the function keys defined for the panel displayed within the window are active. When any function key is pressed and the cursor is located outside the border of the pop-up window, the window is redisplayed and the alarm sounds to indicate that the cursor is not allowed outside the window.

Further differences between pull-down menus and pop-up windows are in how the application developer can control them. Following are the differences:

- A pull-down menu can only contain a list of numbered choices. The application developer defines each choice, which appears in the pull-down menu, and also

assigns an action for each choice. When the user selects one of the choices, the UIM performs the action defined for that choice. A pop-up window can contain any panel element, which can appear in a full-screen panel, with the following exceptions.

- A pop-up window cannot contain a field (dialog variable) which spans multiple lines of the display. Every field must fit within the width of the window.
- A pop-up window cannot contain a menu bar.
- Based on user interaction, the UIM decides when a pull-down menu is displayed and removed. The application program cannot control when a pull-down menu is displayed or removed; nor can the application program control the location or size of the pull-down menu when it is displayed. The application program has control over when and where a pop-up window is displayed and removed. For more information about displaying pop-up windows, see “Adding and Removing Windows” on page 17-28. The size of a pop-up window is specified by the application developer by specifying the WIDTH and DEPTH attributes on the PANEL tag for the panel to be displayed in the window.

Using Pop-Up Windows

A pop-up window is information that overlays part of the display. The user can view information inside the window and the portion of the screen that is not overlaid by the window. However, only the window is active; the user cannot work with the underlying panel. When more than one window is displayed, only one window is active at a time.

Following are some principles of pop-up windows:

- Windows contain a message line, and if the message exceeds the boundary of the window, the message is truncated. To indicate the message is truncated, an ellipsis (...) is added to the end of the message. To see the rest of the message, place the cursor on the message line of the window and press the Help key.
- When a window is displayed, its size and location cannot be changed.
- The cursor is positioned in the active window. If the user moves the cursor outside the active window and presses any function key except Print, the display alarm sounds and the cursor moves back to its previous window location.
- When you leave a window, you are returned to the underlying display at the location where you were before you requested the window.
- The Print key applies to the entire display, not just to the current window.

Defining Application Windows

Application-defined windows can be displayed over UIM and DDS panels.

Application-defined means that the application developer defines the exact size of the window on the display panel (PANEL) tag on the panel group source. The location of the window is specified when the application program calls the Add Pop-Up Window (QUIADDPW) API.

Adding and Removing Windows

The UIM maintains a stack to keep track of windows. Windows can be added to the stack in one of the following ways:

- The UIM adds windows to the stack in order to display help information and command line windows.
- The application developer can request that a window be added to the stack to display a window.

Windows can be removed from the stack internally by the UIM or by the application developer.

Adding and removing windows is controlled by the application program, but the UIM provides a set of APIs to manipulate these windows.

To display a window, an application program must first use the Add Pop-Up Window (QUIADDPW) API to inform the UIM that the next display is for a window. A window displaying a selection list should use field-adjacent positioning, while a window displaying a prompt for positioning a list should use offset positioning.

The QUIADDPW API call does not specify the panel to be displayed in the window. It specifies only the location information necessary to position the window.

A window can be added to a display only after a full-screen panel is determined. A full-screen panel is determined by calling the Display Panel (QUIDSPP) or Set Screen Image (QUISETSC) API. Once a full-screen panel is displayed within an application, a window can be added to the application.

To position a selection list window using field-adjacent positioning, the programmer must specify the name of the field for which the selection window is being displayed. When a panel is displayed within the window, the UIM uses a set of general window positioning rules to position the window so that, if possible, the window does not overlay the specified field.

For a window displaying the prompt for positioning a list, offset positioning should be specified on the Add Pop-Up Window (QUIADDPW) API call. The upper left corner of the window is positioned below and indented to the right of the upper left corner of the underlying panel.

Once a window is added to the display, the Display Panel (QUIDSPP) API is used to display a panel within the window. When the QUIDSPP API is called, the UIM performs the following operations:

1. Determines the actual location for the window. The location is determined according to the location information provided by the call to the QUIADDPW API.
2. Formats the panel.
3. Merges the newly formatted panel and window border with the underlying panel image.
4. Displays the merged panel output.

The end user must interact with the most recently displayed window before interacting with any other underlying panel or window.

The QUIRMVPW API does not cause the UIM to automatically display the underlying panel again. The panel is displayed again without the window on the next call to the QUIDSPP API, or when the UIM automatically displays a panel again after processing a function or running an exit program.

A command line in a window allows the user to enter commands without requiring any reserved space on the panel for a permanent command line. The UIM provides support to display a command line in a window. For UIM application panels, this is done by assigning a function key to the CMDLINE dialog command. The F9 key is recommended. The CMDLINE dialog command is also allowed as the action for a choice in a pull-down menu. When a function key or pull-down field choice is assigned to the CMDLINE dialog command, the key or choice can be conditioned based on the ZLMTCPB dialog variable. Doing this only allows the user to get to the command line window if the user does not have limited capabilities.

Keep the following in mind when using a command line in a window:

- The following example shows a command line pop-up window used on a display.

```

: .....
:                               Command                               :
: .....
: ==> _____
: F4=Prompt  F9=Retrieve  F12=Cancel
: .....

```

UIM as a Request Processor Program When Displaying a Panel

Sometimes the UIM becomes a request processor program when displaying a panel. When the UIM becomes a request processor program, your application is isolated from commands entered on the command line. For example, if the End Request (ENDRQS) command is used to cancel a command entered on the command line, the UIM handles the end request and the application program is not ended. The following types of panels cause the UIM to automatically become a request processor:

- Any panel with a command line. The UIM is required to be a request processor when submitting a command from a command line. When the panel has a command line, the UIM becomes a request processor program so that all functions it performs for the panel work consistently for the End Request (ENDRQS) command.
- A full-screen panel with an action list. Most action list panels have a command line to allow parameters for list options. So for consistency, the UIM becomes a request processor program for all full-screen panels with an action list. This allows ACTOR=UIM action lists without a command line to work in the same way as those that have one when the ENDRQS command is requested while a list option is being processed. This allows a user to perform the ENDRQS command to cancel a long-running option without also canceling the action list panel and the program that displayed it. Any unprocessed list options are left pending in the action list when the ENDRQS command is used to cancel a UIM-processed list option.

If you code ACTOR=CALLER for an action list, you should consider having your code become a request processor program for consistency with the UIM.

- A full-screen panel with a menu area. Most menu panels have a command line. For consistency, the UIM becomes a request processor program for all panels with a menu area. This allows menu panels without a command line to work in the same way as those that have one when the ENDRQS command is requested while a menu option is being processed. This allows a user to perform the ENDRQS command to cancel a long-running option without also canceling the menu panel and the program that displayed it.

If you code the RETURN dialog command for a menu item, you should consider having your code become a request processor program for consistency with the UIM.

For more information on a request processor program, see the *Programming: Control Language Programmer's Guide*, SC41-8077.

Printing Concepts

The UIM allows applications to define and generate printed output to the level required for the OUTPUT(*PRINT) parameter on a CL command. This support provides a hardcopy form of information in a format similar to that displayed by the UIM, but it does not allow for generalized printing via the UIM.

The application developer does not need to provide a print panel and a display panel. However, it is recommended that both print and display panels be placed in the same panel group. For printing panels, use the Print Panel (QUIPRT) API.

A panel group can be opened for either display or print. Once a panel group has been opened for display, it can also be used to produce printed output. The Add Print Application (QUIADDPA) API is provided to open a printer file for an already open display application, and the Remove Print Application (QUIRMVPA) API closes the printer file that was opened with the QUIADDPA API.

For more information on APIs, see the *System Programmer's Interface Reference*.

The UIM tag language is used to define print head panels and print panels. The print head panel, created with the print head (PRTHEAD) tag, defines the header information that is printed at the top of each page. The print panel, created with the print panel (PRTPNL) tag, defines the different panel areas to be printed. Both the print head panels and print panels must be printed for the same open application.

The following areas make up a printed listing and the example that follows is how it would look:

Title	The title consists of two lines printed at the top of every page. The title lines contain information such as the output title, time and date, system name, product information, and page number. All of the information in the title lines is defined by the print head panel.
Prolog	(Optional.) The prolog section is printed only on the first page and comes right after the title lines. The prolog section is used for such things as indicating what parameters were specified to print the output. The prolog section is defined as the portion of the print head panel that has TYPE=PROLOG specified on the data presentation area (DATA) or information area (INFO) tag.
Header	(Optional.) The header section is used to print the same data on every page. This data usually includes things such as the file name, library, and member name for which information is printed. This section comes after the prolog on the first page and after the title lines on all remaining pages. The header section is defined as the portion of the print head panel that has TYPE=NORMAL specified or defaulted.
Page body	The page body is made up of one or more panels of information. These panels of information appear very similar to panels that are used to display information on a display. These panels can contain data, information, and list areas. Menu areas and selection fields cannot be defined for printing. Because there is no such thing as a scrollable print panel, all information and data associated with the panel is printed via the Print Panel (QUIPRT) API.
Trailer	The trailer is a single line of text that is printed after the last panel area on the last page. This trailer usually says something like <div style="margin-left: 40px;">E N D O F L I S T I N G</div> <div style="margin-left: 40px;">or</div> <div style="margin-left: 40px;">E N D O F S O U R C E</div>




Figure 17-2. Example of Printout

Printing a Print Head Panel

When a print head (PRTHEAD) panel is printed by calling the Print Panel (QUIPRTP) API, the heading is formatted and saved until a print panel is printed.

Printing a Print Panel

When a print panel (PRTPNL) is printed by calling the Print Panel (QUIPRTP) API, the UIM:

1. Formats one page of data and prints it.
2. Formats the next page of data and prints it.
3. Formats page by page until the entire panel is printed.
4. Formats and prints the last part of the panel on a partial page. The next call to the QUIPRTP API causes the rest of the partial page to be formatted and printed, assuming that no page eject is requested. If the first area of this next panel does not fit on one page, this area is printed on the next page. This causes the panel title, top separator, and area title, if one exists, to be printed on the next page.

Using Blank Lines for Separating

A single blank line is inserted in the following places by the UIM:

- After the second title line of every page
- After list column and group headings
- After data column headings
- Before the trailer line

Fonts and Highlighting

Only printer files created without using a DDS source may be used by the UIM. No special fonts are supported. The H1 through H4 heading tags are printed as normal text with no highlighting or underlining. H1 headings are centered.

The HP0 through HP9 highlighting phrase tags are not allowed in print panel definitions. Highlighting, underline, and double strike are not supported. (A **double strike** is when the printer prints a letter and then prints the same character or another character in the same position.)

Printing the Trailer

The one-line trailer is specified using the print trailer message (PRTTRAIL) tag in a print head panel. This is a one-line statement such as:

'E N D O F L I S T I N G'. It is printed at the end of an application's printout when the Remove Print Application (QUIRMVPA) or Close Application (QUICLOA) API is called.

Defining Prolog Areas

A print head panel (PRTHEAD) is used to define the prolog and header sections. The print head panel can contain only information and data areas. List areas are not allowed.

With TYPE=PROLOG specified, the prolog section consists of one or more data areas, one or more information areas, or a combination of both. The prolog section is printed only from the first print head panel that is printed for each open printer file. An attempt to print a print head panel containing a prolog section causes an escape message if the print head panel is not the first one printed for an open printer file.

Defining Header Areas

With TYPE=NORMAL specified, the header section is made up of one or more data areas, one or more information areas, or a combination of both. The total depth of the information and data areas in the header section must be less than or equal to six lines.

The minimum page length is 18 lines. To ensure that there is room for data on each page, with the possible exception of the first, the UIM limits the combined total depth of the prolog and header sections to 14 lines. If these maximums are not followed, a compile-time error message occurs.

A title line must be printed at the top of every page, so the UIM requires that a print head panel be printed before any other print panels. The Print Panel (QUIPRTP) API needs to be called only once for the print head panel for each printer file. After that, the same header information is printed on each page of the printer file. To

change the header information, call the QUIPRTP API again for the same or different print head panel.

Using the Page-Eject Function During Printing

An automatic page eject occurs when a print head panel is printed after printing a print panel. However, even if eject is specified on the print panel (PRTPNL) tag, when the next print panel is printed, it does not cause a second page eject.

When a print head panel is processed by the Print Panel (QUIPRTP) API, it is not actually printed until another QUIPRTP API is called for a print panel. Therefore, if the QUIPRTP API is called for five different print head panels before the QUIPRTP API is called for a print panel, only the last print head panel affects the listing.

Sharing and Overriding Printer Files

The UIM allows multiple UIM applications to print to the same printer file by opening the printer file for sharing. However, the UIM does not share information between multiple UIM applications.

If multiple UIM applications are printing to the same printer file, it is possible to have more than one prolog section per printer file, because a prolog section, if there is one, is printed once per open application.

Care must be taken when working with a shared file to avoid inadvertently sharing with a higher or previous program in the program stack. Sharing a printer file between a UIM application and an application using a DDS record format file does not work. The shared file is closed when the last application sharing the shared file uses a Close Application (QUICLOA) or Remove Print Application (QUIRMVPA) API.

The printer file is opened to allow most overrides.

Printing Double-Byte Character Set (DBCS) Considerations

The UIM checks the TXTMODE attribute of the panel group (PNLGRP) tag to determine if double-byte data might be printed. If it might be printed, the UIM opens the printer file to contain DBCS data. For more information on DBCS, see Appendix D, "Double-Byte Character Set Support for Displays" on page D-1.

Part 4. Programming Help Displays


Chapter 18. Making Online Help Information Accessible for Your Display File	18-1
Enabling the Help Key	18-2
Choosing between Panel Groups, Documents, and Records for Help	18-2
Defining Which Areas of Your Display Need Online Help Information	18-3
Specifying Panel Groups for Help in Your Display File	18-6
Copying QUSRTOOL Examples That Specify Help Using Panel Groups	18-9
Specifying Documents in Your Display File	18-9
Specifying Records in Your Display File	18-12
Entering the Records That Contain the Help Information	18-14
Using Records and Documents for Help in the Same Display File	18-15
Understanding the Restrictions on Records	18-15
Paging between Help Displays That Use Records	18-16
Understanding How the System Pages Help Displays	18-16
Displaying Secondary Online Help Information	18-17
Returning Control to Your Program after Pressing the Help Key	18-20
Returning Control to Your Program after Showing the Help Display	18-20
Returning Control to Your Program without Showing the Help Display	18-21
 Chapter 19. Making Online Help Accessible for Your Panel Group	19-1
Definitions and Explanations	19-1
Help in a List Area	19-3
Coding Help	19-4
Help in a Menu Area	19-4
Coding Help	19-5
Help in a Data Area	19-6
Coding Help	19-8
Help in a Menu Bar Area	19-11
Coding Help	19-12
Help in a Function Key Area	19-13
Coding Help	19-14
 Chapter 20. Defining Online Help Information	20-1
Defining Online Help Information in a Panel Group	20-1
Entering the UIM Source for a Panel Group for Help	20-1
Organizing a Panel Group with Help Modules	20-2
Using the Information in a Help Module More Than Once	20-2
Using a Help Module Contained in a Different Help Panel Group	20-3
Emphasizing and Formatting the Text within a Help Module	20-4
Adding InfoSeeker Tags to a Help Panel Group	20-6
Linking Help Modules	20-12
Creating and Deleting Panel Groups	20-14
Assigning Panel Groups as Help for Commands	20-15
Using Panel Groups in a Search Index	20-15
Creating a Search Index	20-15
Adding Entries to a Search Index	20-16
Removing Entries from a Search Index	20-16
Deleting a Search Index	20-16
Copying QUSRTOOL Examples That Define Help in a Panel Group	20-17
Defining Online Information in a Document	20-17

Creating a Document for Help	20-17
Viewing the Document without Pressing the Help Key	20-18
Defining Online Help Information in a DDS Record	20-18

Chapter 18. Making Online Help Information Accessible for Your Display File

Application help is a function provided by the system that lets you define online help information for the records in a display file and then presents that help to the user when the Help key is pressed.

The following illustration shows what happens when the Help key is pressed and online help information is available and accessible:



Note: Caution is advised when using application help with multiple display stations acquired to the file because all display stations wait for the completion of the application help display.

To provide online help information for your display, you need to do the following:

- Add to your display file the necessary DDS keywords to make online help information accessible for your display. This chapter provides instructions for adding these keywords.

- Define the help information that the user sees using either a panel group, document, or record. Chapter 20, “Defining Online Help Information” on page 20-1 provides instructions for defining the help information.

Information about DDS keywords

For more information about the DDS keywords described in this chapter, see the *DDS Reference*.

Enabling the Help Key

If online help information is available for your display, you must enable the Help key on the keyboard. To enable the Help key, specify the HELP keyword at the file or record level of your DDS source.

Choosing between Panel Groups, Documents, and Records for Help

You can define online help information by using one of the following:

Table 18-1. Different Ways to Define Online Help Information

Method	Description
Panel group	Objects into which user interface manager (UIM) source is entered
Documents	Objects created using AS/400 OfficeVision/400
Records	A set of DDS keywords contained in a source file member

Each method has characteristics that can help you choose the method that will work best for you. The following table lists these characteristics and the method or methods that they apply to:

Table 18-2 (Page 1 of 2). Characteristics of Different Methods of Online Help Information


Characteristic	Panel Groups	Documents	Records
Accessible through H specifications for DDS-described displays	X	X	X
Allows cursor-sensitive help	X	X	X
Allows extended help	X	X	X
InfoSeeker function available	X		
Windows used	X		
Hypertext linking available	X		
Used by system displays	X		
Can be used for command help	X		
Word processing functions, such as spell checking, available	X (See note.)	X	
Bookmark and exit function available (allows you to return to the same location in the help the next time you press the Help key)		X	

Table 18-2 (Page 2 of 2). Characteristics of Different Methods of Online Help Information

Characteristic	Panel Groups	Documents	Records
Allows printing of help information	X	X	X
Index for displayed information available		X	
Table of contents for displayed information available		X	
Can be placed in same member as display source			X
Same source type as display source			X
QUSRTOOL example available	X		
Option indicators allowed	X	X	X
Supports DBCS online help information	X		X
Right-to-left and left-to-right orientation of text	X		
Supported for acquired devices			X

Defining Which Areas of Your Display Need Online Help Information

You can define the display file so that you supply the online help information for all or part of a display, as represented by the shaded areas in the following figure:



RV2W020-2

1 Contextual help

Information for rectangular areas that are defined by a record or part of a record format. Contextual information describes one or more fields on a display.

2 Extended help

All information for the entire display, beginning with the information about the purpose and use of the display and followed by contextual help for each field. Extended help is displayed when you press the Help key on an area of the display that does not have contextual help defined for it. If your online help information is defined using panel groups, you can also reach extended help from contextual help by pressing F2.

The cursor location is determined when the Help key is pressed. If the Help key is enabled and the cursor is in any active help area, the online help information associated with that help area is displayed.

Each help area on a display is defined in the DDS source using the following:

H specification

Defines help for the containing record. An H in column 17 of the DDS source indicates a help specification level. The help specifications are defined before the first field in the record.

Help Area (HLPARA) keyword

Defines a help area by giving the upper-left row column and lower-right row column of the rectangular area. These coordinates must be located in the screen area, but are not required to be in the record area.

If *RCD is specified for the HLPARA keyword, the help is associated with the entire record area, which includes all columns in the lines occupied by the record. When the cursor is located in the record area and the Help key is pressed, the online help information from the record on the HLPRCD keyword is displayed.

Help (HLPxxx) keyword

Defines whether a panel group (HLPPNLGRP), document (HLPDOC), or record format (HLPRCD) contains the actual online help information that you see when you press the Help key.

The following illustration shows how H specifications are entered in your DDS source:

|...+...**1**...+...**2**...+...**3**...+...**4**...+...**5**...+...**6**...+...**7**...

H HLPARA(*RCD)
HLPxxx(required-variables)

Figure 18-1. Sample H Specification in DDS Source

This sample DDS defines help for a record. The required variables for the help keyword depend on whether HLPxx is defined as a HLPPNLGRP, HLPDOC, or HLPRCD keyword. Only one help keyword can be defined for the file, but you can specify one or more H specifications for a record.

The order of H specifications is important because the first match found is selected. Therefore, the more specific HLPARA locations should be listed first.

The following sample display is defined with two record formats, HEADER and SINFO:

1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24

Add, Update, Display Supplier

Enter new or existing name: _____

Address: _____
City: _____
State: _____

} Record
HEADER
(lines 5-7)

} Record
SINFO
(lines 15-17)

RV2W022-3

The following table shows one way to define the online help information for the sample display:

Table 18-3. Help for Sample Display

Location on Display	Location in DDS Source	Description of Help Provided
Lines 5-7	Entire record format HEADER	Help is specified for the whole record
Line 15	First line in record format SINFO	Help is specified for the line only
Line 16	Second line in record format SINFO	Help is specified for the line only
Line 17	Third line in record format SINFO	Help is specified for the line only
Remaining lines	Areas in display file that are not defined with record formats	Help is specified for the whole file

Depending on the help method you plan to use, continue with any of the following to define H specifications in your DDS source:

Panel groups (UIM)

“Specifying Panel Groups for Help in Your Display File” on page 18-6

Documents (OfficeVision/400)

“Specifying Documents in Your Display File” on page 18-9

Records (DDS)

“Specifying Records in Your Display File” on page 18-12

To compare and contrast the different ways to create online help information, see “Choosing between Panel Groups, Documents, and Records for Help” on page 18-2.

Specifying Panel Groups for Help in Your Display File

The HLPPNLGRP keyword in DDS identifies the panel group that contains online help information for a display. The HLPPNLGRP keyword may be specified in an H specification or at the file level. To use the HLPPNLGRP keyword, you need to know the name of the help module and the name of the panel group and library that contains that help module.

Several other DDS functions are available for use with panel groups. The functions and their associated DDS keywords are described in the following table:

Table 18-4. Other DDS Keywords for UIM Help

Function	DDS keyword	Description
Defining the name of the help screen	HLPTITLE	The text to be displayed on the first line of the help display is defined with the file- or record-level DDS keyword HLPTITLE (Help Title). This text should be the name of the display that is displayed when the Help key is pressed. The HLPTITLE keyword must be used in the display file. This keyword is used only on full-screen displays of help when no help title is specified in the help source.
Indicating full-screen online help information	HLPFULL	Using the DDS file-level HLPFULL (Help Full) keyword, the UIM-defined online help information for the application is displayed in a full-screen replacement display rather than in a window. When the HLPFULL keyword is not specified, the help is displayed in a window unless the user's profile specifies otherwise.
Excluding panel group help as secondary help information	HLPEXCLD	The HLPEXCLD keyword excludes a help panel group with a duplicate name from being displayed within extended help. To do this, place HLPEXCLD on all but the first H specification that names an identical help panel group. HLPEXCLD indicates that the information associated with the H specification is not displayed as part of the extended help. When the HLPEXCLD keyword is not specified, extended help consists of the information associated with both the file-level HLPPNLGRP keyword (if any) and the HLPPNLGRP keywords on all active H specifications. At least one help panel group name must not specify the HLPEXCLD keyword.
Enabling the InfoSeeker function	HLPSCHIDX	The InfoSeeker function is enabled, and the index search object used for the InfoSeeker function is specified by the file-level DDS keyword HLPSCHIDX (Help Search Index).

Using the sample display from “Defining Which Areas of Your Display Need Online Help Information” on page 18-3, the following online help information is defined for each help area:

1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24

Add, Update, Display Supplier

Enter new or existing name: _____

Address: _____

City: _____

State: _____

} Record
HEADER
(lines 5-7)

} Record
SINFO
(lines 15-17)

RV2W023-5

Table 18-5. Help for Sample Display Using Panel Groups

Location on Display	Location in DDS Source	Name of Help Module in Panel Group SMPPNL in Library SMPLIB
Lines 5-7	Entire record format HEADER	HLPCMPY
Line 15	First line in record format SINFO	HLPADDR
Line 16	Second line in record format SINFO	HLPCITY
Line 17	Third line in record format SINFO	HLPST
All shaded areas	Areas in display file that are not defined with records	SUPHELP

The following DDS source shows how the help areas are defined for the sample display using panel groups:

...+....1....+....2....+....3....+....4....+....5....+....6....+....7...			
			HELP
			HLPPNLGRP(SUPHELP SMPLIB/SMPPNL)
			HLPTITLE('ADD,UPDATE,DISPLAY SUPPLIEF
R HEADER			OVERLAY
H			HLPARA(*RCD)
			HLPPNLGRP(HLPCMPY SMPLIB/SMPPNL)
		5 25	'ADD, UPDATE, DISPLAY SUPPLIER'
		7 10	'ENTER NEW OR EXISTING NAME:'
CONAME	10A	I 7 47	
R SINFO			OVERLAY PROTECT
H			HLPARA(15 1 15 79)
			HLPPNLGRP(HLPADDR SMPLIB/SMPPNL)
H			HLPARA(16 1 16 79)
			HLPPNLGRP(HLPCITY SMPLIB/SMPPNL)
H			HLPARA(17 1 17 79)
			HLPPNLGRP(HLPST SMPLIB/SMPPNL)
		15 10	'ADDRESS:'
ADDR	30A	B 15 32	
		16 10	'CITY:'
CITY	10A	B 16 32	
		17 10	'STATE:'
STATE	2A	B 17 32	

Figure 18-2. Sample DDS Source Showing HLPPNLGRP

The file-level help in SUPHELP provides extended help for the display (when the cursor is not located in the record area for either HEADER or SINFO) because HLPARA(*RCD) is the location specified on the H specification.

The panel groups that contain the online help information must be created by using the UIM source from a source file member. More information about creating panel groups is found in “Defining Online Help Information in a Panel Group” on page 20-1.

Note: HLPPNLGRP and HLPBCD are not allowed in the same display file;
HLPPNLGRP and HLPDOC are also not allowed in the same display file.

Defining Panel Groups with Option Indicators: The HLPPNLGRP keyword can be specified with option indicators. In the following example, assume the SINFO record has indicator 90 on and the cursor is in the help area defined for the H specification. When the Help key is pressed, the panel group HELP1 is displayed. If indicator 90 is off, panel group HELP2 is displayed.

The DDS for this file is:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
                                HELP
                                OVERLAY
                                5 25'ADD, UPDATE, DISPLAY SUPPLIER'
                                7 10'ENTER NEW OR EXISTING NAME'
                                10A I 7 47
                                CONAME
                                R SINFO
                                H
90                                HLPARA(15 9 15 61)
                                HLPNLRGP(HELP1 SMPLIB/SMPPNL)
                                H
N90                             HLPARA(15 9 15 61)
                                HLPNLRGP(HELP2 SMPLIB/SMPPNL)
                                15 10'ADDRESS'
                                ADDR
                                30A B 15 32

```

Figure 18-3. Sample DDS Source Showing HLPNLRGP and Option Indicators

Copying QUSRTOOL Examples That Specify Help Using Panel Groups

The QUSRTOOL library provides four sample DDS-described displays that access online help information using panel groups. You can copy the source for these sample displays into a library of your choosing and then tailor them for your own use. For more information about these sample displays, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Specifying Documents in Your Display File

Online documents used as help information are created by using the word processing function of the OfficeVision/400 licensed program. The document and folders do not have to exist when you create the display file. More information about creating documents for help is found in “Defining Online Information in a Document” on page 20-17.

The source of the online help information that is identified by a help document in DDS source is specified with the help-specification or file-level DDS keyword HLPDOC (Help Document). To use the HLPDOC keyword, you need to know the names of the document and folder (or folders) where the information is stored and the help information label name that marks the specified location in the document where the information is located.

Using the sample display from “Defining Which Areas of Your Display Need Online Help Information” on page 18-3, the following online help information is defined for each help area:

1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24

Add, Update, Display Supplier

Enter new or existing name: _____

Address: _____

City: _____

State: _____

} Record
HEADER
(lines 5-7)

} Record
SINFO
(lines 15-17)

RV2W023-5

Table 18-6. Help for Sample Display Using HLPDOC

Location on Display	Location in DDS Source	Name of Help Information Label (See Note.)
Lines 5-7	Entire record format HEADER	HLPCMPY
Line 15	First line in record format SINFO	HLPADDR
Line 16	Second line in record format SINFO	HLPCITY
Line 17	Third line in record format SINFO	HLPST
All shaded areas	Areas in display file that are not defined with records	SUPHELP

Note: All help information labels are contained in sample document HELP.DOC in sample folder HELPFLD.

The following DDS source shows how the help areas are defined for the sample display using help documents:

```

|...+...1...+...2...+...3...+...4...+...5...+...6...+...7...
                                HELP
                                HLPDOC(SUPHELP HELP.DOC HELPFLD)
                                OVERLAY
                                HLPARA(*RCD)
                                HLPDOC(HLPCMPY HELP.DOC HELPFLD)
                                5 25'ADD, UPDATE, DISPLAY SUPPLIER'
                                7 10'ENTER NEW OR EXISTING NAME:'
                                CONAME      10A  I  7 47
                                R SINFO
                                H                                OVERLAY PROTECT
                                HLPARA(15 1 15 61)
                                HLPDOC(HLPADDR HELP.DOC HELPFLD)
                                HLPARA(16 1 16 41)
                                HLPDOC(HLPCITY HELP.DOC HELPFLD)
                                HLPARA(17 1 17 33)
                                HLPDOC(HLPST HELP.DOC HELPFLD)
                                15 10'ADDRESS:'
                                ADDR      30A  B 15 32
                                16 10'CITY:'
                                CITY      10A  B 16 32
                                17 10'STATE:'
                                STATE     2A   B 17 32

```

Figure 18-4. Sample DDS Source Showing HLPDOC

The file-level help in SUPHELP is used to provide extended help for the display (when the cursor is not located in the record area for either HEADER or SINFO) because HLPARA(*RCD) is the location specified on the H specification.

The DDS keywords HLPDOC and HLPPNLGRP are not allowed in the same display file. The keywords HLPDOC and HLPRCD are allowed in the same display file; however, several considerations apply when mixing the two keywords. For more information about HLPRCD and these considerations, see “Specifying Records in Your Display File” on page 18-12.

Defining Documents with Option Indicators: The HLPDOC keyword can be specified with option indicators. In the following example, assume the SINFO record is put with indicator 90 on and the cursor is in the help area defined for the H specification. When the Help key is pressed, the HELP#1 document in folder HELP.F1, starting at location CITY1, is displayed. If indicator 90 is off, the HELP#2 document in folder HELP.F1, starting at location CITY2, is displayed.

The DDS for this file is:

...+....1....+....2....+....3....+....4....+....5....+....6....+....7...			
			HELP
	R HEADER		OVERLAY
		5 25	'ADD, UPDATE, DISPLAY SUPPLIER'
		7 10	'ENTER NEW OR EXISTING NAME'
	CONAME	10A I 7 47	
	R SINFO		OVERLAY PROTECT
	H		HLPARA(15 9 15 61)
90			HLPDOC(CITY1 HELP#1 HELP.F1)
	H		HLPARA(15 9 15 61)
N90			HLPDOC(CITY2 HELP#2 HELP.F1)
		15 10	'ADDRESS'
	ADDR	30A B 15 32	

Figure 18-5. Sample DDS Source Showing HLPDOC and Option Indicators

Specifying Records in Your Display File

The source of the online help information that is identified by a help record in DDS source is specified with the help-specification or file-level DDS keyword HLPRCD (Help Record).

HLPRCD and HLPPNLGRP are not allowed in the same display file.

Using the sample display from “Defining Which Areas of Your Display Need Online Help Information” on page 18-3, the following online help information is defined for each help area:

1			
2			
3			
4			
5		Add, Update, Display Supplier	} Record HEADER (lines 5-7)
6			
7	Enter new or existing name:	_____	
8			
9			
10			
11			
12			
13			
14			
15			
16	Address:	_____	} Record SINFO (lines 15-17)
17	City:	_____	
18	State:	_____	
19			
20			
21			
22			
23			
24			

RV2W023-5

Table 18-7. Help for Sample Display Using HLPRCD

Location on Display	Location in DDS Source	Name of Record Format that Contains Help
Lines 5-7	Entire record format HEADER	Record format HLPCMPY
Line 15	First line in record format SINFO	Record format HLPADDR
Line 16	Second line in record format SINFO	Record format HLPCITY
Line 17	Third line in record format SINFO	Record format HLPST
All shaded areas	Areas in display file that are not defined with help record	Record format SUPHELP

The following DDS source shows how the help areas are defined for the sample display using help records:

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
                                HELP
                                HLPRCD(SUPHELP)
                                OVERLAY
                                HLPARA(*RCD)
                                HLPRCD(HLPCMPY)
                                5 25'ADD, UPDATE, DISPLAY SUPPLIER'
                                7 10'ENTER NEW OR EXISTING NAME:'
                                CONAME          10A  I  7 47
                                R SINFO
                                H                                OVERLAY PROTECT
                                H                                HLPARA(15 1 15 61)
                                H                                HLPRCD(HLPADDR)
                                H                                HLPARA(16 1 16 41)
                                H                                HLPRCD(HLPCITY)
                                H                                HLPARA(17 1 17 33)
                                H                                HLPRCD(HLPST)
                                15 10'ADDRESS:'
                                ADDR          30A  B 15 32
                                16 10'CITY:'
                                CITY          10A  B 16 32
                                17 10'STATE:'
                                STATE         2A  B 17 32

```

Figure 18-6. Sample DDS Source Showing HLPRCD

The file level help is used to provide general help for the display (when the cursor is not located in the record area for either HEADER or SINFO) because HLPARA(*RCD) is the location specified on the H specification.

You are not required to define each help area with a different record. This means that the same record may be used to define one or more help areas on a display, including the help area that defines the entire display.

Defining Records with Option Indicators: The HLPRCD keyword can be specified with option indicators. In the following example, assume the SINFO record is put with indicator 90 on and the cursor is in the help area defined for the H specification. When the Help key is pressed, the record HELP#1 is displayed. If indicator 90 is off, the record HELP#2 is displayed.

The DDS for this file is:

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
                                HELP
                                OVERLAY
                                5 25'ADD, UPDATE, DISPLAY SUPPLIER'
                                7 10'ENTER NEW OR EXISTING NAME'
                                10A I 7 47
                                CONAME
                                R SINFO
                                H                                OVERLAY PROTECT
                                90                                HLPARA(15 9 15 61)
                                H                                HLPARCD(HELP#1)
                                N90                                HLPARA(15 9 15 61)
                                H                                HLPARCD(HELP#2)
                                15 10'ADDRESS'
                                ADDR                                30A B 15 32
```

Figure 18-7. Sample DDS Source Showing HLPARCD and Option Indicators

Entering the Records That Contain the Help Information

The records that give the actual online help information may be included in the same file as the DDS source for the application display. The records may also be contained in a different file. If the records are contained in a different file, the file and the library that contains the file must be identified on the HLPARCD keyword.

Regardless of where the information is contained, the DDS source for the previous example looks like the following:

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
                                R SUPHELP
                                2 5'TO ADD, UPDATE, OR DISPLAY -
                                THE SUPPLIER NAME AND -
                                ADDRESS, ENTER THE SUPPLIER -
                                NAME. ITS CURRENT ADDRESS, -
                                IF ANY, WILL BE SHOWN AND MAY -
                                BE UPDATED.'
                                R HLPMPY
                                2 5'ENTER THE FIRST 10 -
                                CHARACTERS OF THE COMPANY.'
                                R HLPADDR
                                2 5'ENTER THE NEW OR CHANGED -
                                ADDRESS.'
                                R HLPCTY
                                2 5'ENTER THE FIRST 10 -
                                CHARACTERS OF THE CITY'
                                R HLPST
                                2 5'ENTER THE 2 CHARACTER ABBR -
                                FOR THE STATE.'
```

Figure 18-8. Sample DDS Source with HLPARCD

Using Records and Documents for Help in the Same Display File

HLPBCD and HLPDOC are allowed in the same display file; however, the following considerations apply:

- When the Help key is pressed with the cursor location in a help area described by a document, that document is the only help displayed when the roll keys are used. No other document or help records are displayed.
- When the Help key is pressed with the cursor location in a help area described by a record, the normal sequencing used for records is followed with documents being ignored.
- The HLPDOC and HLPBCD keywords cannot both be specified at the file level or on the same H specification.
- The HLPBDY keyword cannot be specified with the HLPDOC keyword. For more information about the HLPBDY keyword, see “Displaying Secondary Online Help Information” on page 18-17.

Understanding the Restrictions on Records

The following restrictions apply when using the record form of application help:

- The application program does not control the displaying of the records. When the Help key is pressed, the system controls the displaying of help. Because the system does not control the buffers or hidden message line areas of the application program, the following takes place:
 - Output fields in the record formats are displayed as blanks.
 - The ALIAS keyword is allowed but ignored.
 - CSRLOC and MSGID are processed by the system, but the hidden and program-to-system fields are not passed from the application program.
- No input is returned to the user program:
 - Input-capable fields on a record are displayed with underlines; however, no input is returned to the application program. Any input typed in an input field is lost when application help is finished.
 - Response indicators are not returned.
- Help records can contain H specifications, but they are ignored.
- Option indicators are assumed to be off.
- Screen size conditioning can be used.
- Only the following keywords are active when specified for records:

COLOR
DATE
DFT
DSPATR
DSPSIZ
MSGCON
MSGLOC
TEXT
SLNO (constant value). If SLNO(*VAR) is specified, 1 is used for the starting line number.
SYSNAME
TIME
USER

All other display file keywords, though allowed, do not make sense for records and may or may not be processed while displaying the help.


Paging between Help Displays That Use Records

If you use records to define help information, the first display that appears when the Help key is pressed is called **primary help**. When a Roll Up or Roll Down key is pressed on a primary help display, **secondary help** is shown.

Understanding How the System Pages Help Displays

The system maintains a list of all active H specifications from record formats that are on the display. This list of H specifications is called the **help list**. The H specifications on the front of the help list are the first to be searched when the user presses the Help key.

Pressing the Help key in a help area on the display does the following:



- 1** Suspends the display file.
- 2** Searches the list of active help areas to find the first one in the list that contains the cursor location when the Help key is pressed.
- 3** Opens the display file that contains the help record and displays the information.
- 4** Allows the user to roll forward or backward through the online help information.

The order and content of the H specifications in the list are determined by the following:

- When a record format is added to the display, the H specifications for that record format are placed on the front of the list.
- If the record format contains more than one H specification, they are added to the help list in the order in which they are defined in the display file.
- The help list is cleared either when a record format is written that clears the display, or when one is written that has the HLPCLR keyword enabled.
- If a record has the OVERLAY keyword in effect, has H specifications, or completely or partially overlaps another record already on the display, the help list is updated in different ways. The following table describes the type of help-list updating for records for each combination of the three factors:

Overlay	H Specifications	Overlaps	Help List Update
No	No	N/A	Help list is cleared.
No	Yes	N/A	Help list is cleared and H specifications for the record are added to the help list.
Yes	No	No	Help list is not changed.
Yes	No	Yes	H specifications are removed from the help list if they are within the boundaries of the record being written.
Yes	Yes	No	H specifications for the record are added to the help list. H specifications are removed from the help list if they are within the boundaries of any H specification in the record being added.
Yes	Yes	Yes	H specifications are removed from the help list if they are within the boundaries of the record being written. Then the H specifications for the record are added to the list. Finally, H specifications are removed from the help list if they are within the boundaries of any H specification in the record being added.

Note: An H specification with *NONE specified for the help area is removed from the help list when the first H specification with a help area defined above it is removed. If a help specification with *NONE specified for its help area is the first help specification, then it is only removed when the help list is cleared or when a help specification with a help area is placed above this help specification. This H specification is removed when the one above it is removed.

Displaying Secondary Online Help Information

The record formats that are displayed as secondary help come from the same help group, or if none is available there, from the same help sublist as the record format that is currently displayed.

A **help group** is defined with the HLPSEQ keyword and consists of those record formats that have the same group name specified. The HLPSEQ keyword allows you to specify the help group name and the help sequencing number. The help sequencing number specifies the order in which the help will be displayed. If two record formats that are in different display files happen to have the same group name, they are still considered to be in separate help groups. Record formats that do not have a HLPSEQ keyword specified are considered to be groups of one.

A **help sublist** contains all of those H specifications defined between help boundaries. The HLPBDY keyword partitions the help list into sublists by defining **help boundaries**. (The H specification that has the HLPBDY keyword coded is considered to be before the boundary.) Sublists are important when using the roll keys to look at more online help information.

Determining the Sequence of Secondary Help: Depending on whether you are using the Roll Up or Roll Down key, the system selects secondary help as follows:

1. A help record format that is in the same help group as the current help record format and has the next *highest* help sequencing number (if the Roll Up key is pressed) or next *lowest* help sequencing number (if the Roll Down key is pressed) is selected.
2. If the current help record format already has the *highest* help sequencing number (if the Roll Up key is pressed) or the *lowest* help sequencing number (if the Roll Down key is pressed) in the group, the help sublist is searched for the

next H specification that does not refer to the same help group as the currently displayed record format.

Notes:

- a. To prevent including unexpected help, it is recommended that the HLPBDY keyword be specified on the last H specification in each record of the application display file. This defines one sublist for each record that has help. However, if multiple records are on the screen, this may not be desirable. In this case, the HLPBDY keyword should be in effect only on the last record put to the screen.
 - b. Because this second method works only when a sublist can be identified, it is not used if the primary help was the default record format for the file (for example, if it was selected from the file-level HLPRCD keyword).
3. Searching in the sublist continues until the boundary of the sublist is reached. The search then wraps to the other end of the sublist and continues until the current H specification being displayed is reached.
 4. If no H specification that has a satisfactory HLPRCD is found, the record format in the help display file that has the same help group name and the *lowest* help sequence number (if the Roll Up key is pressed) or the *highest* help sequence number (if the Roll Down key is pressed) is selected. This method always finds a match because the current help format always meets this criteria if no other format does.

In the following example, the fields and HLPARA keywords are not specified because neither has an effect on the order of secondary information:




Figure 18-9. Sample DDS Source to Show Secondary Help

The sample file HELPFILE contains the following record formats with HLPSEQ keywords coded as shown:

Record	Keyword Specification
HELP	HLPSEQ(GROUPA 1)
HELP1	HLPSEQ(GROUPA 2)
HELP11	HLPSEQ(GROUPA 3)
HELPSCR1	HLPSEQ(GROUPB 1)
HELPSCR2	HLPSEQ(GROUPB 2)
HELP2SRC	

Note that the help record formats HELP and HELPSCR2 are not referred to in the application display file. Because they are not referred to in this way, they are not primary help, but they are displayed as secondary help as follows:

Sequence 1:

Primary help format	HELP11
Press Roll Down	HELP1
Press Roll Down	HELP
Press Roll Down	HELP11

In this first sequence, HELP1 is shown when the Roll Down key is pressed because this is the previous help record format in GROUPA. Similarly, HELP is shown when Roll Down is pressed the second time. When Roll Down is pressed the third time, the end of the help group is reached. HELP11 is then selected again because it is the last help record format in the original help group.

Sequence 2:

Primary help format	HELPSCR1
Press Roll Up	HELPSCR2
Press Roll Up	HELP1
Press Roll Down	HELP

The second sequence starts with HELPSCR1 being displayed as the primary help record format. Pressing Roll Up causes HELPSCR2 to be displayed because it is the next help record format in GROUPB. Rolling up again runs off the end of the group and HELP1 is found because it is the next help record format found, after wrapping, in the sublist that contains HELPSCR1. Pressing Roll Down now causes HELP to be displayed because it is the previous entry in GROUPA.

Sequence 3:

Primary help format	HELP2SRC
Press Roll Up or Down	HELP2SRC

Because HELP2SRC is not in a help group and is the only one in its sublist, HELP2SRC is to be shown when rolling in either direction.

Understanding the Restrictions of Records for Secondary Help: The following restrictions apply when using the record form of application help:

- Application help controls all function keys when a help record is displayed:
 - The Roll Up key is enabled and causes the next record to be displayed according to the rules for displaying secondary help.
 - The Roll Down key is enabled and causes the previous record to be displayed according to the rules for secondary help.
 - The Enter key is enabled and causes a return to the application program. Any CAnn or CFnn key enabled for the record will also cause a return to the application program. All other function keys, including the Help key, are ignored.
- Records with the USRDFN, SFL, and SFLCTL keywords may not be used as records. When a display file is created, a diagnostic is issued if the HLPSEQ keyword is found on a record with one of these keywords. When the application is running, error reset message CPD4050 is issued if a record with one of these keywords is used as help. The help record is not displayed.

The KEEP and ASSUME keywords should be avoided on records because they cause results that cannot be predicted.

Returning Control to Your Program after Pressing the Help Key

Depending on how you code your DDS, you can return control to your program in one of two ways after you press the Help key:

- You can display online help information and then return control to the program.
- You can return control to the program immediately without displaying the online help information.

Returning Control to Your Program after Showing the Help Display

Use the help command key (HLPAMDKEY) keyword to return control to your application program from the application help record format after a command attention (CAnn) or command function (CFnn) key has been pressed. A CFnn key returns data to the application program, while a CAnn key does not return data to the application program.

The command key must apply to both the application record format and the application-help record format. If a CAnn or CFnn key does not apply to the application-help record format, the HLPAMDKEY keyword is ignored.

The following DDS source, which uses help records, shows how the HLPAMDKEY keyword is specified:

```
|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
      R APPRCD                                CA01
                                           CA03
                                           CF04
                                           HELP
      H                                HLPAMD(HLPAMD)
                                           HLPAMD(1 1 24 80)
                                           8 2'THIS IS THE APPLICATION'
                                           9 2'RECORD FORMAT'
      INPUT1          10 B 12 10
      INPUT2          10 B 13 10
      INPUT3          10 B 14 20
      *
      R HLPAMD                                HLPAMDKEY
                                           CA01
                                           CF03
                                           8 2'SPECIFY COMPANY NAME'
                                           9 2'SPECIFY STREET'
                                           10 2'SPECIFY CITY, STATE, ZIP'
```

Figure 18-10. Sample DDS Source to Show HLPAMDKEY

If the user is on the application help display that uses the previous data description specifications, the following happens when the various keys are pressed:

- The CF04 key, which is specified only on the application record format, acts the same as the Enter key.
- The CMD3 key acts the same as the Enter key. Corresponding CAnn or CFnn keys must be specified on both the application-help record format and application record format for control to return to the program.
- The CA01 key returns control to the application program.

In the next example, response indicators are used. When a response indicator is specified on a CAnn or CFnn key on the application record format (for example, CF12(12)), the response indicator is returned after the application-help record format is displayed. When a response indicator is specified on a CAnn or CFnn key on the application-help record format (for example, CF01(11)), the response indicator is ignored.

```

|...+....1....+....2....+....3....+....4....+....5....+....6....+....7...
      R APPRCD                                CA01
                                              CA03
                                              CF12(12)
                                              HELP
      H                                HLP RCD(HLP RCD)
                                              HLPARA(1 1 24 80)
                                              8 2'THIS IS THE APPLICATION'
                                              9 2'RECORD FORMAT'
      INPUT1                                10 B 12 10
      INPUT2                                10 B 13 10
      INPUT3                                10 B 14 20
*
      R HLP RCD                                HLP CMDKEY
                                              CF01(11)
                                              CF12
                                              8 2'SPECIFY COMPANY NAME'
                                              9 2'SPECIFY STREET'
                                              10 2'SPECIFY CITY, STATE, ZIP'

```

Figure 18-11. Sample DDS Source to Show HLP CMDKEY and Response Indicators


Returning Control to Your Program without Showing the Help Display

Use the HLPRTN keyword to immediately return control to your program (instead of displaying help) when the Help key is pressed.

Chapter 19. Making Online Help Accessible for Your Panel Group

The Help key on most keyboards is either a key specifically labeled Help, or it is a key defined to work as a Help key and labeled with another name. This varies among keyboards, but the F1 key is commonly defined as an alternate for the Help key.

When the user presses the Help key, a sequence of events occur, as illustrated by the following diagram:



¹ If the cursor is on a hypertext link when you press the Enter key, instead of returning to the current UIM panel, you are taken to the hypertext information.

RV2W061-2

When the user presses the Help key, the current panel is suspended by the UIM and a help panel is displayed with information about a specific item, group of items, area on a panel, or the entire panel. When the user has read the displayed help, the user presses the F3, F12, or Enter key to return to the current panel before the Help key was pressed.

Definitions and Explanations

Help for a panel is constructed from help modules referred to in the panel definition. The UIM requires you to define online help information for panels in a panel group, and presents the help to the user when the HELP dialog command is requested.

The user requests the HELP dialog command by pressing a key assigned to it. Typically, the engraved Help key and the F1 key are assigned to the HELP dialog command. In this section, the term **Help key** refers to any key which is assigned to the HELP dialog command.

Online help information is the information displayed to the user when the Help key is pressed on the keyboard. The level of help displayed depends on the location of the cursor when the user presses the Help key.

Help is always available for the entire panel. This help is known as **extended help**, which is the general information for a panel. Extended help begins with information about the purpose and use of the panel and is followed by contextual help for each item on the panel. Extended help includes contextual help for items that do not currently show on the screen, but which can be shown by using the Page Up and Page Down keys. (**Contextual help** provides information about a single item or group of related items where the cursor is positioned when the user requests help.) An item is excluded from extended help when the item is not currently active for the panel by using the COND attribute for a specific item on the panel.

Extended help is displayed when the Help key is pressed for an area of the screen that does not have contextual help defined. It is also displayed when the user presses F2 (Extended help) while viewing contextual help.

The extended help is defined on the HELP attribute of the display panel (PANEL) tag. This attribute identifies the help module containing the beginning of the extended help for the panel.

When coding online help for a panel, the tag which actually contains the information that is displayed when the user presses the Help key is the help module (HELP) tag. For more information on the attributes of this tag, see "HELP (Help Module)" on page A-58.

To code for help in a panel, the HELP attribute must be specified on the tag for which the help is provided. The name of the help module containing the help information is specified on the HELP attribute of a tag.

The help module identified on a HELP attribute exists in the same panel group or menu where that HELP attribute appears, or in another panel group. When the panel group or menu is created, the UIM compiler determines the panel group in which the UIM will find the help module when the Help key is pressed by finding a help module name that matches the name specified on the HELP attribute in one of the following places:

1. If the panel group or menu being created contains a matching name on the NAME attribute of a HELP tag, the help module is found in the same panel group or menu when the Help key is pressed.
2. If the panel group or menu being created contains a matching name on the NEWNAME attribute of an import (IMPORT) tag, the help module is found in the panel group specified on the PNLGRP attribute of the IMPORT tag.
3. If the panel group or menu being created contains an IMPORT tag with NAME=* specified, the help module is found in the panel group specified on the PNLGRP attribute of the IMPORT tag.

If all of the above are not true, the UIM compiler reports an error message and the panel group or menu is not created.

When specifying the name of a help module, apostrophes are not necessary unless characters other than A through Z, a through z, and 0 through 9 are used. If any other keyboard characters are used, apostrophes are required. For example, in a name specifying `HELP='key/enter'`, the apostrophes are required because the slash (/) is not an alphabetic character or a numeral. For more information on the rules for names, see “Name Syntax” on page A-4.

Help in a List Area

A list area displays the contents of a UIM list. The list consists of rows and columns of variable information, which appear in a table format. The following screen is an example of a panel using a list area to display a list of eight rows.

For this panel, the user may enter numbers 2, 4, 5, 7, or 8 in the *Opt* column to specify an action to be performed against one of the rows in the list.

Spooled Files						
Type options, press Enter.						
2=Change 4=Cancel 5=Display 7=Hold 8=Release						
					-----Created-----	
Opt	File	Nbr	User	Pty	Date	Time
-	fffffffffff	nnnn	uuuuuuuuuu	p	mm/dd/yy	hh:mm:ss
-	fffffffffff	nnnn	uuuuuuuuuu	p	mm/dd/yy	hh:mm:ss
-	fffffffffff	nnnn	uuuuuuuuuu	p	mm/dd/yy	hh:mm:ss
-	fffffffffff	nnnn	uuuuuuuuuu	p	mm/dd/yy	hh:mm:ss

Help in a list area must be defined at the group level and at the column level for columns which are not part of a group.

Group Level Help

To define help at the group level, specify the `HELP` attribute on the list group (`LISTGRP`) tag. This attribute identifies the help module which explains the group of columns in the list.

Column Level Help

To define help at the column level in a list area, specify the `HELP` attribute on the list column (`LISTCOL`) tag. This attribute identifies online help information which explains the purpose of the column in the list.

The `HELP` attribute is not allowed if the column is part of a list column group defined by the `LISTGRP` tag, but is required if the column is not part of a group.

The `HELP` attribute of the list action (`LISTACT`) tag identifies the help module which explains the list action. The online help information for all active list actions is displayed as part of the contextual help for the action column.

Coding Help

The following source shows how help is defined for the sample panel with a list area shown above. All help modules for this sample list area are imported from panel group *LIBL/EXAMPL2. When the cursor is positioned on the *Opt* column, the 'splf/option' help module is displayed, followed by these help modules:

- 'splf/change'
- 'splf/cancel'
- 'splf/display'
- 'splf/hold'
- 'splf/release'

When the cursor is positioned on either the *Date* or *Time* column, the 'splf/created date time' help module is displayed. With the cursor on any other column, the help module identified on the LISTCOL tag is displayed.

```
:import name='*' pnlgrp='*libl/example2'.  
:  
:listact option=2 help='splf/change' enter='call listactpgm'.2=Change  
:listact option=4 help='splf/cancel' enter='call listactpgm'.4=Cancel  
:listact option=5 help='splf/display' enter='call listactpgm'.5=Display  
:listact option=7 help='splf/hold' enter='call listactpgm'.7=Hold  
:listact option=8 help='splf/release'enter='call listactpgm'.8=Release  
:  
:listcol var=option help='splf/option' usage=inout maxwidth=6.Opt  
:listcol var=filenam help='splf/file_name' usage=out maxwidth=12.File  
:listcol var=filenbr help='splf/file_number' usage=out maxwidth=6.Nbr  
:listcol var=usernam help='splf/user_name' usage=out maxwidth=12.User  
:listcol var=filepty help='splf/file_priority' usage=out maxwidth=6.Pty  
:listgrp col=filecrt help='splf/created_date_time'.Created  
:listcol var=filedat usage=out maxwidth=8.Date  
:listcol var=filetim1 usage=out maxwidth=8.Time  
:elistgrp.  
:listview cols='option filenam filenbr usernam filepty filecrt'.
```

Help in a Menu Area

A menu area contains one or more items, each of which contains an option number and a description of an action which can be performed. To select an option, the user enters the number of the option on the command or option line and presses the Enter key. The following screen is an example of a panel with a menu area.

This panel has six options the user can choose, and each option has a brief description of the action it performs. The option number chosen by the user is entered on the *Selection* line.

Work with Files
 System: xxxxxxxx

Select one of the following:

1. Display file attributes
2. Display file contents
3. Change ownership
4. Change authorizations
5. Delete
6. Backup to tape

Selection

—

Help in a menu area must be defined at the item level.

Item Level Help

To define help for a menu area, specify the HELP attribute on the menu item (MENU) tag. This attribute identifies the help module which explains the purpose of the menu item.

The online information identified by the HELP attribute is displayed when help is requested while the cursor is positioned on the text for the menu item, or while the cursor is on the command or option line and a valid menu item number has been entered.

Coding Help

The following source shows how help is defined for the sample panel shown on page 19-5.

Reference numbers (**n**) are used in this example to show the relationship between referring to a help module using the HELP attribute of a tag, and the definition of the help module using the HELP tag.

```

:menui option=1 help='option/display_attr' action='call menuipgm' 1
    .Display file attributes
:menui option=2 help='option/display_cont' action='call menuipgm' 2
    .Display file contents
:menui option=3 help='option/change_owner' action='call menuipgm' 3
    .Change ownership
:menui option=4 help='option/change_auth' action='call menuipgm' 4
    .Change authorizations
:menui option=5 help='option/delete' action='call menuipgm' 5
    .Delete
:menui option=6 help='option/backup_tape' action='call menuipgm' 6
    .Backup to tape
:
:help name='option/display_attr' 1
    .Display File Attributes - Help
:xh3.1. Display file attributes

```

:p.Choose this option to display the attributes associated with this file.
The attributes include all the information about the definition of the file.
:ehelp.

:help name='option/display_contents' **2**
 .Display File Contents - Help
:xh3.2. Display file contents
:p.Choose this option to display the data contained in this file.
:ehelp.

:help name='option/change_owner' **3**
 .Change Ownership - Help
:xh3.3. Change ownership
:p.Choose this option to change the owner of this file.
You are prompted to enter the name of the new owner.
:ehelp.

:help name='option/change_auth' **4**
 .Change Authorizations - Help
:xh3.4. Change authorizations
:p.Choose this option to change the list of users
who have authority to access this file.
You are prompted for the user names and authorizations for the file.
:ehelp.

:help name='option/delete' **5**
 .Delete - Help
:xh3.5. Delete
:p.Choose this option to delete this file.
The file and all the data in the file is erased from the system
and the storage used by the file is made available for other use.
:ehelp.

:help name='option/backup_tape' **6**
 .Backup to Tape - Help
:xh3.6. Backup to tape
:p.Choose this option to
save a copy of this file on a magnetic tape.
You are prompted for more information about how to back up the
file on the tape.
:ehelp.

Help in a Data Area

A data area contains one or more data entry items whose variable information may be changed by the user. A data area can also contain output items whose variable information can be viewed by the user but cannot be changed. The following screen is an example of a panel with a data area.

Sample Entry Panel	
Type choices, press Enter:	
File name _____	Name of document to be printed
Type style for printing <u>1</u>	1=Prestige Elite (12 pitch) 2=Courier (10 pitch) 3=Essay Standard (proportional) 4=Essay Bold (proportional)

Help in a data area must be defined for every item at one of three levels.

Area Level Help

To define help at the area level, specify the HELP attribute on the data presentation area (DATA) tag. This attribute identifies the help module which explains all items in the area.

If no HELP attribute is specified on the DATA tag, a help module name must be associated with each item in the area by specifying the HELP attribute on the data group (DATAGRP), the data item (DATAI), and data selection field (DATASLT) tags.

To provide the user with easy access to the online information for a data area with the LAYOUT=HORIZ attribute specified on the DATA tag, specify the HELP attribute on the DATA tag instead of the HELP attribute on the individual DATAI tags.

Group Level Help

To define help at the group level, specify the HELP attribute on the DATAGRP tag. This attribute identifies the help module that explains all items in the group.

If no HELP attribute is specified on the DATA tag or on any outer or nested DATAGRP tags, the HELP attribute is required on all DATAI and DATASLT tags within the group.

Item Level Help

To define help at the item level, specify the HELP attribute on the DATAI or DATASLT tag. This attribute identifies the help module that explains the data item or selection field.

If no HELP attribute is specified on the DATA tag or on DATAGRP tags containing a data item, the HELP attribute is required on the DATAI and DATASLT tags.

To provide the user with easy access to the online information for a LAYOUT=HORIZ data area, use the HELP attribute on the DATA tag instead of the HELP attribute on the individual DATAI tags in the horizontal area.

The HELP attribute applies to all data item extender (DATAIX) tags associated with a data item.

If the HELP attribute is specified on the DATASLT tag, the HELP attribute can also be specified for each choice on the DATASLTC tag. If the HELP attribute is specified on a DATASLTC tag within a selection field, all DATASLTC tags within that selection field must have the HELP attribute specified.

For multiple-choice selection fields, the online information identified for each choice is included as part of the contextual help displayed when the cursor is positioned anywhere within the selection field.

For single-choice selection fields, the online information identified for each choice is displayed when help is requested while the cursor is positioned on the text of the choice. This online information is also included as part of the contextual help displayed when the cursor is positioned within the selection field but not on the text for one of the choices within the field. This includes occurrences when the cursor is positioned on the prompt text for the selection field or in the entry field for the selection field. If the cursor is in the entry field and a valid choice is entered, when help is requested, the help for that choice is displayed.

Coding Help

The following source shows how help is defined for the sample data area panel shown previously. All the help modules for this sample data area are imported from panel group *LIBL/DATAXMP.

```

:
:import name='*' pnlgrp='*libl/dataxmp'.
:
:datai var=filename help='print/filename' usage=inout.File name
:datac.Name of document to be printed
:datai var=typestyle help='print/style' usage=inout.Type style for printing
:datac.1=Prestige Elite (12 pitch)
:datac.2=Courier (10 pitch)
:datac.3=Essay Standard (proportional)
:datac.4=Essay Bold (proportional)
:datai var=leftmarg help='print/left_margin' usage=inout.Left margin
:datac.Number of spaces from the left edge of the paper (1-20)
:datai var=copies help='print/copies' usage=inout.Copies
:datac.Number of copies (1-99)
:datai var=duplex help='print/duplex' usage=inout.Duplex
:datac.1=Yes (Print both sides of paper)
:datac.2=No (Print one side only)
:
```

The following source defines the help modules in panel group *LIBL/DATAXMP. These help modules are imported when the Help key is pressed for the previous sample data area.

```

:
:help name='print/filename'.File Name - Help
:xh3.File name
:p.Enter the name of document to be printed.
:ehelp.

:help name='print/style'.Type Style for Printing - Help
:xh3.Type style for printing
:p.Enter one of the following to select the type style.
:parml.
:pt.1
:pd.A 12 pitch elite style is used.
:pt.2
:pd.A 10 pitch courier style is used.
:pt.3
```

```

:pd.A proportional essay standard style is used.
:pt.4
:pd.A proportional essay bold style is used.
:eparm1.
:ehelp.

:help name='print/left_margin'.Left Margin - Help
:xh3.Left margin
:p.Enter a number from 1 to 20 for the number of spaces from
the left edge of the paper to the beginning of the printed text.
:ehelp.

:help name='print/copies'.Copies - Help
:xh3.Copies
:p.Enter a number from 1 to 99 for the number of copies of the
document to be printed.
:ehelp.

:help name='print/duplex'.Duplex - Help
:xh3.Duplex
:p.Enter one of the following to select whether or not to print on
both sides of the paper.
:parml.
:pt.1
:pd.Print text on both sides of the paper.
:pt.2
:pd.Print text only on one side of the paper.
:eparm1.
:ehelp.
:
```

The following example panel shows the file name and library name in a data area with a horizontal layout.

Work with File Members

File: FILE01	Library: QGPL
--------------	---------------

The following source shows how help is defined for the sample data area shown above. This is an example of providing area level help. When the cursor is positioned anywhere on the line containing the file name, help for the file name and library are displayed.

Reference numbers (**n**) are used in this example to show the relationship between a reference to a help module using the HELP attribute of a tag, and the definition of the help module using the HELP tag.

```

:
:
: data depth=2 help='file_and_library' layout=horiz. 1
: datai var=filename usage=out.File
: datai var=library usage=out.Library
: edata.
:
:
: help name='file_and_library'.File and Library - Help 1
: xh3.File and library
: p.The qualified name of the file whose members are being displayed.
: ehelphelp.
:
:

```

The following example panel shows a qualified file name and a record name in a data area with a two-column, vertical layout.

```

Work with Field Definitions

File . . . . . FILE          Record . . . . . MASTER01
Library . . . . . QGPL

```

The following source shows how help is defined for the sample data area shown above. This includes providing group level help for the qualified file name. When the cursor is positioned on the file or library, help for the qualified file name is displayed. When the cursor is positioned on the record name, help for the record name is displayed.

Reference numbers (**n**) are used in this example to show the relationship between referring to a help module using the HELP attribute of a tag, and the definition of the help module using the HELP tag.

```

:
:
: data depth=3 layout=2.
: datacol width=16.
: datacol width='*'.
: datagrps grpsep=qindent help='library/file' compact. 1
: datai var=filename usage=out.File
: datai var=library usage=out.Library
: edatagrps.
: datai var=record help=record usage=out.Record 2
: edata.
:
:
: help name='library/file'.File and Library - Help 1
: xh3.File and library
: p.The qualified name of the file whose field definitions are displayed.
: ehelphelp.

: help name=record.Record - Help 2
: xh3.Record

```


:p.The name of the record whose field definitions are displayed.
:ehelp.

Help in a Menu Bar Area

A menu bar area is located at the top of the panel and contains choices which give the user access to actions available for the panel. To select a choice in the menu bar, the user positions the cursor on the desired choice and presses the Enter key. After the user selects a choice in a menu bar, a pull-down menu appears below the menu bar containing choices for actions against the panel.

This partial screen contains an example of a menu bar area. The menu bar is the line near the top of the panel, listing *File* and *Help* as choices for the user. The user may select one of the choices to display the pull-down menu for that choice. The second screen in this example shows the pull-down menu displayed after selecting *File*.

```
File  Help
-----
                                Work with Programs
                                System: ROCH0001

Type choices, press Enter.
  2=Change  4=Delete  5=Display

Opt  Program  Library  Text
---  -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
-   -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
-   -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
```

When *File* is selected, a pull-down menu appears containing choices for actions for the panel. The actions available in the pull-down menu are *Change*, *Delete*, *Display*, and *Exit*. A pull-down menu with another list of actions appears when the user selects the *Help* menu bar choice while in the menu bar.

```
File  _Help
-----
:  2. Change      :      Work with Programs
:                :
:  4. Delete      :      er.
:  5. Display     :      5=Display
:  6. Exit        :      F3
:.....: y      Text
-   -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
-   -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
-   -
PPPPPPPPPP LLLLLLLLLL Description textxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx
```

Contextual help for a menu bar choice includes help for the choice on the menu bar, as well as help for each active choice in the pull-down menu for that menu bar choice. Help in a menu bar area must be defined at the menu bar choice level and at the pull-down choice level.

Menu Bar Choice Level Help

To define help at the menu bar choice level, specify the **HELP** attribute on the menu bar choice (MBARC) tag. This attribute identifies the help module which explains the purpose of the menu bar choice.

Pull-Down Choice Level Help

To define help at the pull-down choice level, specify the HELP attribute on the pull-down field choice (PDFLDC) tag. This attribute identifies the help module which explains the purpose of the pull-down choice.

Coding Help

The following source shows how help is defined for the first menu bar choice and the pull-down menu shown on page 19-11.

Reference numbers (**n**) are used in this example to show the relationship between referring to a help module using the HELP attribute of a tag, and the definition of the help module using the HELP tag.

```

:
:mbarc help='mbarpgm/file'.File 1
:pdfld.
:pdfldc option=2 help='mbarpgm/file/change' 2
      action='cmd ?CHGPGM PGM(&var2./&var1.)'
      actfor=list.Change
:pdfldc option=4 help='mbarpgm/file/delete' 3
      action='cmd DLTPGM PGM(&var2./&var1.)'
      actfor=list confirm=confpgm usrexit='call exitpgm'.Delete
:pdfldc option=5 help='mbarpgm/file/display' 4
      action='cmd DSPPGM PGM(&var2./&var1.)'
      actfor=list.Display
:pdfldc option=6 help='mbarpgm/file/exit' action='exit set' 5
      varupd=no.Exit
:pdaccel.F3
:epdfld.
:embarc.
:
:help name='mbarpgm/file'.File - Help 1
:xh3.File
:p.Select this choice to display a pull-down menu containing options
to perform against selected programs.
:ehelp.

:help name='mbarpgm/file/change'.Change - Help 2
:parml.
:pt.Change
:pd.Choose this option to change attributes of the selected
programs.
This choice is not available if no programs were selected
from the list.
:eparml.
:ehelp.

:help name='mbarpgm/file/delete'.Delete - Help 3
:parml.
:pt.Delete
:pd.Choose this option to delete the selected programs.
This choice is not available if no programs were selected
from the list.
:eparml.
:ehelp.
```

```

:help name='mbarpgm/file/display'.Display - Help 4
:parml.
:pt.Display
:pd.Choose this option to display the attributes of the selected
programs.
This choice is not available if no programs were selected
from the list.
:eparml.
:ehelp.

:help name='mbarpgm/file/exit'.Exit - Help 5
:parml.
:pt.Exit
:pd.Choose this option to end the current task and return
to the display from which the task was started.
:eparml.
:ehelp.

```

Help in a Function Key Area

A function key area is located at the bottom of the panel and contains descriptions of the actions available to the user when the user presses a function key. The function key area appears on most panels.

The following partial screen contains an example of a function key area for function keys F3, F4, F9, and F12. The descriptions for these keys are listed in the function key area, which contains the text F3=Exit, F4=Prompt, F9=Retrieve, and F12=Cancel.

Selection or command
 ===> _____

F3=Exit F4=Prompt F9=Retrieve F12=Cancel

Contextual help for the function key area includes help for the entire list of keys, as well as help for each active function key. This includes function keys which do not have text displayed on the panel. Help in a function key area can be defined at the area level and must be defined at the item level.

Area Level Help

To define help at the area level, specify the HELP attribute on the key list (KEYL) tag. This attribute identifies the help module which explains the purpose of the function key area as a whole.

Item Level Help

To define help at the item level, specify the HELP attribute on the key item (KEYI) tag. This attribute identifies the help module which explains the purpose of the function key.

Coding Help

The following source shows how help is defined for the function key area shown on page 19-13. The help module, *fkey*, contains no help information. This help module only provides a title for contextual help for the function key area and a heading for the function keys in extended help. There is no title or extended help heading tag in the help for each function key because the contextual help is for the entire function key area, not for an individual key.

Reference numbers (**n**) are used in this example to show the relationship between referring to a help module using the HELP attribute of a tag, and the definition of the help module using the HELP tag.

```
:
:keyl name=keys help=fkey. 1
:keyi key=f3 help='fkey/exit' action='exit set' varupd=no.F3=Exit 2
:keyi key=f4 help='fkey/prompt' action=prompt.F4=Prompt 3
:keyi key=f9 help='fkey/retrieve' action=retrieve.F9=Retrieve 4
:keyi key=f12 help='fkey/cancel' action='cancel set' varupd=no.F12=Cancel 5
:keyi key=enter help='fkey/enter' action=enter. 6
:keyi key=help help='fkey/help' action=help. 7
:keyi key=pagedown help='fkey/pagedown' action=pagedown. 8
:keyi key=pageup help='fkey/pageup' action=pageup. 9
:keyi key=print help='fkey/print' action=print. 10
:ekeyl.
:
:help name='fkey'.Function Keys - Help 1
:xh3.Function keys
:ehelp.

:help name='fkey/exit'. 2
:parml.
:pt.F3=Exit
:pd.Ends the current task and returns you to the display from
which the task was started.
:eparml.
:ehelp.

:help name='fkey/prompt'. 3
:parml.
:pt.F4=Prompt
:pd.Provides assistance in entering or selecting a command.
:eparml.
:ehelp.

:help name='fkey/retrieve'. 4
:parml.
:pt.:F9=Retrieve
:pd.Shows the last command you entered on the command line,
along with any parameters you included. By pressing this key
once, you receive the last command you ran. By pressing this
key twice, you receive the next to last command that you ran,
and so on.
:eparml.
:ehelp.

:help name='fkey/retrieve'. 5
:parml.
```

```

:pt.F12=Cancel
:pd.Returns to the previous menu or display.
:eparm1.
:ehelp.

:help name='fkey/enter' 6
:parml.
:pt.Enter
:pd.Submits information on the display for processing.
:eparm1.
:ehelp.

:help name='fkey/help' 7
:parml.
:pt.Help
:pd.Provides more information about using the display.
:eparm1.
:ehelp.

:help name='fkey/pagedown' 8
:parml.
:pt.Page Down or Roll Up
:pd.Moves forward to show additional information for this display.
:eparm1.
:ehelp.

:help name='fkey/pageup' 9
:parml.
:pt.Page Up or Roll Down
:pd.Moves backward to show additional information for this display.
:eparm1.
:ehelp.

:help name='fkey/print' 10
:parml.
:pt.Print
:pd.Prints the information currently shown on the display.
:eparm1.
:ehelp.
:

```

Chapter 20. Defining Online Help Information

When the Help key is pressed and the DDS source for your display file specifies that online help information is available for the display, the system shows the information referred to by the panel group or document or, if you used DDS, contained in the record.

The following sections in this chapter tell you how to create the actual information that the user sees:

- “Defining Online Help Information in a Panel Group”

For more information on creating online help using the UIM, see Chapter 19, “Making Online Help Accessible for Your Panel Group” on page 19-1 and Part 3, “Programming Application Displays Using Panel Groups” on page 14-5.

- “Defining Online Information in a Document” on page 20-17
- “Defining Online Help Information in a DDS Record” on page 20-18

If the DDS source for your display does not specify that online help information is accessible for your display, go to Chapter 18, “Making Online Help Information Accessible for Your Display File.”

Defining Online Help Information in a Panel Group

The user interface manager (UIM) uses panel groups to access online help information. The online help information in panel groups may be used in several ways:

- Display help
- Command help
- InfoSeeker topics

To use panel groups for online help information, you must specify them in the DDS source for your application display. If you plan to use panel groups for help but have not yet specified them in your DDS source, see “Specifying Panel Groups for Help in Your Display File” on page 18-6.

Entering the UIM Source for a Panel Group for Help

Like display files that are created by compiling DDS source, panel groups are created by compiling UIM source. The UIM source for a panel group is entered in a source file member. The source type for all panel groups is *PNLGRP. Steps for creating and entering data in a source file member are found in Chapter 1, “Building a Sample Display with Online Help Information.”

UIM tags, which always begin with a colon (:) and end with a period (.), are used to help format and identify the information. Detailed information about UIM tags is found in Appendix A, “UIM Panel Group Definition Language.”

Organizing a Panel Group with Help Modules

The UIM source for every panel group, whether used for display help, command help, or an InfoSeeker topic, starts with a :PNLGRP tag and ends with an :EPNLGRP tag.

Units of help information, known as **help modules**, are defined in the panel group between the :PNLGRP and :EPNLGRP tags. Each help module starts with a named :HELP tag and ends with an :EHELP tag, as follows:

```
:PNLGRP.  
:HELP name=firsthelp.Title of First Help Module  
:P.  
Information for first help module  
:EHELP.  
:HELP name=secondhelp.Title of Second Help Module  
:P.  
Information for second help module.  
:EHELP.  
:EPNLGRP.
```

A panel group may contain one or more help modules. The help module name, which is the value for the *name* attribute on the :HELP tag, identifies the help module and must be unique for each help module in the panel group. The text that follows the period (.) on the :HELP tag is used as the title when the online help information is displayed.

Using the Information in a Help Module More Than Once

The :IMHELP tag allows information to be imbedded, which means that information that is used more than once can be defined in one help module and then used within another help module, as follows:

```
:PNLGRP.  
:HELP name=pacific.Pacific Ocean  
:P.  
The Pacific Ocean is the largest ocean in the  
world.  
:IMHELP name=ocean.  
:EHELP.  
:HELP name=atlantic.Atlantic Ocean  
:P.  
The Atlantic Ocean separates North and South America from  
Europe and Africa.  
:IMHELP name=ocean.  
:EHELP.  
:HELP name=ocean.  
:P.  
An ocean is one of the five large bodies of salt water, which  
together cover nearly three-fourths of the world.  
:EHELP.  
:EPNLGRP.
```

Note: The :P tag used in the previous UIM source indicates the start of a paragraph. More information on the :P tag is available in Appendix A, "UIM Panel Group Definition Language."

When the user sees the online help information in the previous example, the definition of *ocean* is the second sentence for the definitions of both the Pacific Ocean and the Atlantic Ocean.

Using a Help Module Contained in a Different Help Panel Group


If the help module that contains the repeated information is contained in a different panel group, an `:IMPORT` tag is needed. The `:IMPORT` tag identifies the panel group that contains the needed help module and makes that panel group available for use within the current panel group. The `:IMPORT` tag is placed after the `:PNLGRP` tag and before the *first* `:HELP` tag in the panel group that refers to the help module.

First panel group (named *PNLSAM1*):

```
:PNLGRP.  
:IMPORT pnlgrp=pnlsam2 name=ocean.  
:HELP name=pacific.Pacific Ocean  
:P.  
The Pacific Ocean is the largest ocean in the  
world.  
:IMHELP name=ocean.  
:EHELP.  
:HELP name=atlantic.Atlantic Ocean  
:P.  
The Atlantic Ocean separates North and South America from  
Europe and Africa.  
:IMHELP name=ocean.  
:EHELP.  
:EPNLGRP.
```

Second panel group (named *PNLSAM2*):

```
:PNLGRP.  
:HELP name=ocean.  
:P.  
An ocean is one of the five large bodies of salt water, which  
together cover nearly three-fourths of the world.  
:EHELP.  
:EPNLGRP.
```



RV2W056-2

Emphasizing and Formatting the Text within a Help Module

Panel markup tags are UIM tags used within help modules to help format and emphasize the information. More detailed information about the panel markup tags, including examples that show how the tags are used, is found in Appendix A, “UIM Panel Group Definition Language.”

Defining Paragraphs and Notes: The following panel markup tags format blocks of text into paragraphs or notes:

Function	UIM Tags	Use
Notes	:NT and :ENT	A note with one or more paragraphs. A note begins with Note: and usually refers to something in the text that precedes it. Displayed note text is indented.
Paragraphs	:P	A block of text that forms a paragraph. Paragraph text is separated from other paragraphs and text by a blank line.
Paragraph continuation	:PC	Continuation of a paragraph that has been interrupted by another panel markup tag, such as a figure, example, or list. When you specify paragraph continuation for text, paragraph formatting returns.

Adding Headings: The following panel markup tags identify associated text as headings:

Function	UIM Tags	Use
Extended help headings	:XH1 through :XH4	Conditional headings for main topic and subtopics of information. (When displaying contextual help, the first extended help heading tag is ignored so that its text is not shown.) Headings are useful for separating and organizing sections of text. Displayed heading text is highlighted and placed on its own line.
Headings	:H1 through :H4	Main topics and subtopics of information. Headings are useful for separating and organizing sections of text. Displayed heading text is highlighted and placed on its own line.

Highlighting Text: The following panel markup tags allow you to highlight text:

Function	UIM Tags	Use
Highlighted phrases	:HP0 through :HP9 and :EHP0 through :EHP9	A word or phrase to be highlighted. Text may be highlighted to emphasize it from the surrounding text. Depending on the tag, displayed highlighted text may be shown normal, underlined, brightened or colored differently, in reverse image, or a combination of these effects.
Title Citation	:CIT and :ECIT	The title of a publication. Publication titles are underlined when displayed.

Making Lists: You may organize your text in lists using the following panel markup tags:

Function	UIM Tags	Use
Definition List	:DL and :EDL (starts and ends list); :DTHD and :DDHD (provides column headings); :DT and :DD (identify terms and their definitions)	A list of words or phrases and their corresponding definitions, descriptions, or explanations. When definition lists are displayed, each term appears in the left column with its definition across from it in the right column.
List part	:LP	A comment or explanation that applies to a part of a list. A list part allows you to enter text after a list item without making the text part of the previous list item and without interrupting the list. List part text is not indented when displayed.
Ordered list of items	:OL and :LI and :EOL	An ordered list of items. Items in an ordered list are preceded by numbers or alphabetic letters to show sequence or order. Displayed list items in an ordered list are indented.
Parameter list	:PARML and :EPARML	Parameter terms and descriptions. The parameter list is commonly used to define programming keywords and variables. The parameter term is shown in the left column; its definition appears indented on the line following the term.
Simple list	:SL and :LI and :ESL	List of items. Simple lists are commonly used when list items are contained on one line and no sequence is required. List items in a simple list are indented only and not preceded by numbers, letters, hyphens, or dashes.
Unordered list	:UL and :LI and :EUL	Unordered list of items. Unordered lists are commonly used when sequence is not required for the items in the list. List items in an unordered list are indented and preceded by the lowercase letter o, a hyphen, or a dash.

Identifying Programming Keywords and Variables: The following panel markup tags allow you to highlight programming keywords and variables, and are often used with the parameter list tags:

Function	UIM Tags	Use
Programming keyword	:PK and :EPK	A programming keyword. Programming keywords are used to explain the elements of programming syntax. Programming keywords are highlighted and, if specified as a default also, underlined.
Programming variable	:PV and :EPV	A programming variable. Programming variables are used to explain the elements of programming syntax. Programming variables are underlined when displayed.

Indicating Structured Text: If you want text to be displayed as it is entered, you can use the following panel markup tags:

Function	UIM Tags	Use
Example	:XMP and :EXMP	An area of text that is displayed exactly as it is entered. Examples are commonly used to show sample computer input or output. Displayed example text is indented.
Figures	:FIG and :EFIG	A diagram, chart, or other illustration. If desired, figures may be displayed with captions.
Unformatted lines	:LINES and :ELINES	An area of text that is displayed exactly as it is entered. Unformatted lines are used for any text that needs to be displayed without being concatenated.

For more information on the language tags, see Appendix A, "UIM Panel Group Definition Language" on page A-1.

Adding InfoSeeker Tags to a Help Panel Group

Help panel groups may also contain InfoSeeker modules. InfoSeeker supplements the help information that is provided for each display. To use the information in help panel groups for the InfoSeeker function, you need to add the appropriate UIM tags to your help modules.

Understanding How InfoSeeker Works: Users can access the InfoSeeker function from any display help that specifies that the InfoSeeker function is available.


When the user presses the Help key from a working display, help information is displayed. On all help displays that support the InfoSeeker function, F11=InfoSeeker is active. When the user presses F11, the InfoSeeker display appears. This display shows a list of main topics in the topic hierarchy. It has an input field at the bottom for search words.

The user can browse or print any topic in the list or type a word (or words) on the input field. To view one or more topics, the user types a 5 in the option field beside the topic title and presses the Enter key. To print one or more topics, the user types a 6 in the option field.

A plus sign (+) next to a topic means that the user can expand the topic to show its subtopics in the hierarchy using option 7 (Expand topic). Or, the user can use option 8 (Compress topic) to compress a topic so that the subtopics are no longer shown.

If the user types a word or words on the input field, the InfoSeeker function matches the words with synonym tables, and presents a list of topics that match the search words entered.

The following illustration shows how the InfoSeeker function is accessed from display help:



RV2W012-9

The user may also reach the InfoSeeker function by using the Start Search Index (STRSCHIDX) command. The STRSCHIDX command lets a user access the main help index and other indexes without using the Help key or F11.

Deciding Which Topics to Put in InfoSeeker: InfoSeeker topics usually consist of conceptual, procedural, and reference information.

Conceptual information usually answers the question “Why?” Conceptual information includes overviews, rationales, advantages, comparisons and contrasts, and diagrams.

Procedural information answers the question “How do I . . . ?” Procedural information always consists of a series of steps.

Reference Information typically answers the question “What is . . . ?” Reference information includes definitions, examples, commands, tables, prerequisites, and cautions.

Defining InfoSeeker Topics and Root Words: The :ISCH tag defines the title of a topic in the index and specifies the root words that serve as the link between the topic and the search words (synonyms) entered by the user. The tag appears immediately after the :HELP tag to which it refers. There can only be one :ISCH tag within a single help module.

For each :ISCH tag, there can be several lines of root words, provided that the total number of root words is no more than 50. If more than one line of root words is used, ROOTS= must be repeated at the beginning of the second line and subsequent lines:

```
:PNLGRP.  
:HELP name=entry1.  
:ISCH ROOTS='root1 root2 root3 root4 root5'  
ROOTS='root6 root7 root8 root9 root10'  
ROOTS='root11 root12 root13 ... root50'.  
Title of First Topic  
:P.  
This is the first InfoSeeker module in this panel group.  
:EHELP.  
:EPNLGRP.
```

The root words on all lines must be enclosed in apostrophes and a period must be placed only at the end of the last line of root words. The topic title follows the period on the :ISCH tag and may be placed on the line immediately following the period.

Designating Synonyms for Root Words: The :ISCHSYN tag defines the words (synonyms) that, if entered by a user, match a specific root word. If a word that is entered by a user is a synonym for a root word, then a match is found for each topic whose :ISCH tag contains that root.

If you want a word that is used as a root word to be used as a synonym as well, you must include the word as a synonym on the :ISCHSYN tag. For example:

```
:ISCHSYN ROOT='ocean'.ocean water sea
```

The synonyms for the :ISCHSYN tag must be entered on one line, and at least one :ISCHSYN tag must exist for each root word. If more than one line is needed, more :ISCHSYN tags may be entered for the same root word.

UIM does not differentiate between synonyms entered in uppercase, lowercase, or mixed case. For this reason, it is not necessary to repeat synonyms to cover all the different cases.

You may use alphabetic or numeric characters for synonyms; however, the following characters (including their hexadecimal equivalents) are not allowed to be used as a synonym or part of a synonym:

.	(period)
((left parenthesis)
)	(right parenthesis)
;	(semicolon)
,	(comma)
?	(question mark)
:	(colon)

The :ISCHSYN tags may be placed anywhere in the panel group, but to make maintenance easier, place them all in one area (such as at the beginning of your panel group or in a panel group object that contains only :ISCHSYN tags).

The following example shows some :ISCHSYN tags and the :ISCH tags that use them:

```
:PNLGRP.  
:ISCHSYN ROOT='ocean'.ocean water sea  
:ISCHSYN ROOT='lake'.lake water pond  
:ISCHSYN ROOT='definition'.definition define description what  
:ISCHSYN ROOT='definition'.summary concept information explanation  
:HELP name='defocean'.  
:ISCH ROOTS='definition ocean'.  
Definition of ocean  
:P.  
An ocean is one of the five large bodies of salt water, which  
together cover nearly three-fourths of the world.  
:EHELP.  
:HELP name='deflake'.  
:ISCH ROOTS='definition lake'.  
Definition of lake  
:P.  
A lake is a body of standing water that is enclosed by land.  
:EHELP.  
:EPNLGRP.
```

Choosing Root Words and Synonyms for InfoSeeker Topics: The following tips help you decide which words to use as root words and synonyms for your InfoSeeker topics:

- Design the root words as building blocks that can be put together in different combinations for different topics.
- The significant words in the title of a topic provide a good start on an appropriate set of root words for the topic.
- Use only one form of a word as a root word if all forms of the word have the same synonyms.
- If two similar words have the same synonyms, use only one of the words as a root word, not both.

- There will be cases where it is appropriate to use two separate root words that have many common synonyms.
- Include all synonyms that seem reasonable for the root word.
- Remember that the root words are only used to connect synonyms with help topics.
- You may have to create a special root word that applies to only one topic or a few specific topics, but these special root words should be the exception, not the rule.
- For topics whose titles include an abbreviation, the abbreviation and the major words making up the abbreviation should all be used as root words.
- Either uppercase or lowercase may be used.
- Use comment lines liberally to clarify the context in which particular root words are to be used.
- If the root word is a real word, include the same word as a synonym for the root word.
- You may want to include misspellings of commonly misspelled words as synonyms.

Defining an InfoSeeker Hierarchy: The index search subtopic (ISCHSUBT) tag identifies the help modules within the same panel group that are subtopics under the preceding topic specified on an index search (ISCH) tag. The ISCHSUBT tag must appear after the ISCH tag. Any help module that is not identified by an ISCHSUBT tag is a primary topic in the InfoSeeker hierarchy. Therefore, if no ISCHSUBT tags are used, all help modules are primary topics and there is no hierarchy.

The TOPIC attribute on the ISCHSUBT tag is used to define the subtopics for a topic. The order in which the help modules appear on the TOPICS attribute is the order in which they are displayed in the InfoSeeker hierarchy. For more information on the rules for help module names, see “Name Syntax” on page A-4.

A topic can be the subtopic of more than one topic.

Topics can be nested to no more than 16 levels.

The following example shows how the ISCH tags and ISCHSUBT tags work together to form an InfoSeeker hierarchy:

```
:PNLGRP.
:HELP name=mainhelp.
:ISCH roots='root words'.
Main Help Topic
:ISCHSUBT topics='help1'
           topics='help2'.
:
:EHELP.
:HELP name=help1.
:ISCH roots='root words'.
Help number 1
:ISCHSUBT topics='help3 help4'.
:
```



```

:EHLP.
:HELP name=help2.
:ISCH roots='root words'.
Help number 2
:ISCHSUBT topics='help3'
:
:EHLP.
:HELP name=help3.
:ISCH roots='root words'.
Help number 3
:
:EHLP.
:HELP name=help4.
:ISCH roots='root words'.
Help number 4
:
:EHLP.
:EPNLGRP.

```

This UIM source creates the following InfoSeeker hierarchy:

```

                                InfoSeeker

Type options, press Enter. (+ indicates an expandable topic)
  5=Display topic  6=Print topic  7=Expand topic  8=Compress topic

Opt  Topic
      Title of this index
-      Main Help Topic
-      Help number 1
-      Help number 3
-      Help number 4
-      Help number 2
-      Help number 3

Or type search words and press Enter. (* indicates a topic match)

F3=Exit help      F5=All topics  F6=Main topics      F11=Hide structure
F12=Cancel        F13=Information Assistant  F18=More indexes  F24=More keys

```

National Language Considerations: The InfoSeeker function can be used with either double-byte character support (DBCS) or single-byte character support (SBCS) data. When DBCS data is used, the device from which it is requested must be capable of entering and presenting the data in DBCS. The object which contains the InfoSeeker data is marked as containing DBCS data when appropriate. The system determines if the device is capable of handling the DBCS data.

When the data is being prepared for DBCS format and the InfoSeeker function is used with that data, consider the following:

- When the InfoSeeker data is prepared for a DBCS system, the synonyms entered on the ISCHSYN tag must be in double-byte character mode. That is, the first byte after the tag must be a shift-out character and the last byte of the data must be a shift-in character. The system does not convert data on the ISCHSYN tag to double-byte.


- Words must be separated by a single-byte blank. From 1 to 19 double-byte characters may be combined to form a word. Intervening shift-out and shift-in characters are allowed, but are ignored by InfoSeeker.
- The words that are used to link the ISCH and ISCHSYN tags (the ROOTS attribute of the ISCH tag and the ROOT attribute of ISCHSYN tag) must be identical and should not be entered in DBCS.
- Search words can be entered in either single-byte mode or double-byte mode. Single-byte blanks can be entered to separate the words.

When the search words are shown on the screen, the double-byte character representation (the character that was actually used in the search) is shown. Special processing takes place so that InfoSeeker is not case sensitive. The search words from the ISCHSYN tag are uppercased using a translation table for the code page that is specified with the TXTCHRID attribute of the PNLGRP tag. If the search words are DBCS, they are not uppercased. Shift-out and shift-in characters are treated as blanks during parsing; leading and trailing blanks are removed. All SBCS words are uppercased using a translate table for the code page of the device description. For more information on DBCS, see Appendix D, “Double-Byte Character Set Support for Displays” on page D-1

Linking Help Modules


Hypertext is a structure of related help modules that are linked together by their common areas. The linking allows users to select one or more help modules of interest from another help module. A help module that links to one or more help modules is called an information **node**.

Without hypertext, the only way you can access help is through the associated display or the command prompt. You cannot go directly from one help module to another unless a link, an association between two information nodes, exists that makes each help module a node in a hypertext network.



RV2W014-2

Similarly, the only way you can access an InfoSeeker topic is through the InfoSeeker function. You cannot go directly from one InfoSeeker topic to another.



These restrictions make it difficult for you, first, to determine what related information exists and, second, to access the information conveniently. Hypertext makes it possible for you to identify relationships among information nodes so that you and other users can easily access the information you need.

Designing Your Links: The structure of your hypertext nodes determines the relationships among the different nodes.

Relationships that involve hierarchy (such as those between a task and its subtasks or between a command and its parameters) can be expressed as subordinate nodes below a larger node that they relate to, in the same way that an organization chart represents the management structure.

Relationships that do not involve hierarchy (such as those between a procedural node and a reference node or between two similar procedures) can be expressed as clusters of nodes.

If you are designing a complex hypertext structure, the following questions may help you make design decisions about what to link to what:

- “What don’t I understand here?”
- “What words are unfamiliar?”
- “What conceptual information is assumed?”
- “What else do I need to know to complete my task?”
- “What is the next task I want to do after this one?”
- “What other tasks are similar to this one?”
- “What would a graphical representation of this information look like?”
- “What is a specific example of this general information?”
- “What other displays or commands are related to this one?”

You are allowed as many links as you want from any one information node; however, it is not essential that each information node be linked to another node. A link implies a clear logical relationship. If the relationship is not clear and logical, no link should exist.

Creating Links: A **hypertext reference phrase** is a word or phrase that identifies a selectable hypertext link. The reference phrase is emphasized (with high intensity or color or underlining or a combination of these, depending on the display station). The hypertext reference phrase tells the user that there is more information at the other end of the link.

To create a hypertext link, use the :LINK tag to mark the beginning of the reference phrase. Use the corresponding :ELINK tag to mark the end of the reference phrase.

You define a link in one direction only, from node A to node B. The link back from node B to node A is not defined by a :LINK tag. However, the user can return from node B to node A by pressing F12. The user can also press F6 to display a list of the titles of nodes previously displayed, then position the cursor next to a title on that list and press Enter to return to and display the selected node again.

The following example uses the :LINK tag to create a link from one help module to another help module:

```
:HELP NAME='wrkjob'.Work with Jobs - Help
:XH3.Work with jobs
:P.
The Work with Jobs display shows you the status of your
:LINK PERFORM='DSPHELP job pnlgrp1'.
jobs.
:ELINK.
:EHELP.
```

The following display shows how the preceding example would look to the user:

Work with Jobs - Help

The Work with Jobs display shows you the status of your jobs.

Note that the reference phrase is emphasized when displayed. It is also preceded by three blanks for an attribute byte, a one-character field, and another attribute byte. By using the Tab key to place the cursor on this field, the user can see the additional information about the highlighted word or phrase by pressing the Enter key.

Creating and Deleting Panel Groups

The Create Panel Group (CRTPNLGRP) command creates panel groups for help displays. In the following example, the panel group named PNLSAM in library LIBSAM is created by using source file member HDMSAM in the same library.

```
CRTPNLGRP PNLGRP(LIBSAM/PNLSAM) SRCFILE(LIBSAM/SRCSAM) SRCMBR(HDMSAM)
```

The Delete Panel Group command (DLTPNLGRP) deletes panel groups from the system. In the following example, the panel group named PNLSAM in library LIBSAM is deleted:

```
DLTPNLGRP PNLGRP(LIBSAM/PNLSAM)
```

Assigning Panel Groups as Help for Commands

Panel groups can be created as help for command parameters that may be prompted.

The first help module, which contains extended help for the command, is specified for the Help identifier parameter for the Create Command (CRTCMD) command. Each additional help item in the panel group corresponds to a parameter in the command. Only one help module can exist for each parameter that can be prompted.

For a help module to be associated with a parameter, the :HELP name must use the following convention:

```
:HELP name='help-identifier/parameter-name'.
```

where help-identifier is the name specified for the Help identifier parameter in the Create Command (CRTCMD) command, and parameter-name is the name of the parameter that the help module describes.

The following example shows one way to organize a panel group for command help:

```
:PNLGRP.  
:HELP name=startcmd.  
:P.  
The text for this help module is used as the  
extended help for the command.  
:EHELP.  
:HELP name='startcmd/parameter1'.  
:P.  
This help item is used for information about the first  
parameter.  
:EHELP.  
:HELP name='startcmd/parameter2'.  
:P.  
This help item is used for information about the second  
parameter.  
:EHELP.  
:EPNLGRP.
```

Using Panel Groups in a Search Index

Panel groups that contain :ISCH, :ISCHSYN, and :ISCHSUBT tags can be added as entries in a search index. To find out how to access the InfoSeeker function, see “Understanding How InfoSeeker Works” on page 20-6.

Creating a Search Index

The Create Search Index (CRTSCHIDX) command creates a search index object. Search index entries that provide the reference to the online help information contained in one or more panel group objects may be added to this object. These referenced panel groups can be added and removed from the search index.

In the following example, a search index object named ACCOUNTING is created in the current library:

```
CRTSCHIDX SCHIDX(ACCOUNTING)
          TITLE('Accounting Help Index')
          TEXT('Accounting Help Index')
```

Adding Entries to a Search Index

The Add Search Index Entry (ADDSCHIDX) command causes a search index object to build references to the root words and synonyms for each help module in a panel group that contains an ISCH tag. The help modules in the panel group then become entries in the search index object.

When a search index object refers to several panel groups as entries, the order that the panel groups are added into the search index object determines the order the entries are displayed when search index function is shown. Similarly, the order of the help modules in a panel group define the order in which those topics appear in the search index. If the panel group defines a hierarchy, then the topics appear in the order defined by the hierarchy.

A limit of 1000 panel groups may be added to a search index object. Only one type of panel group may be added to a search index object. That is, a search index object cannot contain panel groups that use the ISCHSUBT tag and panel groups that do not use the ISCHSUBT tag.

In the following example, the panel group named PAYROLL is added to the search index named ACCOUNTING. Both the panel group object and the search index object must exist in the library list.

```
ADDSCHIDX SCHIDX(ACCOUNTING) PNLGRP(PAYROLL)
```

Removing Entries from a Search Index

The Remove Search Index Entry (RMVSCHIDX) command removes the references to a panel group from the search index object. The RMVSCHIDX command removes references to a panel group object that was added using the ADDSCHIDX command.

In the following example, entries for the panel group PAYROLL are removed from the search index ACCOUNTING. The search index object is found by searching the library list.

```
RMVSCHIDX SCHIDX(ACCOUNTING) PNLGRP(PAYROLL)
```

Deleting a Search Index

The Delete Search Index (DLTSCHIDX) command deletes a search index object from the system. The DLTSCHIDX command does not delete any panel groups that are referred to by the search index object.

In the following example, a search index object named ACCOUNTING is deleted from the library where the object is first found in the library list.

```
DLTSCHIDX SCHIDX(ACCOUNTING)
```

Copying QUSRTOOL Examples That Define Help in a Panel Group

The QUSRTOOL library provides sample DDS-described displays that access online help information using panel groups. You can copy these examples into a library of your choosing and then tailor them for your own use. For more information about these sample displays, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Defining Online Information in a Document

You can use documents created by the word processing function of AS/400 OfficeVision/400 to contain the online help information for your display.

To use documents for online help information, you must specify them in the DDS source for your application display. If you plan to use documents but have not yet specified them in your DDS source, see “Specifying Documents in Your Display File” on page 18-9.

Online documents used as help information are created using the word processing function of the OfficeVision/400 licensed program. You do not need the OfficeVision/400 licensed program on your system to run online help information, but you do need the licensed program to create an online help document.

When you create your document, you need to use help information labels to mark the specific location in the document where the information is located.

Creating a Document for Help

Follow these steps to create a help document:

1. Create a document to contain the help information source. Create the document using the Create Document (CRTDOC) command. The following example shows how to create a document named HELP.DOC in folder HELPFLD:
`CRTDOC DOC(HELP.DOC) FLR(HELPFLD)`
2. Place a help information label instruction at the beginning of the document for general information about the application display. To do this, follow these steps:
 - a. Press F5.
 - b. Type .help
 - c. Press the Enter key.
 - d. Type a label name.
 - e. Do *not* type a document and folder name unless referring to help information that is stored in another document.
3. Type general information about the display for which you are creating help information. This information appears when the Help key is pressed while the cursor is not on one of the help areas defined in the DDS for the display.
4. Perform the following for each individual prompt in the display for which you are writing the help information:
 - a. Insert a help information label instruction with a label name that describes the prompt (for example, CUSTNBR, NAME, ADDR, and STATE).
 - b. Type the help information for the prompt immediately following the help information label.

5. If desired, insert help information label instructions for the following special areas of the help information document:
 - Insert a help information label called TOC immediately before the table of contents instruction (.toc) if your help information document contains a table of contents.

Note: The Outline Heading Instruction (.h) display contains two options specifically for help information documents. The *Start on new display* and *Show heading text* prompts give you greater control over where and how your help information appears in the resolved help information document.
 - Insert a help information label called INDEX immediately before the index instruction (.ix) if your help information document contains an index.

Note: If you specify Y for the *Create help tags* prompt on the Index Instruction display, help information labels are automatically created for each letter section of the index when your document is resolved. This allows you to type, for example, the letter s to go directly to the index words starting with s when viewing the help document.
 - If your help information document contains a glossary, insert a help information label called GLOSSARY immediately before that section.
6. When you finish creating your help document source, press F3 (Exit), type Y for the *Print document* and *Display print options* prompts, and press the Enter key.
7. Page forward to page three of the Print Options display.
8. Specify Y for the *Save resolved output* prompt, specify a unique document name for the *Document* prompt, and also specify the folder where you want the help information document stored.

The resolved document is your help information document.

More information about using documents in applications is found in *Office Services Concepts and Programmer's Guide*.

Viewing the Document without Pressing the Help Key

The Display Help Document (DSPHLPDOC) command allows you to display the help information document without running an application. This command can be entered in one of the following ways:

- Specify the document name and folder in the DSPHLPDOC command to display the beginning of the help information document.
- Specify a document name, folder, and label with the DSPHLPDOC command to display the help information associated with the specified label.

Defining Online Help Information in a DDS Record

You can use DDS records for the online help information for your display.

The record formats that give the actual online help information may be included in the same member as the DDS source for the application display. The record formats may also be contained in a different display file. An example of DDS

source used for online help information is shown in “Entering the Records That Contain the Help Information” on page 18-14.

Part 5. Guidelines for IBM AS/400-Style Displays

Chapter 21. Designing IBM AS/400-Style Displays	21-1
Using the Displays Example in the QUSRTOOL Library	21-1
Recognizing the Example Objects	21-1
Installing the Example Objects	21-3
Viewing the Sample Displays, Command, and Online Help Information	21-3
Copying the Source for the Example Objects for Your Own Use	21-6
Defining Special Functions and Attributes for All Displays	21-7
Designing the Single-Choice Menu Display	21-7
Title	21-8
Instruction Line	21-8
Menu Options	21-8
Menu Selection Entry Field	21-9
Function Keys	21-9
Online Help Information	21-9
General Menu Display Operation	21-9
Designing the Entry Display	21-10
Title	21-10
Instruction Line	21-11
Prompt Area	21-11
Field Prompts	21-11
Function Keys	21-16
Online Help Information	21-16
General Entry Display Operation	21-16
Designing the Information Display	21-17
Title	21-18
Location Information	21-18
Prompt Area 1	21-18
Prompt Area 2	21-19
Instruction Line	21-19
Function Keys	21-19
Online Help Information	21-19
General Information Display Operation	21-20
Designing the List Display	21-20
Title	21-20
Prompt Area	21-21
Instruction Line	21-21
Options Line	21-21
Column Headings	21-22
Extended Action Entry	21-23
List Fields	21-23
Paging Location Information	21-23
Function Keys	21-24
Online Help Information	21-24
General List Display Operation	21-24
Operating the Controlling Entry Field	21-25
Operating Extended Action Entry	21-25
Positioning the List	21-26
Positioning to Lowercase Names in a List	21-27
Changing the List Control Field and Positioning the List	21-27
List Operation When Options Are Specified	21-27

Cursor Positioning Rules	21-29
Error Condition Rules	21-30
List Where Only One Item Can Be Selected	21-31
List Format in Empty List Situation	21-31
Defining the Function Key Area for All Displays	21-32
Optional Command Line and Identifier Field	21-32
Available Command Line Tool	21-35
Common Key Assignments	21-36
Defining Help Information for All Displays	21-41
Help for the Menu Display	21-41
Help for the Entry Display	21-42
Help for the Information Display	21-43
Help for the List Display	21-44
Defining and Presenting Messages	21-46
Designing Common User Access (CUA) Entry Level Models	21-47
Entry Dialog Actions	21-48
Single-Choice Selection (Menu)	21-49
Selection Choices and Choice Entry Field	21-50
Guidelines for Single Selection Field Operation	21-50
Entry Display	21-50
Entry Fields	21-51
Information Display	21-52
List Display	21-52
Help Information	21-54

Chapter 21. Designing IBM AS/400-Style Displays

If you use data description specifications (DDS) to implement your displays, this chapter shows the format of each AS/400 system display type, giving the position and characteristics of all key display elements, both constants and data fields. In addition, this chapter describes the common actions assigned to function keys across the AS/400 system. However, if you use the user interface manager (UIM) to implement your displays, the UIM provides the correct formatting and placement for you. For more information on UIM, see Part 3, "Programming Application Displays Using Panel Groups" on page 14-5.

By using the guidelines in this chapter, your displays will be compatible with the Systems Application Architecture* (SAA*) environment, which makes significant use of the IBM Systems Application Architecture Common User Access* (CUA*) rules and guidelines that apply to display stations.

Using the Displays Example in the QUSRTOOL Library

The purpose of the QUSRTOOL library, which is optionally installable on the base operating system, is to provide you access to examples of various tools and programming techniques that may help you with application development and management of your system.

The displays example in the QUSRTOOL library gives you access to four sample displays and a sample command. Online information is available for the displays and the command and includes the InfoSeeker function and hypertext links.

Recognizing the Example Objects

The sample displays tool in QUSRTOOL is made up of several members that will help you install, create, and delete the objects used by the example:

Table 21-1. Source Members for Displays Example in QUSRTOOL (Install, Create, and Delete)

Source Member	Source File	Object Type	Description
T0011INF	QATTINFO	N/A	Primary documentation member that tells you what to do to install the example objects in a library of your choosing. The documentation may be viewed using the DSPPFM command, CPYF to a printer, or using the SEU display function.
T0011CRT	QATTCL	*PGM	Installation program for creating all the example objects
T0011DCL	QATTCL	*PGM	Program that shows the example display file with its four sample displays, command, and online help information
T0011DLT	QATTCMD	*CMD	Command to delete all the example objects
T0011DEL	QATTCL	*PGM	Program used by the T0011DLT command to delete the example objects

The sample displays, command, and online help information are contained in the following members of QUSRTOOL:

Table 21-2. Source Members for Displays Example in QUSRTOOL (Sample Displays, Command, and Online Help Information)

Source Member	Source File	Object Type	Description
T0011CMD	QATTCMD	*CMD	Sample command
T0011CLP	QATTCL	*PGM	Command processing program (CPP) used by the sample command
T0011CHL	QATTUIM	*PNLGRP	Online help information for the sample command
TD0011DS	QATTDDS	*FILE	Example display file that contains the DDS source for a sample AS/400-style menu, entry display, information display, and list display
T0011DHL	QATTUIM	*PNLGRP	Online help information for the example display file
T0011IDX	QATTUIM	*PNLGRP	Online help information referred to by the index search object

The other objects are not contained in the QUSRTOOL library but are created when you create the example objects into your library:

Table 21-3. Objects Created When Creating Example Objects

Source Member	Object Type	Description
T0011IDX	*SCHIDX	Search index object
T0011MSGFL	*MSGF	Message file used when creating the sample command and display file

Installing the Example Objects

To install the displays example, follow the installation instructions in T0011INF. The install program places all the example objects in a library of your choosing.

Viewing the Sample Displays, Command, and Online Help Information

You can view the sample displays, command, and online help information after installing the example objects. To view the samples, enter the following commands:

- To view the sample menu, enter:

```
CALL PGM(your-library/T0011DCL) PARM(MENU)
```

The sample menu appears:

```

                                Go To Another List

Select one of the following:

    1. Work with documents in folder
    2. Work with documents to be printed
    3. Work with folders
    4. Work with nontext document data
    5. Work with text profiles

Selection
-
F3=Exit    F12=Cancel
```

Figure 21-1. Sample Menu in QUSRTOOL

Press the Help key to view the online help information for the display. The online help information shown depends on where the cursor is located when you press the Help key.

- To view the sample entry display, enter:

```
CALL PGM(your-library/T0011DCL) PARM(ENTRY)
```

The sample entry display appears.

Merge Options		
Type choices, press Enter.		
Place on job queue	-	Y=Yes, N=No
Send completion message	-	Y=Yes, N=No
Job description	_____	Name, F4 for list
Library	_____	Name, *LIBL
Adjust/paginate option	-	1=Do not adjust
		2=Line ending only
		3=Line and page ending
Multiple line report	-	Y=Yes, N=No
Collect footnotes		
in merged document	-	Y=Yes, N=No
F3=Exit F4=Prompt F12=Cancel		

Figure 21-2. Sample Entry Display in QUSRTOOL

Press the Help key to view the online help information for the display. The online help information shown depends on where the cursor is located when you press the Help key.

- To view the sample information display, enter:
CALL PGM(your-library/T0011DCL) PARM(INFO)
The sample information display appears:

[illegible]

Figure 21-4. Sample List Display in QUSRTOOL

- To view the InfoSeeker function, do the following:
 1. Type the command to show any of the displays shown in Figure 21-1 on page 21-3, Figure 21-2 on page 21-4, Figure 21-3 on page 21-5, or Figure 21-4.
 2. Press the Help key to show the help for the display.
 3. Press F11 to use the InfoSeeker function.
 4. Press F5 to show all the topics available in InfoSeeker.
 5. You can choose to view any topic shown in the list. The second topic in the list contains a hypertext link. The fourth topic in the list uses the same panel group as the help for the command.
- To view the sample command, enter T0011CMD:

Press the Help key to view the online help information for the command. The online help information shown depends on where the cursor is located when you press the Help key.

You can tailor the example objects for your own use after you copy the source from the QUSRTOOL source file. There are basically two different ways that you can copy the source from the QUSRTOOL source file:

- ## 21-6 AS/400 Guide to Programming Displays

More information about QUSRTOOL, including examples for copying QUSRTOOL source, is available in the manual *Application Development by Example*.

Defining Special Functions and Attributes for All Displays

The following functions and attributes are *required* for all AS/400-style displays:

Table 21-4. Required Functions and Attributes of All AS/400-Style Displays

Function	Description
Online help information	Available from every display using the Help key and a command attention (CA _{nn}) key as an alternative Help key. The default for the alternative Help key is CA01, which assigns the help function to F1 (the CUA designated Help key).
Blinking cursor	Blinks as long as the record appears on the display screen.
Command function keys CF03 and CF12	Allows the corresponding function keys (F3 and F12) to be active on the display
Help clearing	Ensures that only the current help is available.

The following functions and attributes are *optional* for all AS/400-style displays:

Table 21-5. Optional Functions and Attributes of All AS/400-Style Displays

Function	Description
Print key	Allows the user to print a display
Page Up and Page Down (Roll Up or Roll Down) keys	Allows the user to page the message subfile
Alternative Page Up and Alternative Page Down (Alternative Roll Up and Alternative Roll Down) keys	Assigns a command function (CF _{nn}) key as an alternative paging key (default keys are CF07 and CF08, respectively)
Keyboard locking	Avoids unlocking the keyboard until the system has finished writing the display and is ready for input.

Designing the Single-Choice Menu Display

An AS/400 system menu shows a list of choices from which the user can select one choice. It always has a title, an instruction, a list of choices, and a labeled field for typing the number of the choice selected. Figure 21-5 on page 21-8 shows an example of a menu.

```

                                Go To Another List

Select one of the following:

    1. Work with documents in folder
    2. Work with documents to be printed
    3. Work with folders
    4. Work with nontext document data
    5. Work with text profiles

Selection
-
F3=Exit    F12=Cancel
```

Figure 21-5. Sample Application Menu

Before you continue designing this display, define the required and, if desired, optional functions and attributes found in “Defining Special Functions and Attributes for All Displays” on page 21-7.

For information about viewing this sample display or copying the source for your own use, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Title

The title should be centered on line 1, in mixed case, and displayed in high intensity.

Instruction Line

The guidelines for an instruction line are as follows:

- The instruction line is located on line 3 and begins in position 2. It tells the user to choose between the options listed on the display.
- The instruction line format for a menu is:
Select one of the following:
Note that the instruction line ends in a colon.
- All instruction lines on system displays are specified as blue on color displays.
- Leave line 4 blank and begin the menu options on line 5.

Menu Options

The guidelines for menu options are as follows:

- Begin the options following one blank line after the instruction line.

- List the options (one per line) starting in position 7 for options 1 through 9 and position 6 for options 10 and above. The option number is followed by a period and is not highlighted.
- Limit the number of options to a maximum of 10 wherever possible.
- Options are single-spaced and in numeric order. A gap in the numeric sequence is indicated by one blank line, regardless of how many numbered options are missing.
- Capitalize the first letter of the first word of the option text; the remaining words should be capitalized as appropriate for a sentence.
- There is no punctuation at the end of each line of the option text.
- If Sign-off is an option on a menu, it should have option number 90.
- Existing option numbers should not change when new options are added.

Menu Selection Entry Field

The guidelines for the menu selection entry field are as follows:

- The length of a menu selection entry field is one position for option numbers 1 through 9, and two positions for option numbers 10 or greater (up to 99).
- The menu selection entry field is located in a fixed position relative to the function key area. It begins in position 7 on the second line above the top (or only) line of the function key area.
- The selection prompt is on the line above the menu selection entry field and begins in position 2.
- The text of the selection prompt is:
Selection
- The line immediately above the top line of the function key area is blank.

Function Keys

Guidelines for defining the function key area are available in “Defining the Function Key Area for All Displays” on page 21-32.

Online Help Information

Online help information for this sample display using the user interface manager (UIM) is available in QUSRTOOL. For information on how to use the source in QUSRTOOL, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Guidelines for defining the online help information are available in “Help for the Menu Display” on page 21-41.

General Menu Display Operation

Following is a summary of what happens when the user presses the Enter key with or without making any entries on the menu:

- If there is no entry in the selection entry field, the menu remains on the display (no-operation instruction) and an informational message is displayed, if the keyboard is not locked. For example:
Enter option number or command. Press Help for details.

- If the value entered was not a valid menu option, a message such as:
Value entered is not a valid menu selection
should be issued.
- If there is an entry that is determined to be a valid option, the requested action is processed.

Designing the Entry Display

Entry displays let users type in entry field, and are typically used to provide the system parameters and options associated with an action request. Figure 21-6 shows an example of an entry display.

Merge Options

Type choices, press Enter.

Place on job queue	—	Y=Yes, N=No
Send completion message	—	Y=Yes, N=No
Job description	_____	Name, F4 for list
Library	_____	Name, *LIBL
Adjust/paginate option	—	1=Do not adjust
		2=Line ending only
		3=Line and page ending
Multiple line report	—	Y=Yes, N=No
Collect footnotes		
in merged document	—	Y=Yes, N=No

F3=Exit F4=Prompt F12=Cancel

Figure 21-6. Sample Entry Display

Before you continue designing this display, define the required and, if desired, optional functions and attributes found in “Defining Special Functions and Attributes for All Displays” on page 21-7.

For information about viewing this sample display or copying the source for your own use, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Title

The title should be centered on line 1, in mixed case, and displayed in high intensity.

Instruction Line

The guidelines for an instruction line are as follows:

- The first character of each instruction line begins in position 2.
- The instruction line for an entry display is a mandatory field in mixed case characters. The format is one of the following, depending on what is to be entered:

Type choices, press the Enter key.

Type changes, press the Enter key.

Type information, press the Enter key.

- The top instruction line for an entry display ends in a period.
- All instruction lines on system displays are specified as blue on color displays.
- Although a single instruction (one sentence) is recommended, two instructions are allowed. Each instruction should fit on a single line with the first character of each line beginning in position 2. There is no blank line between the instructions. For example,

Type choices, press Enter.
Press F16 to send.

- A single instruction can have a maximum length of two lines. The line that is carried over is indented two spaces (begins in position 4).

Type information to define the.....
of the distribution list, press Enter.

Prompt Area

In general, the columns containing the field prompts and entry fields should be on the left half of the display, and the column containing the list of possible choices should be on the right half of the display. If all the prompts for a request cannot be shown in the prompt area of a single display, make paging of the prompt area possible.

Field Prompts

The guidelines for field prompts are as follows:

- Field prompts are in normal sentence capitalization and are located to the left of the field they identify.
- The first letter of the first word of the prompt should be uppercase; the remaining text should be lowercase, unless grammatically incorrect to do so.
- There is no punctuation at the end of the prompt.
- A series of periods (dots) is used to connect the field prompt and the input field.
- Dots are spaced every other character. The farthest right dot is in the last position within the column width specified for the field prompt, and the dots are placed every other position back to the prompt text. There must be three blank spaces between the farthest right dot and the input field the prompt identifies.
- The closest dot to the prompt text is two or three positions after the prompt (minimum of one blank between prompt text and dot).

- For input fields, there should be room for two or more dots; otherwise dots should not be shown.

Prompt . . . _____ (room for at least 2 dots)

Long prompt _____ (no room for 2 dots)

- Indentation of field prompts and their corresponding input fields is allowed to show a level of hierarchy.
- The field prompt column is separated from the column containing the input field by 3 character positions (blanks).
- When two or more lines of field prompts are presented, the starting positions of the prompts, the dots, and the input fields are aligned.
- Field prompts on entry displays are preceded by an instruction line beginning in position 2. The field prompts start in position 4.

For example:

Type changes, press Enter.

```
Customer name . . . . . _____
Customer address . . . . . _____
Telephone number . . . . . _____
```

The instruction line is separated from the first field prompt by one blank line.

- If field prompt text carries over to a second line, it is indented an additional two spaces. The input field is after the last line.

```
Record format
  of file . . . . . _____
```

- The use of leader dots with an unformatted (continuous) entry field that carries over to multiple lines is the same as with standard formatting. If the field carries over to another line, however, it must extend to position 80 and carry over to position 1 on the following line.

```
Cause . . . . . _____
_____
```

- Entry fields formatted on a line-by-line basis should occupy individual lines beginning with the line following the prompt. The entry fields should be indented two positions from the beginning of the prompt.

The prompt is not followed by leader dots. Never use leader dots unless the field being identified is on the same line.

```
Memo
_____
_____
_____
_____
```

- When a single piece of data to be entered has multiple parts, the parts can be put on one line if they are understood by the user and considered one piece of data.

```
Social security number . . . . . _ _ _
Row/column . . . . . _ _
```


A From/To date in a field prompt should be formatted as two fields on one line as follows:

```
Date filed . . . . . From  __/__/__ To  __/__/__ MM/DD/YY
Document date . . . . . From  __/__/__ To  __/__/__ MM/DD/YY
```

- Any indication of the type of value (for example, Name), range of value (for example, 1 to 99), or specific value (for example, Y=Yes, N=No) should not appear with the field prompt, but should be shown only in the possible choices area.
- For a qualified name hierarchy, indent *both* the prompt text and the entry field by two positions.
- Indent prompts under a group heading by two positions. A group heading has no corresponding input field. The group heading should be followed by a colon. It can extend to more than one line, but only one level of indent is allowed.
- Do not show an entry field if the value on the display is not meaningful. If entry fields are conditionally meaningful, place conditionally valid prompts on a display separate from the prompt they are dependent on.

As an alternative, the prompt can be indented under a group heading that defines the conditions. For example:

```
Place on job queue . . . . . _ Y=Yes, N=No
For choice Y=Yes:
Send completion message . . . . _ Y=Yes, N=No
```

Entry Fields: A *required* entry field requires the user to type a value. Such a field cannot be supported by a default. An *optional* entry field does not require the user to type a value. The program can always get a value for an optional entry field by defining a default.

Entry fields take two forms. The first form requests a user-supplied value, like a name, descriptive text, or address. Frequently, these fields can accept a value from a list of values of variable length and contents. When such a list of valid choices exists, F4 should be supported to allow the user to request the list and simply choose from it.

```
File . . . . . _____ Name, F4 for list
```

The second type of entry field supports a selection from a fixed set of choices. CUA calls this a *Selection* field. If only one choice can be selected, the choices should be numbered. For example:

```
Type style . . . . . 1 1=Prestige elite (12 pitch)
                        2=Courier (10 pitch)
                        3=Essay standard
```

The only exceptions to numbering the choices are when the answers are Yes or No and when the choice value has significance to the user by itself.

If the list of values is longer than five lines, F4 should be supported.

When the prompt requires a Yes or No response, Y and N should be valid entries. For example:

```
Duplex . . . . . Y Y=Yes, N=No
```

When a display first appears, the cursor should be positioned on the first entry field that the user will type into. This is usually the first field unless a field specified on an earlier display is carried over to this display.

On some entry displays it is desirable to indicate previous user entries in an entry field. For example, if a user typed some command values prior to requesting prompting, those user-supplied values would be flagged on the prompt.

The greater than symbol (>) is used as the indication. In the entry display format, there are three blank spaces between the last leader dot and the beginning of the input field. The > is placed in the middle space of those three blank spaces.

Rules for Entry Fields: The following rules apply to the entry fields themselves:

- Required fields cannot have a default. A subvalue of a required specification can have a default. For example, a file name parameter is required. No default file name is defined but a default library qualification of the file name can be provided.
- Required entry fields must be displayed in high intensity. The field prompt and possible choices information are in normal intensity. If a value is entered in error the value should be shown again in reverse image and underlined.
- Optional entry fields should be normal intensity.
- Wherever possible, optional entry fields should have a defined and displayed default value.
- Starting positions for entry fields must be left-justified and aligned (unless there are hierarchical fields).
- If defined, default values should appear in the input fields. Values shown in fields are left-justified, including numbers that are displayed as character values (see Figure 21-6 on page 21-10). When values shown in fields are specified as numeric, they are right-justified.
- User-supplied values typed in the entry fields override the default values.
- Use the underline attribute to indicate the length of the entry field. The indicated length should be the same as the maximum number of characters that can be entered.
- The entry field can extend into the possible choices information and even carry over into the field prompt area on subsequent lines if needed. If an unformatted, or continuous, field carries over to another line, it must extend to position 80 and carry over to position 1 on the following line. For example:

Message text

If a list of possible choices is appropriate for an extended length input field (see "Descriptive Text Area (Possible Choices Information)" on page 21-15), the choices may be shown after the input field or accessed through F4.

- Echoed errors (incorrect values in input fields) are displayed again in reverse image. The keyboard should be unlocked so that the user can correct the error without having to press Error Reset before making the correction. The cursor should be positioned at the first field in error.

Note: If reverse image is used in a highlighted input field (for example, a required field), the highlight attribute should be turned off (changed to normal intensity) to avoid a no display situation with 5250 display stations.

- If a field supports F4 for a list of choices, F4 must remain available if an error is made in the field. This is important in helping the user correct the error.

If the entry display can be paged and the first error is on the currently displayed fields, show the display as is without special positioning. If the first error is not on the currently displayed fields, position the first error at the top of the area that can be paged.

Descriptive Text Area (Possible Choices Information): Possible Choices information should be shown in the description area to the right of entry fields for which only a predefined set of values or a limited range of values is allowed. If the number of values is too great to be shown, or if the values are dynamic, as in a list of document names, F4 should be supported. The phrase *F4 for list* must appear as Possible Choices information for that field. (If F4 is supported for all fields on the display, *F4 for list* does not have to appear for each field.) A description of the values should also be provided in the Help information supporting the entry field.

The following rules apply to Possible Choices information:

- Information for all entry fields on a display should have the same starting position.
- Choices are separated by one comma and one blank if shown in a horizontal character string.

Y=Yes, N=No

QDKT, QTAPE1, QTAPE2, *SAVF

Name, *ALL

Choices are aligned on the left and on separate lines if shown vertically. No comma or other punctuation is shown at the end of any line.

Y=Yes

N=No

1=Prestige elite (12 pitch)

2=Courier (10 pitch)

3=Essay standard (proportional)

4=Essay bold (proportional)

- Capitalize the first word on either side of the equal sign, regardless of whether it is the first value, last value, or only value. For example:

1-255, Blank=Entire instruction

Blank=Entire instruction, *NONE=None of instruction

- Specific values that can be typed are shown in uppercase.

Files _____ Name, *NONE

- Yes and No should be specified by Y=Yes, N=No.
- Use 'generic*' to indicate that generic names must be followed by an asterisk.

For example:

Files _____ Name, generic*

- Identify key numeric ranges. For example:

0-99

If the range is not important, do not include it. For example, if there is no limit to the value, do not show anything.

- If a numeric value is being prompted and the value must be in specific units, identify the type of units. For example:

Time in seconds

- In a series of possible choices without space to show all the values, show the most useful beginning with the default and ending with an ellipsis.
- Show a word in quotation marks only when the value being prompted needs to be in quotation marks.

Function Keys

Guidelines for defining the function key area are available in “Defining the Function Key Area for All Displays” on page 21-32.

Online Help Information

Online help information for this sample display using the user interface manager (UIM) is available in QUSRTOOL. For information on how to use the source in QUSRTOOL, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Guidelines for defining the online help information are available in “Help for the Entry Display” on page 21-42.

General Entry Display Operation

The guidelines for entry display operations are as follows:

- If a user blanks out a field that has a default, return the default to the field when you show the display again after other checking is completed. *Do not issue an error message.* The function of the display is not performed so the user can accept or change the returned default.
- If a user blanks out an optional field that does not have a default, leave the field blank. *Do not issue an error message.* Processing can occur as appropriate.
- If a user blanks out a required field that has no default, a message such as
Library name is required
is displayed.
- The other fields on the display screen are checked for errors when a field is blanked out and the Enter key is pressed. In some cases, returning the default may cause an error, depending on another field on the display screen. When these errors occur, error messages should be displayed.
- In all cases, if required values are not supplied or there is no valid entries, the display is shown again with an error message indicating what is needed. Fields

For information about viewing this sample display or copying the source for your own use, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Title

The title should be centered on line 1, in mixed case, and displayed in high intensity.

Location Information

Location information for a multiple-part display is right-aligned on line 1 and is in the form:

Page xx of xx

Prompt Area 1

The guidelines for field prompts are as follows:

- Field prompts are in normal sentence capitalization and are located to the left of the field they identify.
- Field prompts for output fields are not preceded by an instruction line and begin in position 2.
- A series of periods (dots) and a colon are used to connect the field prompt and the output field.
- The colon is in the last position within the column width specified for the field prompt, and the dots are placed every other position back to the prompt text. The closest dot to the prompt text is two or three positions after the prompt (minimum of one blank between prompt text and dot).
- The field prompt column is separated from the column containing the output field by 3 character positions (blanks).
- When two or more lines of field prompts are presented, the dots and colons on each line are aligned vertically.
- Output fields are always preceded by a colon, and have no underline attributes marking the field length.
- If the prompt requires more than one line, indent the second line two positions. The output field is after the last line.

Record format
of file : _____

- For output fields, dots should be used if there is room for one or more in addition to the colon. The colon is required. There must be one blank space before the colon in the output field format.

Prompt . . . : XXXXXXX (room for more than 1 dot)

Med prompt . : XXXXXXX (room for 1 dot only)

Long prompt : XXXXXXX (no room for 1 dot)

- Indentation of field prompts and their corresponding output fields is allowed to show a level of hierarchy.

- When two or more lines of field prompts are presented, the starting positions of the prompts, the dots and colons, and the output fields are aligned.
- The use of leader dots and the colon with an unformatted (continuous) output field that carries over to multiple lines is the same as with standard formatting. The second and subsequent lines, in the case of output fields, are indented by two positions from the beginning of the prompt text.

```
Cause . . . . : XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
                XXXXXXXXXXXXXXX. XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX.
```

- Output fields formatted on a line-by-line basis should occupy individual lines beginning with the line following the prompt. The output fields should be indented two positions from the beginning of the prompt.

The prompt is followed by a colon with no intervening blank. The prompt is not followed by leader dots. Never use leader dots unless the field being identified is on the same line.

Buckslip:

```
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
```

- When the information to be shown has multiple parts, the parts can be put on one line if they are understood by the user and considered as one piece of data.

```
Social security number . . . :   XXX   XX   XXXX
Row/column . . . . . :   27   43
```

Prompt Area 2

The prompts on the second part of the information display follow the same format as those on the first part of the display.

Instruction Line

Multipart information displays use an instruction line that tells the user how to continue or end the dialog with the display. For example:

Press Enter to continue.

This bottom instruction line is placed one blank line after the last line of information or one blank line above the first function key line.

Function Keys

Guidelines for defining the function key area are available in “Defining the Function Key Area for All Displays” on page 21-32.

Online Help Information

Online help information for this sample display using the user interface manager (UIM) is available in QUSRTOOL. For information on how to use the source in QUSRTOOL, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Guidelines for defining the online help information are available in “Help for the Information Display” on page 21-43.

General Information Display Operation

This output information has been set up as separate information displays that the user progresses through by pressing the Enter key. A paging model can also be used. When the Enter key is pressed, the dialog proceeds to the next logical display. The instruction *Press Enter to continue* should be shown on the display.

Designing the List Display

List displays show a list of items from which users may select one or more and then specify one or more actions to perform on those items. Figure 21-8 is an example of a list display with an extended action entry. This example shows a list area along with entry fields at the top of the display. You can see list displays on the system both with and without these initial entry fields. This is also a special kind of list in that it has an entry field within the list itself.

```

Work with Documents in Folders

Folder . . . _____
Position to . . . . . _____ Starting character(s)

Type options (and Document), press Enter.
1=Create      2=Revise     3=Copy       4>Delete     5=View
6=Print       7=Rename     8=Details    9=Print options 10=Send
11=Spell      12=File remote 13=Paginate  14=Authority

Opt Document          Document Description              Revised   Type
___
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
___ 000000000000 000000000000000000000000000000 00000000 0000000000
Bottom
F3=Exit      F4=Folder list      F5=Refresh      F6=Print list
F9=Goto      F10=Search for document F12=Cancel

```

Figure 21-8. Sample List Display

Before you continue designing this display, define the required and, if desired, optional functions and attributes found in “Defining Special Functions and Attributes for All Displays” on page 21-7.

For information about viewing this sample display or copying the source for your own use, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Title

The title should be centered on line 1, in mixed case, and displayed in high intensity.

Prompt Area

The guidelines for field prompts are as follows:

- Field prompts are in normal sentence capitalization and are located to the left of the field they identify.
- A series of periods (dots) is used to connect the field prompt and the input field. The farthest right dot is in the last position within the column width specified for the field prompt, and the dots are placed every other position back to the prompt text. The closest dot to the prompt text is two or three positions after the prompt (minimum of one blank between prompt text and dot).
- The field prompt column is separated from the column containing the input or output field by 3 character positions (blanks).
- When two or more lines of field prompts are presented, the farthest right dots should be vertically aligned if possible.
- Field prompts that are not preceded by an instruction line (on some mixed displays) begin in position 2.
- Input fields have underline attributes marking their length.

Instruction Line

The guidelines for the instruction line are as follows:

- The first character of an instruction line begins in position 2.
- There is no blank line between an instruction line and a following options line.
- The top instruction line for a list display ends in a period.
- If the instruction line is preceded by any information, such as an entry field, it must be separated from that information by one blank line.
- The instruction line for a standard action list is as follows:
Type options, press Enter.
- The instruction line for an action list with an extended action entry is as follows:
Type options (and Xxxx), press Enter.
where Xxxx identifies the type of item the list contains, such as Dictionary, Document, and so on.
- When an instruction line followed by an options line is used with a list, the instruction and option combination is separated from the list column headings by one blank line.
- All instruction lines on system displays are specified as blue on color displays.

Options Line

The guidelines for the options line are as follows:

- The options line begins in position 4.
- Each listed option has its first letter in uppercase and is preceded by a number and equal sign with no intervening spaces. A minimum of two spaces must be left between listed options.
- Three lines of options is the maximum (it is recommended that the options line be held to two lines). When options extend to more than one line, the digits

are vertically aligned. List displays can have up to three lines of options if preferable to a switch to the F23=More options function.

- Use full word names for option labels (for example, 5=Display jobs, 8=Save library).
- If more options are not shown, put an ellipsis after the last option shown and support and show F23=More options to switch a second set of option descriptions into the instruction area.
- Use the following standardized list action codes:
 - 1 Select (used on the display resulting from pressing F4). Selects for return of value to entry field where F4 was pressed. Do not use to select an action. The other action codes for the actual action should be used. This is only used when an object or item in the list is just being chosen.
 - 1 Create. Used on lists with an extended action entry in the list, reserved for Create on all Work with... displays.
 - 2 Change or Edit.
 - 3 Copy or Hold.
 - 4 Delete or End.
 - 5 Display or Work with the actual object represented and its content. If it is an object with content, display or work with the content. If it is a description, display or work with the attributes it describes.
 - 6 Print or Release.
 - 7 Rename.
 - 8 Display attributes or Detail (the secondary display option) Work with ... attributes or Detail (the secondary work with).
 - 9 Run.
- Work with... actions should be assigned to 5 or 8 if they are not needed for Display actions. If both are used, 9 or 12 may be used for the work with option.
- The option numbers supported for any list display must be listed in order, but gaps are allowed in the sequence.
- If the option field is 2 characters (because of the number of options), typing a one-digit selection code in either position of the field should be accepted.

Column Headings

The guidelines for column headings are as follows:

- Column headings are required on list displays and must be in mixed case.
- Column headings should be left-justified over the corresponding data if the data is character or character and numeric. Column headings over numeric data only is right-justified. When the heading is longer than the data, it should be centered over the data.
- The column heading for the option field should be *Option*. (*Option* can be abbreviated *Opt* when space is limited.)
- Columns should be separated by no fewer than two spaces and no more than seven spaces.

- Column headings can occupy a maximum vertical size of three lines.

Extended Action Entry

In the extended action entry, the first line under the column headings is an entry area that cannot be paged. The entry area contains an option field and an identifier field. The identifier field is an input field with its length indicated by underline attributes and is the same length as the corresponding output fields on those lines of the list that can be paged. For example:

Opt	Document	Document Description	Revised	Type
—	_____			

Both fields have the attributes of entry fields: underline plus reverse image and cursor positioning in case of errors.

List Fields

The farthest left column in the list area is the *Option* column. It contains input fields (underlined) 1 or 2 characters long, depending on the number of options available. One-character entries are accepted in either position for two-character input fields.

The column to the right of the *Option* column should contain the information for identifying the list item or for sequencing (if the list is ordered). This column usually names the item.

Lists can be described using subfiles (see Chapter 4, “Displaying Groups of Records Using Subfiles”). Use of subfiles, however, does not support the descriptive paging information used by the system interface at the bottom of the area to be paged.

In the sample list display shown in Figure 21-8 on page 21-20, the fields on the available list lines are described using five fields on a line and nine lines in each field. The program then loads the successive nine-line blocks of data as the user pages through the file.

The fields in the *Option* column have the attributes of entry fields. The fields in the other columns, being defined as input/output (B), have the protect attribute to prevent user access.

Paging Location Information

Whenever the user is on any part other than the last part of an area that can be paged, the phrase *More...* appears highlighted (high intensity) in the location information field on the bottom separator line. When the user is on the last display of an area that can be paged, *More...* is replaced by *Bottom*.

The location information field is defined as the seven farthest right display positions of the bottom separator line. *More...* and *Bottom* are right-aligned in this field.

When multiple areas on a mixed display can be paged, each requires its own paging information. Figure 21-9 on page 21-24 shows the layout of a display with location information.

```

01                                     Display Title
02 Top Separator Line
03 Display Body
04
05 - - - - - start of paging area - - - - -
06
07
08
09
10
11
12
13
14
15
16
17
18
19
20
21 - - - - - end of paging area- - - - -
22 Bottom Separator Line
23 Function Key Area
24 Message Area

```

More...

Figure 21-9. Layout of Display with Location Information

Each allowable constant is conditioned by an indicator. The program must display the correct constant, depending on the status of the paging.

Function Keys

Guidelines for defining the function key area are available in “Defining the Function Key Area for All Displays” on page 21-32.

Online Help Information

Online help information for this sample display using the user interface manager (UIM) is available in QUSRTOOL. For information on how to use the source on QUSRTOOL, see “Using the Displays Example in the QUSRTOOL Library” on page 21-1.

Guidelines for defining the online help information are available in “Help for the Information Display” on page 21-43.

General List Display Operation

The processing priority of a mixed list display when the Enter key is pressed is as follows:

- The object name field (folder, dictionary, and so on) at the top of the display
- The *Position to* prompt
- The extended action entry
- Options within the list proper

Error diagnosis follows this same sequence.

On this type of mixed list, the input/output field at the top of the display normally contains the name of the object (folder, dictionary, and so on) whose contents are being displayed. By changing the name, for example to another valid folder name, the user is essentially issuing a display command for the contents of the newly specified folder. When the user presses the Enter key, the list display area is then replaced with a new list display.

Operating the Controlling Entry Field

The guidelines for the operation of the controlling entry field are as follows:

- Once a list of items is displayed, changing the name of the list at the top of the display while selections within the list are pending causes an error message. The pending selections are saved and the field with the changed name is in reverse image. The error message must include the name that was changed so the user can change the name back, if desired.

Blanking out the name simply results in the name being restored when the list is displayed again after pending operations are completed.

- If a list of items from folder A is being displayed and there are no pending selections entered in the list, the user may obtain a list of items from folder B by changing folder A to folder B at the top of the display and pressing the Enter key.
- While a list of items from folder A is being displayed with no pending requests, the user may perform a specific function on a particular item in folder B by changing folder A to folder B, typing in the selected option number and the identifier on the extended action entry, and then pressing the Enter key. After the option is performed, the folder B list is displayed.
- If folder A is changed to folder B and *the Enter key is not pressed*, and then a page/roll operation is attempted (with or without selections pending), the page/roll is not performed, an error message is shown, and the folder field is in reverse image.

Operating Extended Action Entry

The guidelines for the operation of the extended action entry are as follows:

- The cursor is initially positioned on the option field of the extended action entry. The cursor returns to this position after either of the following operations:
 - Position to
 - Any paging operation
- When using the Create function with an extended action entry:
 - If the user has typed valid options in the list:
 - First the Create operation is performed
 - Then the other options are performed
 - If the user has typed options in the list that are not valid:
 - No Create operation is performed; the field remains as typed
 - A message that states that options are not valid is shown
 - If the user has also typed a Position to value:
 - No Create operation is done; the field(s) remains as typed
 - The list is positioned
 - If the item to create already exists in the list:
 - The *Create* field is displayed in reverse image
 - An *Item already exists* message is shown
 - The list is not repositioned to show the existing item
- Specifying the Create option on any list line other than the extended action entry results in an error.

- Specifying the Create option creates a single new list item identified by the user (using the extended action entry). If the program requires other user-supplied information to create the list item, it must present the user with an entry display on which to supply that information.
- The user can enter any of the other options valid for that list using the extended action entry. The user must identify the list item the action is to be performed against by typing the name of that item in the input field on the extended action entry.
- Options entered on the extended action entry are valid against any item in the list proper. The user can perform an option against any item identified in the list proper.
- On the extended action entry, if an option is entered and an identifier is not, an error message should state that no function can be performed unless an identifier is specified. There are two exceptions:
 - The identifier is one of the items prompted for on an accompanying entry display that is always presented to the user
 - The program supports creating a temporary object (for example, a query) that can be named later
- If an identifier is entered and an option is not, no operation is performed against the contents of the identifier field.
- The identifier field can contain a defaulted value. When list processing is performed, the option field on the extended action entry is restored to blanks. The identifier field, however, can keep a defaulted value.

Positioning the List

The guidelines for positioning the list are as follows:

- The Position to function is used for quick repositioning of the list.
 - If the user specifies the character *S* as the starting point, the resulting list starts with the first *S* item and includes all items after that as well, not just the items beginning with *S*. When positioning to *S*, if the list contains AA, BB, SA, SB, the list is positioned to SA.
 - Once the list has been repositioned, the Page Up and Page Down keys can still be used to page to any other items in the list.
 - The special values *TOP and *BOT are supported to position the list to the beginning or end.
 - If no items are found that begin with the characters entered, the list is positioned beginning with the item immediately preceding the requested position.
- After a Position to function, the item to which the list is positioned should be at the top of the list area, the cursor should be on the first option field that follows the input-capable field (if one exists), and the *Position to* field should be blanked out.
- The *Position to* field is not checked for being a valid syntax name or a direct match on a name in the list. Instead, the user is positioned in the list where the entered string would fit based on collating sequence rules (the user can enter A& to position to where A& is in the collating sequence).
- *Position to* field entries in the list option column are ignored. If the user types characters into this prompt and presses the Enter key while operations are

pending in the list area of the list, the list is repositioned and the selections are saved, just as if a page/roll key had been pressed.

Positioning to Lowercase Names in a List

If you support a *Position to* prompt for your list, and the items in the list have lowercase characters, you should follow these rules to let the user position the list to those items:

- If the input in the *Position to* field does not begin with double quotation marks ("), the input should be folded to uppercase and positioned to the name closest to that uppercase name.
- If the input in the *Position to* field begins with double quotation marks ("b or "b"), the list should be positioned to the name closest to "b.

If the user types the ending quotation marks ("b"), you must strip them off so that list positions to the name beginning with the double quotation marks ("b). Otherwise, it will look for "b" in the collating sequence.

- If double quotation marks are used on a string that has no special or lowercase characters that would require quotation marks, they are removed, and the list is positioned to the name that is not marked by quotation marks.

Using the following list,

```
"aa"  
"bb"  
AAAAA  
BBBBB
```

- Position to "b and Position to "b" should both put "bb" at the top of the list.
- Position to "AAA," Position to "AAA, and Position to AAA should all put AAAAA at the top of the list.

Changing the List Control Field and Positioning the List

The list control field specifies what the list contains. For example, by changing the list control field from FOLDER1 to FOLDER2 and pressing the Enter key, the user gets a new list that displays the contents of FOLDER2.

Options for positioning the list include:

- If the control field is changed to a valid value (a new list can be shown), and a value is typed in the *Position to* field, show the new list positioned according to the *Position to* field.
- If the control field is changed to a value that is not valid and a value is typed in the *Position to* field:
 - Display the same list
 - Reverse image the control field and show the message
 - *Position to* field remains as typed; list is not positioned

List Operation When Options Are Specified

The following rules cover the general operation of lists that have options (actions) specified against items (objects) in the list.

List processing should follow these general rules:

- The sequence of list processing should match the sequence in which the list items are presented on the display screen; that is, proceeding from the top line to the bottom line (and from left to right if there is more than a single item on a line).
- After processing, the same view of the list that was presented before processing should be shown again (unless an error occurs).

Specific rules for list operations are as follows:

- The user can choose the same or different options for more than one list item. The choices can be made on any of the item displays that can be paged. Options are not processed until the Enter key is pressed (on the list display itself or on an entry display that was displayed after the Prompt key was pressed).
- There should not be a limit on the number of options that can be typed on a list (except the Select option).
- If the user does not have the proper authority to perform the operation, display such a message on the message line.
- Operations are performed in the order shown in the list area.

Note: Some operations supported on list displays (Delete is an example) can be grouped together on a separate display when presented for confirmation. Confirmation is given on the group of operations, but then each operation is performed in the order shown in the list.

- When list processing has completed, after having started from a page other than the first, the user is returned to the same page of the list, and the list position does not change (unless an error occurs). However, if the top entry of the page was removed as a result of a delete operation, the list is positioned such that the next remaining entry *prior* to the deleted entry is at the top of the list.

When processing is completed, after being started from the first page, the list is positioned with the current top entry in the list, even if entries were added to or deleted from the beginning of the list.

- The page/roll keys are used to move forward and backward through the list. Pressing a page/roll key causes a full page roll (all items are replaced).
- Even if a list allows a user to perform only one operation, the user should be allowed to roll even after one item has been chosen, because processing will not occur until the Enter key is pressed.
- When a page/roll key is pressed, any selections made should be saved (the operations should not be performed).
- Lists that can page will not wraparound at the beginning or end of the list.
- If multiple display operations are being performed, they should be done one at a time, with completion of each indicated by the user pressing the Enter key on the last display.
- If the user interrupts list processing before it is finished (for example, by pressing F3 or F12 from an interim display), the list is shown with all processed options blanked out (in the *Option* column). All unprocessed options are still marked. The option that was being processed when F3 or F12 was pressed

(the one where the cursor was positioned), is considered processed and, therefore, is unmarked.

- If no processing errors occur, all operations are completed prior to the list being shown again.
- If a processing error is detected, processing is interrupted at that point to allow the user to handle the error. The list can be displayed again with the option field corresponding to the error in reverse image and the cursor positioned to that field. A separate display may also be presented that allows the user to handle the error. The appropriate error message is always presented on the message line. When the user has resolved the error condition, list processing is started again.
- If multiple errors are detected, the list is displayed again with all option fields corresponding to the errors in reverse image. The cursor is positioned to the first field in error.

If the list display can be paged and the first error is on the currently displayed fields, show the display as is without special positioning. If the first error is not on the currently displayed fields, position the first error at the top of the area that can be paged.

- You can elect to have applications either dynamically update the list as the operations in the *Option* column are performed, or wait to display the updated list until the user presses F5=Refresh. Each option is described as follows:
 - A dynamic update of the list can be done if the number of entries in the list is not large and the update can occur as operations are performed without a significant delay.
 - If the number of entries is large and updating the list would result in a noticeable delay, the list should be updated only when the user presses F5=Refresh. If dynamic updating is not used, the entries that the user has operated on (by entering an option next to one or more), and therefore changed, should be annotated as to what operation has been performed on them. The annotation should be made in a status field to the right of the entry. Annotation should only be made by type of operation (for example, operations that change the item or its status, such as Delete or Change, should be annotated; operations such as Display should not.) No annotation should be made on an entry where the operation failed. The annotation should indicate the type of operation performed on the item. Show (Ended) if the entry was ended, (Held) if held, (Changed) if changed, or (Released) if released. Abbreviations that correspond to the operation performed, such as Cn1, H1d, Chg, R1s, can be used if needed.

Cursor Positioning Rules

Cursor positioning rules are as follows:

- When a list display is initially shown, position the cursor to the option field for the first item in the list. Follow this rule even when there are some secondary fields (for example *Position to*) at the top of the display.
- When a list is presented after a position list or a page/roll function, position the cursor to the first option field in the list area. After a position list function, the item to which the list is to be positioned should be at the top of the list area and the cursor should be in the option field for that item.

- When another view of the list is presented, the cursor should remain on the entry where it was (unless the cursor was not in the list area originally; then it is positioned at the first item in list).
- After selected operations have been performed and the list reappears, the following rules apply:
 - The user should always return to the same page of the list from which the Enter key was pressed. This is the primary rule.
 - Place the cursor by the last item selected. If that item is not on the current display, place the cursor by the first item on the current display.
 - If the list was positioned at the top before the Enter key was pressed, the list should stay at the top when processing is complete. For example, if an item was added to the beginning of the list, position the list to start with the new item. The user expects to see the top of the list if positioned to the top.
 - When errors are detected, position the cursor in the first option in error (options in error should be in reverse image). The list should be positioned again only if the entry that caused the error is not on the current display page.

Error Condition Rules

Error condition rules are as follows:

- When a page/roll key is pressed, option number fields are checked for entries that are valid.
- When an Exit or Refresh function is performed, the entries on the display are not processed, and errors are not returned to the user.
- If errors occur, the option field corresponding to the error is in reverse image, the cursor is positioned to that field, and the appropriate error message appears on the message line.

If the list display is can be paged and the first error is on the currently displayed fields, show the display as is without special positioning. If the first error is not on the currently displayed fields, position the first error at the top of the area that can be paged.

- If the first error is on the currently displayed fields, show the display as is without special positioning. If the first error is not on the currently displayed fields, position the first error at the top of the area that can be paged.
- Each product can have an internal limit for the number of selections that can be made from a list at one time. If the user exceeds this limit, display an error message. This error message should include these items:
 - The fact that the maximum number of allowed selections has been exceeded.
 - The amount by which this maximum number was exceeded (so the user knows how many selections to remove).

When this message is presented, *the pending selections should not be in reverse image.*

- Issue the following errors if the user attempts to page past the top or bottom of an area that can be paged:
 - Top message

Message Text: Already at top of area.

Cause: You pressed a key to move backward in an area. However, you cannot move in that direction because you are already at the top of that area.

Recovery: If you want to move displayed information backward in another area, move the cursor to that area and press either the Page Up key or the Roll Down key again.

- Bottom message

Message Text: Already at bottom of area.

Cause: You pressed a key to move forward in an area. However, you cannot move in that direction because you are already at the bottom of that area.

Recovery: If you want to move displayed information forward in another area, move the cursor to that area and press either the Page Down key or the Roll Up key again.

List Where Only One Item Can Be Selected

If more than one item is selected and the Enter key is pressed:

- List is shown again with all selections still marked
- All selections are in reverse image
- Issue the message: Only one selection allowed

If one or more items are selected and a Roll key is pressed:

- No message is issued
- Roll is performed

List Format in Empty List Situation

If the user requests a list of items and there are no items available, the rules are as follows:

1. Start the text in column 4 on the second line following the list area column headers (leave one blank line). If only one list line is available, place the text on the line immediately following the column headers.

Opt	Document	Date	Text
—	_____		
	...blank line...		
	(No documents in folder)		
2. The attributes of the text should be of normal emphasis and normal color (green).
3. If the Help key is pressed while the cursor is anywhere in the list area, processing should be done as though the list is not empty (online help information is available for the columns).
4. The text should be generic and state that the list is empty, but should not state the reason. The text should be in parentheses.
5. The text should begin with No xxxxxxxx where xxxxxxxx identifies what is not displayed. The phrase should not be followed with a period, because it is not a full sentence. For example:

(No objects in library)

6. If information about why the list is empty is desired, present it in a message on the message line.

Defining the Function Key Area for All Displays

The guidelines for the function key area are as follows:

- List active key assignments from left to right in numeric order, beginning at position 2. Active F keys cannot be omitted (with the exception of F1) unless they are displayed by the More keys function, in another set of keys. Capitalize only the first letter of the first word in the function descriptions.
- Leave three spaces between key assignments unless more are needed for alignment.
- When function keys are displayed on two lines, align the key assignments on the left (on F) if possible.

```
F3=XXXXXXXXX  F4=XXXXX  F5=XXXXXXXXXXXXX  F6=XXXXXXXXXXXXX
F7=XXXXXXXXX  F12=XXXXXXX  F13=XXXXXXX
```

- Display the keys in ascending numeric sequence (gaps in the sequence can exist).
- If one line of a two-line function key area contains a function key description that is very long (that is, forces a gap of up to seven blanks), this description may span two or more function key descriptions on the other line for the purpose of alignment. For example:

```
F3=Exit  F4=Prompt  F9=Retrieve  F12=Cancel
F13=Information Assistant  F16=System main menu
```

- If all the active keys cannot be displayed in two lines, support F24=More keys. The guidelines for what to display are:

- Enter, Help, and the Roll or Page keys should not be displayed.
- Display active function keys in multiple one-line or two-line sets. Use F24=More keys to see the next set of function keys in the function key area of a display. All sets must reserve the same number of lines, one or two.

```
F3=XXXXXXXXX  F4=XXXXX  F5=XXXXXXXXXXXXX  F6=XXXXXXXXXXXXX
F7=XXXXXXXXX  F12=XXXXXXX  F24=More keys
```

- F3=Exit and F12=Cancel must be shown in the primary set (and only in that set). Only F24 is displayed in all sets.
- Although the function keys should be in numeric sequence in each set, the application can determine which keys are in each set. The functions displayed in the primary set should be those that are used the most.
- Displayed function keys on system displays are specified as blue on color displays.

Optional Command Line and Identifier Field

You have probably seen other *system* menus with a slightly different format. Figure 21-5 on page 21-8 shows a menu from within an application, and is the type of menu you should create. System menus have an additional *system identifier* in the upper left corner. This is used as a name in conjunction with the GO command. Such names have to be present as object names in system tables.

The system uses names in this identifier field only on menus accessed by the GO command. Using this identifier field on application menus could confuse the user because the names would not work with the GO command. A user can access the system menus, given the menu identifier. Using the GO command, a user can specify a particular menu, by the menu identifier, or, if a particular menu is not known, a generic identifier can be used. In this case, the user is shown the Work with Menus display and from this list, can specify a menu to run. For more information on how to create display file menus, see Chapter 9, “Creating and Accessing Menus Using Display Files” on page 9-1.

System menus also use a command line as the entry field for menu selection. The only command area support DDS provides is to allow you to define an entry field (with accompanying field prompt) into which a command could be entered. You write all code to support this entry area as a command area, including passing the command to the system, handling the Prompt function, handling the Retrieve function, and handling help for the command. “Available Command Line Tool” on page 21-35 provides information on a command line function available in the QUSRTOOL library to assist in putting a command line on an application display.

To support commands from within an application, make one or more system displays with a command line available or provide a command line on one or more application displays.

Note: If the commands change something the application is dependent on, results that cannot be predicted can occur.

With the AS/400 system you can limit command entry to the system commands and application commands you want. Typically, this is the best approach for the user. You can limit the user to special commands by specifying *YES for the *Limit capabilities* prompt on the Create User Profile (CRTUSRPRF) display, as in Figure 21-10 on page 21-34. You can then create commands with the Create Command (CRTCMD) command. Specify *YES for the *Allow limited users* prompt to make the command available to limited users as in Figure 21-11 on page 21-34 and Figure 21-12 on page 21-35.

Note: Most commands are shipped with ALWLMTUSR(*NO). See the *Limit capabilities* (LMTCPB) prompt on the Create User Profile (CRTUSRPRF) display for a list of ALWLMTUSR(*YES) commands. You can change IBM-supplied commands with the Change Command (CHGCMD) command. If you change an IBM-supplied command you must keep track of your changes in a control language (CL) program because the commands are replaced with each release.

Create User Profile (CRTUSRPRF)		
Type choices, press Enter.		
User profile	_____	Name
User password	*USRPRF_____	Name, *USRPRF, *NONE
Set password to expired	*NO_____	*NO, *YES
User class	*USER_____	*USER, *SYSOPR, *PGMR...
Current library	_____	Name, *NONE
Initial program to call	*NONE_____	Name, *NONE
Library	_____	Name, *LIBL, *CURLIB
Initial menu	MAIN_____	Name, *SIGNOFF
Library	*LIBL_____	Name, *LIBL, *CURLIB
Limit capabilities	*YES_____	*NO, *PARTIAL, *YES
Text 'description'	*BLANK_____	
<hr/>		
F3=Exit F4=Prompt F5=Refresh F10=Additional parameters F12=Cancel F13=How to use this display F24=More keys		Bottom

Figure 21-10. Create User Profile Entry Display

Create Command (CRTCMD)		
Type choices, press Enter.		
Command	_____	Name
Library	*CURLIB_____	Name, *CURLIB
Program to process command . .	_____	Name
Library	*LIBL_____	Name, *LIBL, *CURLIB
Source file	QCDSRC_____	Name
Library	*LIBL_____	Name, *LIBL, *CURLIB
Source member	*CMD_____	Name, *CMD
Text 'description'	*SRCMBRTXT_____	
<hr/>		
Additional Parameters		
Validity checking program . . .	*NONE_____	Name, *NONE
Library	_____	Name, *LIBL, *CURLIB
Mode in which valid	*ALL_____	*ALL, *PROD, *DEBUG, *SERVICE
+ for more values	_____	
F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display F24=More keys		More...

Figure 21-11. Create Command Display with Additional Parameters Selected

Create Command (CRTCMD)

Type choices, press Enter.

Where allowed to run	*ALL _____	*ALL, *BATCH, *INTERACT...
+ for more values		
Allow limited users	*YES _____	*NO, *YES
Maximum positional parameters .	*NOMAX _____	0-75, *NOMAX
Message file for prompt text . .	*NONE _____	Name, *NONE
Library	*LIBL _____	Name, *LIBL, *CURLIB
Message file	QCPFMSG _____	Name
Library	*LIBL _____	Name, *LIBL, *CURLIB
Current library	*NOCHG _____	Name, *NOCHG, *CRTDFT
Product library	*NOCHG _____	Name, *NOCHG, *NONE
Authority	*USE _____	Name, *USE, *ALL, *CHANGE...

Bottom

F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display
 F24=More keys

Figure 21-12. Second Display of Additional Parameters

If your application uses commands, you should define an entry field (with accompanying field prompt) on the display. To match the AS/400 system, command lines should appear as follows:

```
Selection or command
====> _____
```

- The one-line command line begins in position 7 on the line immediately above the function key area and ends in position 79 on the same line.
- The command line is identified by a command line prompt, beginning in position 2. If the command line is used to enter either the menu selection or a command, the text of the prompt is:
Selection or command
- The command entry arrow (====>) is in positions 2 through 5 of the first line of the command line.
- The command entry arrow (====>) is normal intensity like the command line.

Available Command Line Tool

General-Use Programming Interface

The QUSCMDLN program can be used to display a pop-up window that contains a command line. The command line can be used to enter system commands. QUSCMDLN can be called by any user program. More information about QUSCMDLN is available in *System Programmer's Interface Reference*.

End of General-Use Programming Interface

The QUSRTOOL library on the AS/400 system contains a command line function and documentation to assist in putting a command line function on an application display (member CMDLINE, in file QATTINFO, in QUSRTOOL). One way to

access this function is by using the Work with Members Using PDM (WRKMBRPDM) display, shown in Figure 21-13 on page 21-36.

Work with Members Using PDM (WRKMBRPDM)

Type choices, press Enter.

File	QUSRT00L	*PRV, name
Library	QATTINFO__	*PRV, name, *LIBL, *CURLIB
Member	CMDLINE__	*PRV, name, *generic*...
Member type	*ALL__	*PRV, name, *generic*...

Bottom

F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display

F24=More keys

Figure 21-13. Work with Members Using PDM Entry Display

Common Key Assignments

Table 21-6 summarizes common AS/400 function key assignments and indicates when each key is used. The keys identified as CUA can be used only for the function defined. If the function is not available, the key should not be used for another function.

Non-CUA keys are keys commonly used on the system for a particular function. If the function is available on a display, the key assignment given should be used for compatibility with system key assignments. If the function is not being used, you can use the key assignment for an application-specific function.

Table 21-6 (Page 1 of 5). Function Key Assignments

Name	Key	CUA	Usage/Function
Help	F1	Yes	Active on all displays, but not shown on the display. F1 is also mapped to the Help function but is not displayed in the function key area.
Set 1/Set 2	F2	Yes	Required when applications need more function keys than can be assigned to the 24 numbered keys. F1=Help, F2=Set n, F3=Exit, F9=Retrieve/command, and F12=Cancel are required in both sets of function keys.

Table 21-6 (Page 2 of 5). Function Key Assignments

Name	Key	CUA	Usage/Function
Exit	F3	Yes	<p>Usually active and shown on all displays. F3 exits the application or a unit of work within the application. If the application is exited, the user is returned to the display from which the application was requested. If a unit of work within an application is exited, the user is returned to a predefined point within the application that serves as a point of focus for requesting work (usually a primary menu). User input is normally discarded; however, if pressing the Exit key could cause loss of data and require extensive user effort to retrieve or reconstruct, an exit display should be provided to give the user the option of saving the data before exiting.</p> <p>The Exit function must be available on all displays except:</p> <ul style="list-style-type: none"> • Displays used for confirmation of the delete action • List display shown as a result of pressing F4 • Exit displays provided to give the user the option of saving the data before exiting <p>The following describes the use of the Exit key for specific display types:</p> <ul style="list-style-type: none"> • Menu. If the menu is part of a dialog that began with a primary menu or the initial menu after sign-on (for example, the primary or initial menu is the first menu on the current menu stack), returns to this primary or initial menu. Pressing the Exit key from the primary menu exits the current dialog and returns to the display from which the dialog was entered. • List display. Returns to the menu or other display from which the list display was requested. User input is discarded. • Entry display. Returns to the menu or other display from which the entry display (or set of entry displays) was requested. User input is discarded. However, an exit display can be provided to give the user the option of saving the entries or changes. • Information display. Returns to the menu or other display from which the information display (or set of information displays) was requested. • Any help display. Returns to the display from which help was originally requested.

Table 21-6 (Page 3 of 5). Function Key Assignments

Name	Key	CUA	Usage/Function
Prompt	F4	Yes	<p>Should be supported whenever the display contains an entry field for which the valid entries are known but are not shown on the display. F4 provides a list of selectable values (usually a list of names) related to the field where the cursor is currently positioned. When the user selects one or more values from the list, those values are used as input values for the field.</p> <p>If F4 is pressed and the function is not supported for the field containing the cursor, the user receives an error message.</p> <p>If the function is supported for the field containing the cursor and either a default value exists or the user makes an entry in the field, the value in the field is kept and the list is displayed. If the user selects a value from the list, this value replaces the previous value in the field. If the user does not select a value, the previous value is kept.</p> <p>If the user leaves the field blank and presses F4, the list is also displayed for a value to be selected.</p> <p>When a command is typed on a system command line and F4 is pressed, a prompt for the command (an entry display with input fields for the command parameters) is displayed.</p>
Refresh	F5	Yes	<p>Should be used where the Refresh function is appropriate. F5 can start resetting defaults on an entry display, or update (refresh) system output being displayed. The using program determines what is appropriate depending on the display type:</p> <ul style="list-style-type: none"> • Menu and help display. Not usually used. • Entry display. Clears user input and shows the display again with the original values provided at the time the display was first shown. The cursor is repositioned at the first logical input field on the display. If the entry fields are on a display that can be paged, Refresh should position the cursor at the beginning of the list of entry fields. • List display. Clears user input and updates the display to show the current status. Refresh should maintain the same position in the list. The list should be shown again with the entry that was at the top of the list page when F5 was pressed still at the top of the list page, and with the cursor positioned at the top list item. • Display with output-only fields (data output items). Updates the information variable fields to show the current values. If the information variable fields are in a display that can be paged, Refresh should maintain the same position in the list of fields.

Table 21-6 (Page 4 of 5). Function Key Assignments

Name	Key	CUA	Usage/Function
			<p>Summary of list positioning rules with the Refresh function:</p> <ol style="list-style-type: none"> 1. The display is shown again with the entry that was at the top of the display still at the top of the display. 2. If that entry no longer exists, the entry following it is shown at the top of the display. 3. When the first entry in the list was at the top, the first entry is shown at the top again (even though it may be a new first entry). 4. If the entry that was at the top of the display no longer exists and there are no entries following it, the display is shown with the first entry of the entire set of values at the top of the display. 5. If the location-determining attributes of the entry at the top of the display have changed, the list is shown with the entries starting where the old entry would have been.
Create	F6	No	<p>Optional. F6 is used for the Create function on a list display that has not converted to the combination list with 1=Create. However, using a combination list is preferred on the AS/400 system. Summary of uses for F6:</p> <ul style="list-style-type: none"> • May be requested with the cursor in any position. • Go to separate display in which additional object(s) can be defined. • On completion, show list display from which Create request was made again. • Show created object(s) sorted into the list. • Requests that were pending at the time F6 was pressed should not be processed, but should still be pending. <p>Note: When a very large number of new entries can be added, such as with Add Entries to a Distribution List, it may be a good application decision to not allow an Add or Create function until other pending requests are completed. In this case, a message can be issued when F6 is requested and other requests are pending.</p>
Retrieve	F9	Yes	Required on all panels or pop-up windows with a command line.
Command	F9	Yes	Used to display a pop-up window containing a command line.

Table 21-6 (Page 5 of 5). Function Key Assignments

Name	Key	CUA	Usage/Function
Cancel	F12	Yes	<p>Must be active and shown on all displays. F12 returns to the previous logical display. It provides the basic navigation function of backing up one step in the interface, as described for the following displays:</p> <ul style="list-style-type: none"> • Menu. Backs up to the previous menu or other display from which the menu was directly started. Any user input is discarded. • Entry and List displays. Backs up to the previous display. User input is discarded. (If significant data would be lost, an exit display should be shown.) • Information displays. Backs up to the display previously shown. <p>Note: If a set of information (including input or output fields) can logically be presented in a paging format, use a display that can be paged instead of the Enter and Cancel keys for forward and backward navigation through the information.</p> <p>This function must be available on all displays, except when a logical Cancel function is precluded by other factors. An example is when only the Exit function is appropriate because the user must first verify (using an exit display) whether data is to be saved or not.</p>
XXXX Main Menu	F16	No	<p>Optional for applications. F16 must be active and shown on system menus. It provides a direct path to the system or application primary menu. A target menu other than the system main menu must be explicitly stated. This key would normally be used within an application to provide a direct path to the application main menu. When this key is pressed, any user input is discarded. If F3 or F12 is pressed on the target menu, the user is returned to the display where F16 was pressed.</p>
Top of list	F17	No	<p>Optional on displays that can be paged. F17 pages to the top or beginning (same as *TOP in the <i>Position to</i> field). This key should be supported when the <i>Position to</i> field is not present.</p>
Bottom of list	F18	No	<p>Optional on displays that can be paged. F18 pages to the bottom or end (same as *BOT in the <i>Position to</i> field). This key should be supported when the <i>Position to</i> field is not present.</p>
Left	F19	Yes	<p>Should be operational on all displays with a horizontal area that can be paged. There are no common columns of information between successive views.</p>
Right	F20	Yes	<p>Should be operational on all displays with a horizontal area that can be paged. There are no common columns of information between successive views.</p>
More options	F23	No	<p>Optional. List displays only. Use F23 to display the next set of options in the instruction area of a list display. Use when the first set of options shown in up to three lines is not complete. It is recommended that an ellipsis be shown after the last option in the options area if other options exist that cannot be seen until F23 is pressed. The most important functions are shown first, and the less frequently used options are shown after F23 is pressed.</p>
More keys	F24	No	<p>Optional. Use F24 to see more active function keys in the function key area of a display. Use when all key descriptions will not fit in the two-line function key area.</p>

Defining Help Information for All Displays

Help for AS/400 system displays consists of specific information on fields where the cursor is positioned, and, when the cursor is positioned anywhere else, general information on what the display is for and how the user interacts with it.


Help on the system also includes a system help index. This section describes the type of help support for fields provided by the system for each display type.

Help for the Menu Display

The following table and illustration describe the help information for each menu help area:

Table 21-7. Type of Help for Each Help Area–Menu Display

Cursor Position	Help Information	UIM Tag
On line containing option number and description	What function each option performs	HELP element of MENU1 tag
In function key area	Function performed by each function key turned on for the display	HELP element of KEYL and KEYI tag
Any other display position	Beginning of general help for display (user can page through all help for display, which includes description of how to use the entry line)	HELP element of PANEL tag
On command line with no entries	Entry at beginning of general help for panel (user can page through all help for display)	HELP element of PANEL tag
On command line with option number entered	What function each option performs	HELP element of MENU1 tag



RV2W027-4

The following table gives the DDS considerations for help on menu displays:

Table 21-8. DDS Considerations—Help on Menu Displays

Item Help Area	Area Covered
Each menu option	From position 1 to the farthest right display position on the line containing the option number and the option text
Function key area	From position 1 on the first line of the function key descriptions to the farthest right display position on the last line of the function key descriptions

The remainder of the display is defined as the general help area.

Help for the Entry Display

The following table and illustration describe the help information for each entry display help area:

Table 21-9. Type of Help for Each Help Area—Entry Display

Cursor Position	Help Information	UIM Tag
On input field or descriptive lines associated with input fields (data entry item)	Use of each possible entry in input field	HELP element of DATAI tag
In function key area	Function performed by each function key turned on for the display	HELP element of KEYL tag
Any other display position	Beginning of general help for display (user can page through all help for display)	HELP element of PANEL tag




Figure 21-14. Help Areas for Entry Displays

The following table gives the DDS considerations for help on menu displays:

Table 21-10. DDS Considerations—Help on Entry Displays

Item Help Area	Area Covered
Each item	From position 1 on the first line of the item text to the farthest right display position on the last line of either (1) the input field(s) or (2) the possible choices text, whichever occupies the most lines (see Figure 21-14).
Function key area	From position 1 on the first line of the function key descriptions to the farthest right display position on the last line of the function key descriptions


The remainder of the display is defined as the general help area.

Help for the Information Display

The following table and illustration describe the help information for each information display help area:

Table 21-11. Type of Help for Each Help Area—Information Display

Cursor Position	Help Information
In output field or descriptive lines associated with output field.	Meaning of output field. (A data output field is an area on a display consisting of descriptive text and an associated output field into which variable data is written at display time.)
In function key area	Function performed by each function key turned on for the display
Any other display position	Beginning of general help for display (user can page through all help for display)



RV2W043-5

Figure 21-15. Help Areas for Information Displays

The following table gives the DDS considerations for help on information displays:

Table 21-12. DDS Considerations—Help on Information Displays

Item Help Area	Area Covered
Data output items	From position 1 to the farthest right display position on the line (see Figure 21-15)
Function key area	From position 1 on the first line of the function key descriptions to the farthest right display position on the last line of the function key descriptions


The remainder of the display is defined as the general help area.

Help for the List Display

The following table and illustration describe the help information for each list display help area:

Table 21-13. Type of Help for Each Help Area—List Display

Cursor Position	Help Information	UIM Tag
In input field or descriptive lines associated with input fields	Use of each possible entry in input field	HELP element of LISTCOL tag
In specific column	Meaning and use of column. This includes how to use that entry field (for example, creating a list entry or performing an action against a list entry without paging to it) for the column containing the extended action entry.	HELP element of LISTCOL tag
In function key area	Function performed by each function key turned on for the display	HELP element of KEYL tag
Any other display position	Beginning of general help for display (user can page through all help for display)	HELP element of PANEL tag



RV2W025-3

Figure 21-16. Help Areas for List Displays

The following table gives the DDS considerations for help on list displays:

Table 21-14. DDS Considerations—Help on List Displays

Item Help Area	Area Covered
Each column	From the farthest left position on the first line of the column heading to the farthest right position on the last line of column data. The farthest left position is defined as the farthest left character position of either the longest heading line or the data column, whichever is wider. The farthest right position is defined as the farthest right character position of either the longest heading line or the data column, whichever is wider. (See Figure 21-16).
Function key area	From position 1 on the first line of the function key descriptions to the farthest right display position on the last line of the function key descriptions

The remainder of the display is defined as the general help area.

Defining and Presenting Messages

For compatibility with the system, an application should present an error message any time a user types a selection or actual value that is not allowed. The message itself should provide as much information as possible to allow users to continue processing. On the system, messages appear on the bottom line of the display.

Messages should be supported by help information that gives an expanded description of the error (if necessary) and a remedy to the problem. In general, the help information should state what happened and, if possible, what to do if an action is required. The highest priority should be given to a statement of action required.

The user can request help for the message being displayed by moving the cursor to the message line and pressing the Help key. Message help is presented on a separate display and can extend to more than one display if needed.

The DDS keyword `ERRMSG` is easy to use, but locks the keyboard and lets the user see only one message at a time. This option is acceptable if there are only a few messages. However, to keep the user's interaction with the message easy, the goals are to:

- Not make the user unlock the keyboard to respond to the message
- Provide a formatted display that can be paged for additional message information

To accomplish this, you should use a subfile containing messages from a program message queue (`SFLMSGKEY`, `SFLMSGRCD`, and `SFLPGMQ` keywords) rather than use the `ERRMSG`, `ERRMSGID`, `SFLMSGID`, and `SFLMSG` keywords.

To provide messages that tell the user what is correct, not simply that an entry is not valid, validity checking in your program is recommended over using the `CHECK`, `RANGE`, `VALUES`, and `COMP` keywords in DDS. When these keywords are used, a message tells the user that what is entered is not valid, but no explanation or indication of what is valid is given.

Message presentation on the AS/400 system adheres as closely as possible to the following rules:

- Detected input errors result in an error message and the function is not performed.
- Error messages are shown on the display where the values that are not valid or options were entered. The error message does not appear on a separate display started by the data entered and the Enter action.
- When errors are detected on data entered on a display, the display is shown again with:
 - The first value(s) in error visible. In the case of a display that cannot be paged, the display is shown again with the erroneous values still in the fields where they were entered. For the display that can be paged where the user only entered values on one display page of values, the display is shown again as it appeared when the Enter key was pressed. For the display that can be paged where the user has paged and entered values on multiple pages, the display is shown again with the first page of values that contains an error.
 - The erroneous values are shown in reverse image (if the display station supports this).

Note: If reverse image is used in a highlighted input field, the highlight attribute should be turned off (changed to normal intensity) to avoid a no display situation with 5250 display stations.
 - The cursor is positioned on the first field with a value in error.
 - The keyboard is not locked.
- When multiple errors are detected on data entered on a display:
 - Error messages for all errors on the display can be viewed, one at a time, on the message line using the roll/page key.
 - If multiple messages are waiting, the last three positions of the message line contain "b+b" (b indicates blank) in high intensity to indicate additional messages are present. The roll/page keys allow viewing the other messages. To page through the messages, the user moves the cursor to the message line and presses the appropriate roll/page key.
 - When multiple messages are presented, the messages are in the same order as the values in error appear on the display.
 - When the user takes the appropriate corrective action (pressing a key, for example), the error message is removed. Only messages for errors that have not been corrected are present on the message line or waiting to be viewed.
- If a user requests help for an item other than the message (the cursor is not on the message line when the user presses the Help key), the message remains on the display when the user returns from the Help displays.

Designing Common User Access (CUA) Entry Level Models

CUA has defined the entry model to guide the programmer of an existing simple, transaction-oriented application in redesigning the user interface of that application to use some of the standard interface components defined by CUA. The key difference between entry and the other CUA models is that entry is action oriented and follows an action-object process sequence. Other CUA models have an object-action orientation.

The CUA entry model closely resembles the existing AS/400 interface. The user is typically asked to select an action or task from a menu or list and then indicate the object to which that action applies.

Entry Dialog Actions

Certain CUA entry dialog actions must be shown in the function key area when they are available on the display area. Table 21-15 summarizes CUA entry dialog actions indicating the function key assignments and when each key is used. If the function is not available, the key should not be used for another function.

Table 21-15 (Page 1 of 2). CUA Entry Dialog Actions

Function	Key	Usage Requirements
Enter	Enter	Active on all displays, but not shown in function key area
Help	F1, Help	Help must be active on all displays, but is not shown on the display. F1 must also be mapped to the Help function. F1 is not shown in the function key area. CUA screens should have F1 turned on for help; however, DDS also allows the Help key to be assigned to this function.
Exit	F3	Must be active and shown on all displays except: <ul style="list-style-type: none"> • Confirmation displays. • List display that appear as a result of the user pressing F4. • Exit displays that result from the user pressing F3=Exit where the decision is made as to save or not. • Pop-up windows
Prompt	F4	Must be supported whenever the display contains an entry field for which the valid entries are known but cannot be shown in the possible choice description area. Required on any display with a command line.
Refresh	F5	Required on action list displays (except selection lists) and strongly recommended on other list displays. Should be used on other displays where the refresh function is appropriate.
Backward	Page Up, F7	Must be operational on all displays with an area that can be paged. Not shown in function key area. Page up shows the previous page of data. CUA displays should have Page up turned on for paging; however, DDS also allows F7 to be assigned to this function.
Forward	Page Down, F8	Must be operational on all displays with an area that can be paged. Not shown in function key area. Page down shows the next page of data. CUA displays should have the Page Down key turned on for paging; however, DDS also allows F8 key to be assigned to this function.
Retrieve	F9	Required on all displays with a command line.
Command	F9	Used to display a pop-up command line.

Table 21-15 (Page 2 of 2). CUA Entry Dialog Actions

Function	Key	Usage Requirements
Cancel	F12	Must be active and shown on all displays except: <ul style="list-style-type: none"> • When the previous display was a prompt for a function that had already been processed. • On a display where only the Exit function is appropriate because the user must not be allowed to exit without first verifying (by way of an Exit display) whether data is to be saved.
Left	F19	Must be operational on all displays with a horizontal area that can be paged. There are no common columns of information between these successive views.
Right	F20	Must be operational on all displays with a horizontal area that can be paged. There are no common columns of information between these successive views.

Function Key Area and Message Line Relationship: The entry model has the message line placed as a separator between other display areas and the function key area, and command area if used. A command line would be above the function key area and below the message line.

The guidelines for the function key area do not change, except for placement. A single line of function keys is on line 24. Two lines of function keys occupy lines 23 and 24. The message area is on the line immediately above the function keys.

Single-Choice Selection (Menu)

A CUA single-choice selection field displays a list of choices from which the user can select one choice. The display always has a title, an instruction, a list of choices, and a labeled field for typing the number of the choice selected. Figure 21-17 shows an example of a CUA single-choice selection field on a display.

Go To Another List

Select one of the following:

- 1. Work with documents in folder
- 2. Work with documents to be printed
- 3. Work with folders
- 4. Work with nontext document data
- 5. Work with text profiles

F3=Exit F12=Cancel

Figure 21-17. Example of an Application Menu

Selection Choices and Choice Entry Field

The guidelines for selection choices and the choice entry field are as follows:

- Begin the choices one blank line after the instruction line.
- A choice entry field is on line 5 preceding the first choice. The length of a choice entry field is one position if the number of choices is less than 10, two positions if any choice numbers are 10 or greater (up to 99).
- The choice entry field starts in position 2.
- List the choices (one per line) starting in position 4 if the number of options is nine or less. The number is followed by a period and is not highlighted.
- If any choice number exceeds 9, the choice entry field requires 2 characters (in positions 2 and 3). Option numbers 1 through 9 start in position 6, and numbers 10 and higher start in position 5.

Guidelines for Single Selection Field Operation

The single selection field allows two methods of interaction. The user can enter the number of the choice in the choice entry field and press the Enter key, or can move the cursor directly to the desired choice and press the Enter key.

Use the following rules:

- If the cursor is in the choice entry field, or 1 character position to the right (position 3 or 4), process the choice in the choice entry field.
- If the cursor is not in or immediately to the right of the choice entry field, and the choice entry field contains a blank, process the choice on the same line as the cursor.
- If the cursor is not in or immediately to the right of the choice entry field, the choice entry field is not blank (a value has been entered), and the value in the field is not the same as the choice being selected, present a message that asks the user to choose between the choice being pointed at and the choice indicated by the value in the choice entry field.

Entry Display

Entry displays let users type in entry fields, and are typically used to indicate the system parameters and options associated with an action request. Figure 21-18 on page 21-51 shows an example of an entry display.

```

Merge Options

Type choices, press Enter.

Job queue . . . . . - 1. Placed on job queue
                   - 2. Not on job queue
Completion message . . . . . - 1. Message sent
                   - 2. Message not sent
Job description . . . . . _____ + Name
      Library . . . . . _____ Name, *LIBL
Adjust/paginate option . . . . . - 1. Do not adjust
                   - 2. Line ending only
                   - 3. Line and page ending
Report line format . . . . . - 1. Multiple lines
                   - 2. No multiple lines
Footnotes . . . . . - 1. Collected
                   - 2. Not collected

```

CUA entry fields take two forms. The first form is an entry field that requests a user-supplied value, like a name, descriptive text, or address. Frequently, these fields can accept a value from a list of values that is of variable length and contents. When such a list of valid choices exists, support F4 to allow the user to request the list and simply choose from it.

File + Name

```
Type style . . . . . - 1. Prestige elite (12 pitch)
                        2. Courier (10 pitch)
                        3. Essay standard
```

If the list of values is more than can be shown in one to five lines, support F4.

Duplex - 1. Yes
2. No

Chapter 21. Designing IBM AS/400-Style Displays **21-51**

One or both sides . . . 1. Both sides
2. One side

Selection choices are aligned on the left and shown on separate lines. No comma or other punctuation is shown at the end of any line.

- 1. Prestige elite (12 pitch)
- 2. Courier (10 pitch)
- 3. Essay standard (proportional)
- 4. Essay bold (proportional)

Information Display

A CUA version of the information display shown could be paged instead of being in two parts as the AS/400 example shown in Figure 21-7 on page 21-17. Also, the explanatory information for Yes and No would not be required because Yes and No would not have been used for the entry function for which this information display is based. See “List Display” for a discussion of CUA paging information.

Figure 21-19 shows an example of the sample information display in CUA format.

[illegible]

Figure 21-19. Example of an Information Display

List Display

Like the information display, a CUA version of the sample list display would differ primarily in the display of paging information. Figure 21-20 on page 21-53 shows an example of a list display.

CUA uses the word **More** followed by a colon and then paging symbols to indicate additional information exists outside the visible area, and the direction to page to see that information.

If the user can page in all four directions, backward, forward, left, and right, reserve space for all four paging symbols. If the user can page in only two directions,

Help Information

CUA help information resembles AS/400 help information by having a number of defined functions available from every help display via function keys. These function keys and their functions are:

- F1=Help for help
- F2=Extended help
- F3=Exit
- F5=Tutorial
- F9=Keys help
- F11=Help index
- F14=Tutorial

These functions cannot be provided by DDS using function keys from help displays. For information on DDS capabilities for help information, see “Defining Help Information for All Displays” on page 21-41.

Part 6. Appendixes

Appendix A. UIM Panel Group Definition Language	A-1
Tag Content Formatted as Paragraphs	A-2
Panel Areas	A-2
Panels	A-2
Panel Group Objects	A-3
Help on Panels	A-3
Panel Group Organization	A-4
Name Syntax	A-4
Symbols	A-5
Comments	A-6
Imbeds	A-6
DBCS Graphic Literals	A-6
Hexadecimal Literals	A-6
APPFMT (Application Formatted Area)	A-8
Required Attributes	A-8
Optional Attribute	A-8
Application Formatted Data	A-9
Example: Application Formatted Area	A-9
BOTINST (Bottom Instruction)	A-10
Optional Attribute	A-10
Optional Text	A-10
CHECK (Validity Checking)	A-11
Required Attribute	A-11
Optional Attributes	A-11
Example: Validity Checking	A-12
UIM Source	A-12
CIT (Title Citation)	A-13
Optional Text	A-13
Example: Title Citations	A-13
UIM Source	A-13
Results	A-13
CLASS (Class Definition)	A-14
Required Attributes	A-14
Optional Attributes	A-17
Example: Class Definitions	A-22
UIM Source	A-22
Display Forms of Numeric Values	A-22
Display Forms of Character, Date, and Time Values	A-23
CMDLINE (Command Line)	A-24
Required Attribute	A-24
Optional Attribute	A-24
Optional Text	A-24
COND (Condition Definition)	A-25
Required Attributes	A-25
Optional Attribute	A-26
Example: Conditioning an Option	A-27
UIM Source	A-27
COPYR (Copyright)	A-28
Required Text	A-28
DATA (Data Presentation Area)	A-29

Required Attribute	A-30
Optional Attributes	A-30
Optional Text	A-31
Print Formatting Considerations	A-31
Example 1: Data Entry Panel	A-32
UIM Source	A-32
Results	A-32
Example 2: Two-Column Format in a Data Entry Panel	A-32
UIM Source	A-32
Results	A-33
Example 3: Two Presentation Areas for Data Items	A-33
UIM Source	A-33
Results	A-34
Example 4: Data Presentation Area with a Menu Area	A-34
UIM Source	A-34
Results	A-34
Example 5: Data Entry Panel with a Nested Data Group	A-34
UIM Source	A-34
Results	A-35
DATAC (Data Item Choices)	A-36
Optional Attribute	A-36
Optional Text	A-36
DATACOL (Data Column)	A-37
Required Attribute	A-37
Optional Text	A-37
DATAGRP (Data Group)	A-38
Optional Attributes	A-38
Optional Text	A-39
DATAI (Data Item)	A-40
Required Attributes	A-40
Optional Attributes	A-41
Optional Text	A-43
DATAIX (Data Item Extender)	A-45
Required Attributes	A-45
Optional Attributes	A-46
DATASLT (Data Selection Field)	A-49
Required Attributes	A-49
Optional Attributes	A-49
Optional Text	A-50
Example 1: Data Entry Panel	A-51
UIM Source	A-51
Results	A-51
Example 2: Multiple-Selection Field	A-51
UIM Source	A-52
Results	A-52
DATASLTC (Data Selection Field Choice)	A-53
Optional Attributes	A-53
Optional Text	A-54
DL (Definition List)	A-55
Optional Attribute	A-55
Required Tags	A-55
Optional Tags	A-56
Example 1: Definition List	A-56
UIM Source	A-56

Results	A-56
Example 2: Compact Definition List	A-56
UIM Source	A-56
Results	A-56
FIG (Figure)	A-57
Optional Attribute	A-57
Optional Tag	A-57
Example: Sample Figure	A-57
UIM Source	A-57
Results	A-57
HELP (Help Module)	A-58
Required Attribute	A-58
Optional Attributes	A-58
Optional Text	A-59
Example: Help Panel Definition	A-60
UIM Source	A-60
Results	A-60
HP0 through HP9 (Highlighted Phrase)	A-61
Optional Text	A-61
H1 through H4 (Heading)	A-63
Required Text	A-63
Example: Heading Tags	A-63
UIM Source	A-63
Results	A-63
IMHELP (Imbed Help)	A-64
Required Attribute	A-64
Example: Imbedded Help	A-64
UIM Source	A-64
IMPORT (Import)	A-65
Required Attributes	A-65
Optional Attributes	A-65
INFO (Information Area)	A-66
Required Attribute	A-66
Optional Attributes	A-66
Optional Text	A-66
Print Formatting Considerations	A-67
ISCH (Index Search)	A-68
Required Attribute	A-68
Required Text	A-68
Example: Index Search	A-68
UIM Source	A-68
ISCHSUBT (Index Search Subtopic)	A-69
Required Attribute	A-69
Example: Index Search Hierarchy	A-69
UIM Source	A-69
ISCHSYN (Index Search Synonym)	A-70
Required Attribute	A-70
Required Text	A-70
Example: Index Search Synonyms	A-70
UIM Source	A-70
KEYI (Key List Item)	A-72
Required Attributes	A-72
Optional Attributes	A-73
Optional Text	A-73

Example: Key Definitions	A-73
UIM Source	A-73
Results	A-73
KEYL (Key List)	A-74
Required Attribute	A-74
Optional Attribute	A-74
Example: Key List	A-74
UIM Source	A-74
LINES (Unformatted Lines)	A-75
Optional Text	A-75
Example: Unformatted Lines	A-75
UIM Source	A-75
Results	A-75
LINK (Hypertext Link Definition)	A-76
Required Attribute	A-76
Optional Attributes	A-76
Conditional Expressions	A-77
Bidirectional Considerations	A-78
Example: Hypertext Link	A-78
UIM Source	A-78
Results	A-79
LIST (List Area)	A-80
Required Attributes	A-81
Optional Attributes	A-81
Optional Text	A-83
Print Formatting Considerations	A-84
Example 1: List Area	A-84
UIM Source	A-84
Results	A-85
Example 2: List Area with Three Layout Columns	A-85
UIM Source	A-85
Results	A-85
Example 3: List Area with List Column Groups	A-85
UIM Source	A-85
Results	A-86
Example 4: Dynamic List Column Heading Formatting	A-86
UIM Source	A-86
Results	A-87
LISTACT (List Action)	A-88
Required Attributes	A-88
Optional Attributes	A-89
Optional Text	A-92
Confirmation Panel Requirements	A-92
Confirmation Panel Conventions	A-92
Example: List Actions	A-93
UIM Source	A-93
Results	A-93
LISTCOL (List Column)	A-94
Required Attributes	A-94
Optional Attributes	A-95
Optional Text	A-96
Formatting Considerations	A-97
LISTDEF (List Definition)	A-98
Required Attributes	A-98

Optional Attributes	A-98
LISTGRP (List Column Group)	A-101
Required Attributes	A-101
Optional Attribute	A-101
Optional Text	A-101
LISTVIEW (List View)	A-103
Required Attribute	A-103
Optional Attribute	A-103
LP (List Part)	A-105
Example: List Part	A-105
UIM Source	A-105
Results	A-105
MBAR (Menu Bar)	A-106
Required Attribute	A-106
Optional Attributes	A-106
Example: Menu Bar	A-106
UIM Source	A-106
Results	A-107
MBARC (Menu Bar Choice)	A-108
Required Attributes	A-108
Required Text	A-108
MENU (Menu Area)	A-109
Required Attribute	A-109
Optional Attribute	A-109
Optional Text	A-110
Example 1: Simple Menu Area	A-110
UIM Source	A-110
Results	A-110
Example 2: Menu Area with Groups	A-110
UIM Source	A-110
Results	A-111
MENUGRP (Menu Group)	A-112
Optional Attribute	A-112
Optional Text	A-112
MENUI (Menu Item)	A-113
Required Attributes	A-113
Optional Attributes	A-113
Optional Text	A-114
NT (Note)	A-115
Optional Text	A-115
Example: Using a Note	A-115
UIM Source	A-115
Results	A-115
OL (Ordered List)	A-116
Optional Attribute	A-116
Required Tag	A-117
Example: Ordered List	A-117
UIM Source	A-117
Results	A-117
OPTLINE (Option Line)	A-118
Optional Attribute	A-118
Optional Text	A-118
P (Paragraph)	A-119
Optional Text	A-119

Example: Paragraph Tag	A-119
UIM Source	A-119
Results	A-119
PANEL (Display Panel)	A-120
Required Attributes	A-120
Optional Attributes	A-121
Optional Text	A-124
Example: Panel Definition	A-124
UIM Source	A-124
Results	A-125
PARML (Parameter List)	A-126
Required Tags	A-126
Example: Parameter List	A-127
UIM Source	A-127
Results	A-127
PC (Paragraph Continuation)	A-128
Example: Paragraph Continuation	A-128
UIM Source	A-128
Results	A-128
PDACCEL (Pull-Down Accelerator)	A-129
Required Text	A-129
PDFLD (Pull-Down Field)	A-130
Optional Attribute	A-130
PDFLDC (Pull-Down Field Choice)	A-131
Required Attributes	A-131
Optional Attributes	A-131
Optional Text	A-133
Confirmation Panel Requirements	A-133
Confirmation Panel Conventions	A-133
PK (Programming Keyword)	A-135
Optional Attribute	A-135
Required Text	A-135
PNLGRP (Panel Group)	A-136
Optional Attributes	A-136
PRTHEAD (Print Head Panel)	A-139
Required Attribute	A-139
Optional Attributes	A-139
Optional Text	A-140
Layout of the Title Lines	A-140
Example: Print Title Line	A-142
PRTPNL (Print Panel)	A-143
Required Attribute	A-143
Optional Attributes	A-143
Optional Text	A-143
PRTTRAIL (Print Trailer Message)	A-145
Required Text	A-145
Example: Trailer Message	A-145
UIM Source	A-145
PV (Programming Variable)	A-146
Required Text	A-146
RT (Reverse Text)	A-147
Example 1: Left-to-Right Formatting on a Right-to-Left Panel	A-147
UIM Source	A-147
Results	A-147

Example 2: Left-to-Right Formatting on a Left-to-Right Panel	A-148
UIM Source	A-148
Results	A-148
SL (Simple List)	A-149
Optional Attribute	A-149
Required Tag	A-149
Example: Simple Lists	A-150
UIM Source	A-150
Results	A-150
TI (Translation List Item)	A-151
Optional Attribute	A-151
Optional Text	A-151
TL (Translation List)	A-152
Optional Attributes	A-152
Examples: Translation List	A-152
UIM Source	A-152
UIM Source	A-153
TOPINST (Top Instruction)	A-154
Optional Attribute	A-154
Optional Text	A-154
TT (Truth Table)	A-155
Required Attributes	A-155
Example: Truth Table	A-155
UIM Source	A-155
TTROW (Truth Table Row)	A-156
Required Attribute	A-156
UL (Unordered List)	A-157
Optional Attribute	A-157
Required Tag	A-157
Example: Unordered Lists	A-158
UIM Source	A-158
Results	A-158
VAR (Variable Definition)	A-159
Required Attribute	A-159
Optional Attributes	A-159
Dialog Variables Defined by UIM	A-159
VARRCD (Variable Record Definition)	A-162
Required Attributes	A-162
Optional Attributes	A-162
XH1 through XH4 (Extended Help Headings)	A-163
Required Text	A-163
Formatting Rules	A-163
Example: Sample Headings	A-163
UIM Source	A-163
Results	A-163
XMP (Example)	A-164
Example: Formatting an Example	A-164
UIM Source	A-164
Results	A-164
Appendix B. UIM Dialog Commands	B-1
The VARUPD Attribute	B-4
ACTIONS (Menu Bar Cursor Action)	B-4
CALL (Call Program)	B-4

Required Parameter	B-5
CANCEL	B-6
Optional Parameter	B-6
CHGVIEW (Change View)	B-6
CMD (System Command)	B-7
CMDLINE (Command Line)	B-7
DSPHELP (Display Help)	B-7
Required Parameter	B-7
Optional Parameter	B-8
ENTER	B-8
Considerations for Using the ENTER, HELP, and PROMPT Dialog	
Commands	B-8
EXIT (Exit Display)	B-8
Optional Parameter	B-9
EXTHELP (Extended Help)	B-9
HELP	B-9
HELPHelp	B-9
HELPIDX	B-9
HOME (Display Home Menu)	B-10
KEYSHelp	B-10
MENU	B-10
Required Parameter	B-10
Optional Parameter	B-10
MOREKEYS (Display More Function Keys)	B-10
MOVETOP (Move to Top)	B-11
MSG (Display Message)	B-11
Required Parameter	B-11
Optional Parameter	B-11
PAGEDOWN	B-12
PAGEUP	B-12
PRINT (Print Display)	B-12
PROMPT	B-12
Prompting an Entry Field	B-13
Prompting an Action List Option or Command	B-13
PULLDOWN (Display Pull-Down Menu)	B-14
RETRIEVE (Retrieve Command String)	B-14
RETURN (Return Control to Application)	B-14
Required Parameter	B-14
Appendix C. Feedback Area Layouts for Display Files	C-1
Open Feedback Area	C-1
Device Definition List	C-4
I/O Feedback Area	C-6
Common I/O Feedback Area	C-6
I/O Feedback Area for Display Files	C-9
Get Attributes	C-12
Appendix D. Double-Byte Character Set Support for Displays	D-1
Double-Byte Character Set Fundamentals	D-1
DBCS Code Scheme	D-1
Shift-Control Characters	D-3
Using Double-Byte Data	D-3
How You Can Use	D-3
How You Cannot Use	D-4

Double-Byte Character Size	D-4
Processing Double-Byte Characters	D-4
Basic Characters	D-4
Extended Characters	D-4
What Happens When Extended Characters Are Not Processed	D-4
Device File Support	D-5
What a DBCS File Is	D-5
When to Indicate a DBCS File	D-5
How to Indicate a DBCS File	D-5
Improperly Indicated DBCS Files	D-6
Display Support	D-6
Inserting Shift-Control Characters	D-6
Number of Displayed Extended Characters	D-6
Number of Input Fields on a Display	D-6
Effects of Displaying Double-Byte Data at Alphanumeric Work Stations	D-7
Effects of Displaying DBCS-Graphic Fields on Double-Byte Displays	D-7
Application Program Considerations	D-7
Designing Application Programs That Process Double-Byte Data	D-7
Changing Alphanumeric Application Programs to DBCS Application Programs	D-7
DBCS Font Tables	D-8
Finding Out if a DBCS Font Table Exists	D-8
Copying a DBCS Font Table onto Tape or Diskette	D-9
How to Copy a Table onto Tape or Diskette	D-9
Copying a DBCS Font Table from Tape or Diskette	D-9
How to Copy a Table from a Tape or Diskette	D-9
Deleting a DBCS Font Table	D-10
How to Delete a DBCS Font Table	D-10
Starting the Character Generator Utility	D-10
Copying User-Defined Double-Byte Characters	D-10
DBCS Font Files	D-10
DBCS Sort Tables	D-11
Using DBCS Sort Tables on the System	D-12
Finding Out if a DBCS Sort Table Exists	D-12
Saving a DBCS Sort Table onto Tape or Diskette	D-12
When to Save a DBCS Sort Table onto Tape or Diskette	D-12
Restoring a DBCS Sort Table from Tape or Diskette	D-12
Copying a Japanese DBCS Master Sort Table to a Data File	D-12
When to Copy the Japanese DBCS Master Sort Table to a Data File	D-12
How to Copy the Japanese DBCS Master Sort Table to a Data File	D-13
Copying a Japanese DBCS Master Sort Table from a Data File	D-13
When to Copy the Japanese DBCS Master Sort Table from a Data File	D-13
How to Copy the Japanese DBCS Master Sort Table from a Data File	D-13
Deleting a DBCS Sort Table	D-14
When to Delete a DBCS Sort Table	D-14
How to Delete a DBCS Sort Table	D-14
DBCS Conversion Dictionaries	D-14
System-Supplied Dictionary (for Japanese Use Only)	D-14
User-Created Dictionary	D-15
Commands for DBCS Conversion Dictionaries	D-15
Creating a DBCS Conversion Dictionary	D-15
Editing a DBCS Conversion Dictionary	D-16
Displaying and Printing the DBCS Conversion Dictionary	D-19
Deleting a DBCS Conversion Dictionary	D-19


DBCS Conversion (for Japanese Use Only)	D-19
Where You Can Use DBCS Conversion	D-20
How DBCS Conversion Works	D-20
Using DBCS Conversion	D-20
Performing DBCS Conversion	D-21
Examples	D-22
Considerations for Using DBCS Conversion	D-25
Appendix E. Display File Return Codes	E-1
Major Code 00	E-1
Major Code 02	E-1
Major Code 03	E-2
Major Code 04	E-2
Major Codes 08–11	E-3
Major Code 34	E-3
Major Code 80	E-3
Major Code 81	E-6
Major Code 82	E-7
Major Code 83	E-10
Appendix F. Edit Codes	F-1
OS/400 Edit Codes	F-1
Examples of Editing Using OS/400 Edit Codes	F-3
User-Defined Edit Codes	F-4
Using User-Defined Edit Codes	F-5
Example of a User-Defined Edit Code	F-5
Appendix G. System/36-Compatible Display Data Management	G-1
Clearing Lines on the Display	G-1
Input Data for Display File Records	G-2
Input Data from the Work Station Controller	G-2
Self-Check	G-2
Return Input	G-3
Erase Input Fields	G-3
Display Attributes	G-3
Positioning the Cursor	G-4
Displaying Messages	G-4
Put Override	G-6
Handling Signed Numeric Data	G-7
Function Keys	G-7
Help Key Considerations	G-7
Using Command Keys to Exit Application Help	G-8
Cancel-Invite Operation	G-8
Retain Command and Function Keys	G-9
System/36 Functions Not Supported	G-9
Restricted DDS Keywords/Functions	G-10

Appendix A. UIM Panel Group Definition Language

This appendix describes the UIM panel group definition language. Following some introductory material on the nature of the language syntax and the structure of the panel group definitions, the

actual statements of the language, the **tags**, are defined. The tag definitions in this chapter are organized alphabetically.

A sample syntax diagram is shown below:



The TAGNAME specifies the name of the tag. This sample tag has two attributes: VATTR, for value attribute; and KATTR, for keyword attribute. The second attribute in this example is shown on the alternate branch to indicate that it is an optional attribute. This attribute can have one of three values: DEFAULT, VALUE1, and VALUE2.

DEFAULT is the value used when you do not specify a value for the KATTR attribute. If there is a default value, it appears on the group choice line above the attribute name, as DEFAULT appears on the line above the KATTR attribute name. Instead of using the DEFAULT value, you may choose either VALUE1 or VALUE2. These values are entered as shown in the syntax diagram.

The *value* is a value you enter, as specified for that attribute. An attribute *value* must be enclosed with apostrophes (') when it contains characters other than A through Z or 0 through 9, and it must be contained on one source line. To enter an apostrophe in a value surrounded by apostrophes, type the apostrophe twice.

The *tag-content* is text associated with that tag that may be displayed or printed for the user. It is designed to allow national language translation.

The period at the end of the tag and before the tag content is known as the **markup/content separator**. This separator is required for all tag markup.

The source for a panel group can be entered in either lowercase, uppercase, or mixed case characters. The UIM converts the tag names, attribute names, and attribute values to uppercase as

appropriate during the compile process. For example, the following uses of the example tag, TAGNAME, are equivalent specifications:

```
:TAGNAME VATTR=VALUE.
:tagname vattr=value.
:Tagname Vattr=Value.
```

Tag attributes do not need to be specified in the order specified in the syntax diagram. For example, the following uses of the example tag, TAGNAME, are equivalent specifications:

```
:tagname vattr=value kattr=value1.
:tagname kattr=value1 vattr=value.
```

Sometimes it is necessary to continue the attribute of a tag to another source line. However, not all attributes can be continued. The attributes in the following table are the only ones that can be continued.

Table A-1 (Page 1 of 2). Tag Attributes That Can Be Continued

Attribute	Tag
ACTION	KEYI
ACTION	MENUI
ACTION	PDFLDC
COLHEAD	LISTCOL
COLS	LISTVIEW
CONDS	TT
EMPHASIS	LISTDEF
ENTER	LISTACT
ENTER	PANEL
EXPR	COND
EXTENTER	LISTACT
EXTPROMPT	LISTACT
LINKWHEN	LINK
NOGET	VARRCD
NOPUT	VARRCD

Tag Language

Table A-1 (Page 2 of 2). Tag Attributes That Can Be Continued

Attribute	Tag
PERFORM	LINK
PROMPT	LISTACT
PROTECT	LISTDEF
RANGE	CHECK
REL	CHECK
ROOTS	ISCH
TOPICS	ISCHSUBT
UNLESS _n	LINK
VALUES	CHECK
VALUES	TTROW
VARs	LISTDEF
VARs	VARRCD

To continue an attribute, repeat the attribute on the next source line, as in the following example:

```
:TAGNAME
      VATTR='value1 value2 value3'
      VATTR='value4 value5 value6'
      VATTR='value7 value8 value9'.
tag-content
```

A maximum of fifty attribute names can be specified for any tag, including each repeated attribute name.

Tag Content Formatted as

Paragraphs: The period (.), question mark (?), and exclamation point (!) are sentence-ending characters. Depending on the national language requirements, one or more blanks are placed after each of the sentence-ending characters that end a UIM source line when the panel group or menu object is created. The number of blanks can be from one to six, and is specified in the message text of the CPI6AB9 message in the message file QCPFMSG.

The following example shows how the CPI6AB9 message works.

```
:p.This is the first sentence.
This is the second! This is the third.
```

In this example, :p. is the tag name. The :p. tag does not require attributes. There are three spaces between the second sentence and the third sentence because of national language requirements. If the CPI6AB9 message is set to

xx, this paragraph appears this way to the UIM after it is compiled:

This is the first sentence. This is the second! This is the third.

There are two spaces between the first and second sentences. There are three spaces between the second and third sentences.

Because the CPI6AB9 message affects the amount of space that follows the end of a source line, if the CPI6AB9 message is changed to xxx, there will be three spaces between each sentence in the previous example.

Note: The CPI6AB9 message should already be translated to the proper number of x's for your country.

Panel Areas: The four types of panel areas are menu, information, data, and list areas. A mixed panel is constructed by using two or more of these areas within the same panel.

The restrictions associated with mixed panels are listed in Table A-2.

Table A-2. Restrictions Associated With Mixed Panels

	Menu	Info	Data	Non-Action List	Action List
Menu	No	Yes	Yes	Yes	No
Info	Yes	Yes	Yes	Yes	Yes
Data	Yes	Yes	Yes	Yes	Yes
Non-Action List	Yes	Yes	Yes	Yes	Yes
Action List	No	Yes	Yes	Yes	No

All of these area types can be scrolled. Scrolling, as well as presentation of the appropriate scroll location information, is handled by the UIM.

Panels: A panel is made up of one or more panel areas, each of which has a specific layout and function. Specific panels are usually categorized according to the nature of their application areas, such as information panels, menu panels, and list panels.

Panel Group Objects: A panel group is a logical grouping of panels that can correspond to a software product, a command, or a related collection of commands or other services. It can contain panels of any type. Panel groups provide a context for names of panels, variables, list definitions, and help modules.

Help on Panels: Help for a panel is constructed from help modules referred to in the panel definition. Extended help for a panel is a concatenation of the help for the panel, the menu bar, items in all areas in the order of their definitions, and function keys in the order of their definitions.

Panel Group Organization

The following list shows the required order of tags in the UIM source for panel groups and menus.

Panel Group Outline

Panel Group (PNLGRP)

- Prolog section
 - Copyright statement (COPYR)
 - Import statements (IMPORT)
 - Class definitions (CLASS)
 - Variable definitions (VAR)
 - Variable Record Definitions (VARRCD)
 - List definitions (LISTDEF)
 - Condition definitions (COND)
 - Truth table definitions (TT)
 - Menu bar definitions (MBAR)
 - Key list definitions (KEYL)
- Body section
 - Display panel definitions (PANEL)¹
 - Area definitions (MENU, INFO, DATA, LIST)
 - Command and option line definitions (CMDLINE, OPTLINE)
 - Print head panel definitions (PRTHEAD)¹
 - Area definitions (INFO, DATA)
 - Print trailer message (PRTRAIL)
 - Print panel definitions (PRTPNL)¹
 - Area definitions (INFO, DATA, LIST)
 - Help module definitions (HELP)¹

A UIM menu, created with the Create Menu (CRTMNU) command, is a special form of panel group. These menus are limited to the following panel group tags:

UIM Menu Outline

Panel Group (PNLGRP)

- Prolog section
 - Copyright statement (COPYR)
 - Import statements (IMPORT)
 - Variable definitions (VAR)
 - Condition definitions (COND)
 - Truth table definitions (TT)
 - Menu Bar (MBAR)
 - Key list definitions (KEYL)
- Body section
 - Panel definitions (PANEL)²
 - Area definitions (MENU, INFO, DATA)
 - Command and option line definitions (CMDLINE, OPTLINE)
 - Help module definitions (HELP)²

Name Syntax

There are several elements, identified with tags, within a panel group that can be named so that they can be referred to from other elements within that panel group, such as classes, dialog variables, lists, and conditions. The application program can also refer to named elements by passing the name to the UIM as a parameter on an application programming interface (API) call. These elements have a NAME attribute on the tags that define them. These names may be up to 10 characters long and can contain only the characters A through Z and 0 through 9. The first character of a name must be an A through Z character.

Names of help modules defined by the HELP tag can be up to 32 characters long and are defined in the same name space as other elements. As a result, a help module and another element cannot have the same name in a panel group. They can contain the characters A through Z, 0 through 9, slash (/), and underscore (_). If the name contains a slash or an underscore, it must be enclosed between apostrophes. The first character of a help name must be an A through Z character, a slash, or an underscore.

¹ PANEL, PRTHEAD, PRTPNL, and HELP tags can be used in any order.

² The PANEL and HELP tags can be used in any order.

Because all names are stored in the panel group object in uppercase format, lowercase alphabetic characters (a through z) are converted to uppercase alphabetic characters (A through Z). When the name of an element is passed to the UIM through an application program interface, the name must be passed in uppercase characters.

Because these names stay within the panel group and reside in the same name space, a dialog variable and a UIM list cannot have the same name.



There is an occasional need to refer to object names in the panel group source. These names must obey the rules for OS/400 object names. They must be enclosed between apostrophes when they contain characters other than A through Z and 0 through 9.

Symbols

A symbol is a name that can be replaced with something else while the panel group is compiling. All symbols use an ampersand (&), followed by the symbol name, followed by a period. Symbols must appear in the text following the period of a tag.

Symbols can be entered in either uppercase or lowercase.

The following symbols are defined by the UIM:


- &.** Creates an ampersand (&) without triggering symbol processing. This symbol is used when an ampersand is needed in the text of a tag. If this symbol is not used, the UIM replaces the symbol name with its actual value.

- &colon.** Creates a colon (:) without triggering tag processing. This symbol is used when a colon is needed in the text of a tag.

- &cont.** Forces the concatenation of the next source line with the current source line. Concatenation occurs only when the symbol is the last character in a source line. No visible symbol is created for the &cont. symbol.

When the &cont. symbol is used to continue the two parts of a double-byte character set (DBCS) word, both the ending shift-in character of the first line and the starting shift-out character of the second line are discarded.

The &cont. symbol is useful with a figure, a line, or an example. The symbol can be used when a CIT, HPn, or LINK tag would cause the resulting source line to be longer than the length of the source record.

Here is an example of how to use the &cont. symbol.


```
:LINES.  
Text to be continued &cont.  
:LINK perform='dsp help hyper'  
linkwhen='chkusrcls("PGMR")'&cont.  
reference phrase&cont.  
:ELINK.&cont.  
more text on line.  
:ELINES.
```




&msg(msgid,msgf,lib).

The compiler extracts the first-level message text for the message MSGID from the message file MSGF in library LIB and substitutes the text in place of this symbol. The message text is retrieved without any substitution variables.

The message file defaults to the message file specified on the SUBMSGF attribute of the PNLGRP tag. If SUBMSGF is not specified, the message file must be specified in the symbol.




&period. Creates a period (.) in the text. This symbol is used when a period is needed in column one of the text without triggering control word processing.



Tag Language

`&slr.` Creates a right slash (/) in the text. This symbol is used if a right slash is needed in column one of the tag source. If this symbol is not used, right slashes in column one of the source file can cause problems if the source file is part of the input stream for a batch job.



Comments

In addition to markup done with tags, comments can also be inserted into the source of the panel group. Typically, comments are used to describe the content of the file, or to give information as to the structure, format, date, author, and so on.

Comments begin with a period followed by an asterisk (*). They must be used in columns one and two of the source record. They are ignored by the compiler, but are listed in the source listing. They are not preserved in the panel group object. An example using comments follows:

```
.*****  
.* panel group      xxx.xxx  
.* author          X. X. XXXXXX  
.* change history  9/18/92 (xxx) Created  
.******  
:pnlgrp ...  
:  
:epnlgrp.
```

Imbeds


Source from other files can be brought into a panel group at the time the panel group is compiled. This allows you to create a panel group or menu from multiple source file members. Imbeds are done with the `.IM` control word. An example using imbeds follows:

```
.im member1
```

The member (member1) in the file named in the include file (INCFILE) parameter on the Create Panel Group (CRTPNLGRP) or Create Menu (CRTMNU) command is opened and processed as if it appeared in the original source file. Imbeds can be nested up to 10 deep; attempting to nest deeper than 10 results in an error and the panel group or menu object is not created.

DBCS Graphic Literals

DBCS graphic literals are supported by the UIM to support processing of strings of literal characters of DBCS graphic data. The syntax of the literals follows:



Notes:

- ¹ *Shift-out* is X'0E'
- ² *D* is one DBCS character
- ³ *Shift-in* is X'0F'

The value must be enclosed in apostrophes because it contains special characters.


All strings of literal characters coded on UIM tags that are compared against a DBCS graphic field must be in the form of DBCS graphic literals. The shift-out and shift-in characters are removed from the graphic strings before the comparison is performed.

Caution should be used when literals are compared to input-capable graphic fields. You must realize that on a nongraphic DBCS device, there are two fewer bytes available for input. As a result, you should always use literals that are two bytes less than the maximum length of the entry field of the DBCS graphic variable.

When DBCS graphic characters are used after the period of a tag, (such as on the translation list item (TI) tag) a graphic literal should not be used. What should be used is everything between and not including the quotation marks in the diagram above.

Hexadecimal Literals

Hexadecimal data can be entered in attributes wherever a character string literal is allowed. The syntax of hexadecimal literals follows:



Note:


- ¹ *xx* is a pair of hexadecimal digits (0 through 9, a through f, or A through F)

The following example shows how to code a hexadecimal value for a translation item.

```
:TI value='"01"x'.*YES  
:TI value='"02"x'.*NO
```

The value must be enclosed in apostrophes because it contains special characters.

APPFMT (Application Formatted Area)



The application formatted area (APPFMT) tag is an optional tag which defines an area in the upper right corner of a menu area to be formatted by the application. Only one APPFMT tag can be specified in each menu area. It must immediately follow the menu area (MENU) and top instruction (TOPINST) tags.

The application formatted area is part of the menu area, appearing at the right edge of the menu area and ending one character position before the right edge of the panel. The width is determined by the WIDTH attribute of this tag. The application formatted area extends from the blank line following the top instruction lines of the menu area to the number of lines defined in the DEPTH attribute of this tag. A two-byte separator is maintained between the menu item descriptions and the application formatted area.

If the depth of the application formatted area is less than the depth of the menu area, the area below the application formatted area and to the right of the menu area is blank. The depth of the application formatted area may not be greater than the depth of the menu area.

If the menu area is scrollable, the scroll indicators appear to the left of the separator between the menu area and the application formatted area. You cannot scroll the application formatted area, even if you can scroll the menu area.

The application formatted data is described in “Application Formatted Data” on page A-9.

Extended help for the panel is displayed if the Help key is pressed while the cursor is in the application formatted area.

Required Attributes

VAR=*dialog-variable-name*

The name of the dialog variable containing the application formatted area. Define the dialog

variable using a class definition (CLASS) tag with a BASETYPE of CHAR *x*, where *x* equals the product of the area width times the area depth.

You can use the exit program for application formatted data, specified on the USREXIT attribute of this tag, to update this dialog variable each time the panel is displayed. The UIM uses the value of the dialog variable as the application formatted data, described in “Application Formatted Data” on page A-9.

WIDTH=*area-width*

The width, in characters, for the application formatted area associated with the menu area. The width specified must be an integer in the range of 1 to 40, or the panel width minus 17, whichever is less.

DEPTH=*area-depth*

The depth, in lines, of the application formatted area. This depth must be no greater than the number of lines available for the body of the menu. The body of the menu is the area between and excluding the top instruction line and the bottom instruction line or bottom separator.

Optional Attribute

USREXIT=*'CALL program-reference'*

The exit program for application formatted data, called to update the value of the dialog variable containing the application formatted data each time the panel is displayed.

For a description of the CALL dialog command, see Appendix B, “UIM Dialog Commands” on page B-1.

For a description of the interface between the UIM and the exit program for application formatted data, see the *System Programmer's Interface Reference*, SC41-8223.

Application Formatted Data

The dialog variable containing the application formatted data is specified on the VAR attribute of this tag. The contents of this variable is viewed by the UIM as a *d* by *w* array of characters, where *d* is the depth and *w* is the width of the application formatted area. Each row of the array is displayed as one line of the application formatted area.

Any character within the data can be a selection character for a highlighting class. Only output and text classes are allowed in an application formatted area; no input fields are allowed. The class selection applies to the following characters up to another class selection character or the end of the row, whichever occurs first. The UIM sets the highlighting class to normal text at the beginning of each row of the area.

The selection characters for highlighting are in the range of X'01' through X'06'. The following selection characters for highlighting are recognized by the UIM:

- X'01' Normal variable output
- X'02' De-emphasized variable output
- X'03' Emphasized variable output
- X'04' Normal text
- X'05' De-emphasized text
- X'06' Emphasized text

The UIM replaces each class selection character with the appropriate display attributes for the class. Other character values in the ranges X'01' through X'06', and X'10' through X'3F', as well as X'FF', are converted to X'1F', appearing as a reverse image box on the screen. Characters X'00' (null), X'0E' (shift-out for double-byte), X'0F' (shift-in for double-byte), and X'40'

through X'FE' (normal, displayable characters), are passed unchanged to the screen.

The UIM inserts a normal text attribute before each line of the application formatted area and a field-ending attribute after each line of the application formatted area. This effectively isolates the application formatted area from the rest of the panel with respect to highlighting attributes.

No character set and code page conversion is done on the application formatted data. If conversion is necessary, it must be done by the application.

When the UIM calls the exit program to format the application area of a menu, it passes a value which identifies the BIDI attribute on the panel group (PNLGRP) tag and the code page number of the display device.

The NBRSHAPE and SYMSWAP attributes of the CLASS tag used for the application formatted area are determined from the class of the dialog variable containing the application formatted data.

Example: Application Formatted Area

OfficeVision/400
System: RCHAS767

Select one of the following:
Time: 9:09

1. Calendars
2. Mail
3. Send message
4. Send note
5. Documents and folders
6. Word processing
7. Directories/distribution lists
8. Decision support
9. Administration
90. Sign off

February 1992


S	M	T	W	T	F	S
						1
2	3	4	5	6	7	8
9	10	11	12	13	14	15
16	17	18	19	20	21	22
23	24	25	26	27	28	29

Press ATTN to suspend a selected option.
Selection
Bottom

—

F3=Exit F12=Cancel F19=Display messages
(C) COPYRIGHT IBM CORP. 1985, 1991.

BOTINST (Bottom Instruction)



The bottom instruction (BOTINST) tag specifies the bottom instruction lines for an area of the panel. This tag appears immediately before the ending tag for the area. You can use multiple bottom instruction tags to present multiple instruction lines if the tag contains instruction text after the period. If multiple tags are coded, no blank lines appear between the text on different tags. Only one bottom instruction tag is allowed per area if the *INST* attribute is used on this tag.

If you do not specify a BOTINST tag for an area, no instruction line is allocated for the area.

For menus and information areas, a blank line is always left between the body of the area and the instruction lines. If you can scroll the area, a blank line is reserved for the scroll information between the body of the area and the bottom instruction. For information about how instruction lines are formatted with respect to the body of data and list areas, see the *BODYSEP* attribute in “DATA (Data Presentation Area)” on page A-29 and “LIST (List Area)” on page A-80.

Optional Attribute

INST=dialog-variable-name

The name of a dialog variable that contains the bottom instruction text to be displayed. The dialog variable must be defined with a width less than or equal to the width specified on the panel tag minus 2. If the *INST* attribute

is used, no *instruction-text* can be specified for this tag.

Dialog variables must be defined with a *BASETYPE* of CHAR, IGC, or BIN on the class definition (CLASS) tag.

The error state of the dialog variable is not used for determining the highlighting of the text.


Special formatting for IGC. (The abbreviation IGC is used in commands and keywords to represent double-byte character set functions.) When a dialog variable with a *BASETYPE* of IGC is specified on the CLASS tag, the UIM does special formatting. If the dialog variable value begins with a shift-out character (X'0E'), the UIM shifts the value one byte to the left to preserve vertical alignment with other lines.

Optional Text

instruction-text

The text appearing as bottom instructions for the area. The text is an implied paragraph. When the display is formatted, any text that does not fit onto one display line is formatted on multiple lines as necessary and indented two display positions. The text can be a maximum of 255 characters, and can contain only the reverse text (RT) tag. The *instruction text* is required unless the *INST* attribute is specified on this tag.

CHECK (Validity Checking)



The validity checking (CHECK) tag is used within a class definition to specify validity checks associated with variables of that class.

Validity checking occurs on input of the variable value and after translation list processing. If a translation list is specified for this class and can be applied to an input value, no validity checking is performed on the translated input value. If the translation list is not applicable and indicates no error, the validity checks defined by this tag are applied to the input value. For more information on using the CHECK tag with translation lists, see “TI (Translation List Item)” on page A-151 and “TL (Translation List)” on page A-152.

At least one RANGE, REL, or VALUE attribute of this tag must be coded. If more than one validity check is coded on the tag, the value must pass only one of the check attributes to be accepted for this check. If more than one CHECK tag is used, a value must pass all the check tags to be accepted. Operations from multiple attributes are ORed together.

Required Attribute

MSGID=*message-identifier*

The message identifier of the error message displayed to the user if a validity check fails. The message should have no substitution variables defined, because the UIM does not supply replacement text when the message is sent.

Optional Attributes

MSGF=*'qualified-message-file-name'*.

The message file that contains the message specified on the MSGID attribute of this tag. If

the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, this attribute must be specified.

RANGE=*'value1 value2'*

A range check is valid for both character and numeric types. The check passes if the value entered by the user is greater than or equal to *value1* and less than or equal to *value2*. This attribute can be specified more than once.

Each value must be numeric or character to match the BASETYPE of the variable as specified on the class definition (CLASS) tag, and cannot be a dialog variable. All character values must be enclosed in quotation marks.

REL=*'relop value'*

A relational check is valid for both numeric and character types. This attribute can be specified more than once.

Each value must be numeric or character to match the BASETYPE of the variable as specified on the CLASS tag, and cannot be a dialog variable. All character values must be enclosed in quotation marks.

Relational operators are listed below. All operators are valid for both character and numeric types. The check is affected by the CASE and BLANKS attributes of the CLASS tag.

- = **Equal.** The check passes if the value entered by the user is equal to this literal value.
- ≠ **Not equal.** The check passes if the value entered by the user is not equal to this literal value.
- > **Greater than.** The check passes if the value entered by the user is greater than this literal value.

CHECK Tag

- < **Less than.** The check passes if the value entered by the user is less than this literal value.
- >= **Greater than or equal.** The check passes if the value entered by the user is greater than or equal to this literal value.
- <= **Less than or equal.** The check passes if the value entered by the user is less than or equal to this literal value.

The relational operator may be specified as =, !=, >, <, >=, or <=, if the code page of the source maps the not character (¬) to X'5F'. Otherwise, it is suggested that the special values *EQ, *NE, *GT, *LT, *GE, or *LE be used, respectively, for the relational operator.

VALUES='value1 value2 ... value-n'

A values check is valid for both character and numeric types. The check passes if the value entered by the user is equal to one of the values in the list. Checking on character values is affected by the CASE and BLANKS

attributes of the CLASS tag. The VALUES attribute can be specified more than once, and up to 50 values can be specified for this tag.

Each value must be numeric or character to match the BASETYPE of the variable as specified on the CLASS tag, and cannot be a dialog variable. The values in the list are separated by blanks. All character values must be enclosed in quotation marks.


Example: Validity Checking

UIM Source

```
:CHECK RANGE='1 10' REL='= 99' MSGID=USR0234.  
:CHECK REL='< 5' REL='> 10' MSGID=USR1234.  
:CHECK VALUES=' "*YES" "*NO"  
MSGID=MMM0001 MSGF=USRMSGF.
```

The range check allows values 1 through 10, or 99, for any variables of the class to which it applies. The relational check allows values less than 5 or greater than 10. The values check accepts two special values.

CIT (Title Citation)



The title citation (CIT) tag identifies the title of a publication and requires a matching end tag. This tag is only allowed in information areas and help areas. Title citations are underscored for online and printed text, and can occur anywhere in the text.

The CIT and ECIT tags must be specified on word boundaries. If the two characters immediately following the ECIT tag are a punctuation mark and a blank, the UIM extends the emphasis attribute to include the punctuation mark. This allows the punctuation mark and the title to be displayed using the same emphasis.

Optional Text

title-text

Although the title to be cited is not required, the tag has no meaning when no title is specified.

Example: Title Citations


UIM Source

`:P.For more information about
the UIM, see the :CIT.Guide to Programming
Applications and Help Displays,:ECIT. SC41-0011.`

Results

For more information about the UIM,
see the Guide to Programming Application
and Help Displays, SC41-0011.

CLASS (Class Definition)



The class definition (CLASS) tag defines variable types in variable pools and on panels. Attributes of the CLASS tag define the data type for the class of the dialog variable and the validity checking necessary for all variables of that class. The attributes of this tag also determine the methods for mapping an internal dialog variable of a particular class to or from a displayed form.

Other tags can be nested within the CLASS tag. These tags are listed in the following table. The table defines the order in which the tags must appear and specifies on which page more information can be found about each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower

order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-3. Tags Allowed Between the CLASS and ECLASS Tag

Tag Name	Order	Page
TL (Translation list)	1	A-152
CHECK (Validity checking)	2	A-11

Required Attributes

NAME=class-name

The name assigned to the class. For more information on the rules for naming, see "Name Syntax" on page A-4.

BASETYPE

The base data type for variables in the class. The BASETYPE for a class determines the internal storage representation and basic input and output editing characteristics for variables of a class.

CHAR *n*

Variables of this class are character strings of a fixed length. The number of bytes, *n*, is from 1 to 32 767.

IGC *n* [OPEN | EITHER]

Variables of this class are fixed-length character strings which may contain double-byte data surrounded by shift-out and shift-in characters. The number of bytes, *n*, is from 4 to 32 767.

OPEN indicates that variables defined with this class can contain both single-byte and double-byte data.

EITHER indicates that variables defined with this class can contain single-byte or double-byte data, but not both. If EITHER is specified, the number of bytes, *n* must be an even number.

The CASE attribute on this tag is not allowed for IGC classes. For IGC classes, processing for CHRID=PNLGRP on this tag depends on whether or not the field value contains double-byte character set (DBCS) data.

A dialog variable with a BASETYPE of IGC can be presented on a device that is not DBCS-capable, as long as the panel group object in which the variable is declared does not have TEXTMODE=DBCS specified on the panel group (PNLGRP) tag. This allows the same panel group object and application to support both single-byte character set (SBCS) and DBCS field values as long as the predefined text in the panel group is only SBCS.

GRAPHIC *w*

Variables of this class can contain only DBCS characters which are not surrounded by shift-out and shift-in characters. The number of DBCS characters, *w*, is from 1 to 16 383 (1 DBCS character equals 2 bytes).

The contents of a GRAPHIC dialog variable must only be double-byte data.

When GRAPHIC is specified on this tag, the shift-out and shift-in characters are not placed in the variable pool by either the application or the UIM.

NAME *n* [SIMPLE | GENERIC]

Use a BASETYPE of NAME for System/38 names and names which follow the same rules as System/38 object names, such as names of record formats.

Lowercase characters (a through z) are converted to upper case characters (A through Z) according to the same rules that commands follow. For more information on converting lowercase characters to uppercase characters, see the *Programming: Control Language Reference*, SC41-0030.

The number of bytes, *n*, is from 1 to 255.

SIMPLE indicates that the name entered must be allowed as a simple OS/400 name.

GENERIC indicates that the name must be a syntactically correct OS/400 generic name.

A translation list must be specified in the class definition if blanks or any other name value that is not valid is allowed as an input value for a dialog variable of this BASETYPE.

OBJNAME *n* [SIMPLE | GENERIC | POSTO]

Use a BASETYPE of OBJNAME for OS/400 object names. SIMPLE indicates that the name entered must be a single OS/400 object name.

GENERIC indicates that the name must be a syntactically correct OS/400 generic object name.

POSTO indicates that the name is used for a position-to field, and does not have to be a syntactically correct OS/400 name. Lowercase characters (a through z) are converted to uppercase characters (A through Z) unless the name is enclosed in apostrophes. The number of bytes, *n*, is from 1 to 255.

When POSTO is specified, if the first and last character of the name is a quotation mark, the last double quote is removed from the name. If the first character is not

CLASS Tag

a quotation mark, all lowercase characters (a through z) are converted to uppercase characters (A through Z). When POSTO is specified, the name does not have to be a valid object name.

A translation list must be specified in the class definition if blanks or any other name value that is not valid is allowed as an input value for a dialog variable of this BASETYPE. For example, a translation list is necessary when *LIBL should be an allowed value for a variable containing the library name. For an example of a translation list, see "TL (Translation List)" on page A-152.

The CASE attribute on this tag cannot be specified for an object name class. The UIM automatically adds or removes delimiter characters (quotation marks) and converts lowercase input values to uppercase as necessary.

BIN *b*

Variables of this BASETYPE are signed binary numbers. The number of bits, *b*, is either 15 or 31.

'BIN 15' is the same as BINARY(2), and 'BIN 31' is the same as BINARY(4), as described in chapter two of the *System Programmer's Interface Reference*, SC41-8223.

PACKED *t f*

Variables of this class are packed decimal numbers. The number of digits, *t*, is from 1 to 31. The number of decimal positions, *f*, is from 0 to *t*.

ZONED *t f*

Variables of this class are zoned decimal numbers. The number of digits, *t*, is from

1 to 31. The number of decimal positions, *f*, is from 0 to *t*.

PTR

Variables of this class are pointers. Any variables of this BASETYPE cannot be displayed or printed.

DATE

The variable is a 7-byte string representing the date in the form *cyymmdd*. The date abbreviations are represented as follows:

c Century. Zero indicates the twentieth century and one indicates the twenty-first century.

yy Year

mm Month

dd Day

TIME

A value of this class is a 6-byte string representing the time in the form *hhmmss*. The time abbreviations are represented as follows:

hh Hours

mm Minutes

ss Seconds

ACTION

The variable is a 2-byte binary number with the same internal form as BIN 15, used as the option column for an action list or the selection column for a selection list.

When a variable with this BASETYPE is specified for the VAR attribute on a list column (LISTCOL) tag for an action list, the UIM determines the width of the input field based on the maximum OPTION attribute value specified for any list action (LISTACT) tag in the area.

Table A-4 (Page 1 of 2). Attribute Summary for Each BASETYPE

BASETYPE	Default WIDTH Attri- bute	Minimum WIDTH Attribute	Maximum WIDTH Attribute	Default SHIFT Attri- bute	Default CASE Attri- bute	Default BLANKS Attribute
BIN 15	6	1	255	UPPER	UPPER	IGNORE
BIN 31	11	1	255	UPPER	UPPER	IGNORE
CHAR <i>n</i>	<i>n</i>	<i>n</i>	32767	NONE	MIXED	RESPECT

Table A-4 (Page 2 of 2). Attribute Summary for Each BASETYPE

BASETYPE	Default WIDTH Attribute	Minimum WIDTH Attribute	Maximum WIDTH Attribute	Default SHIFT Attribute	Default CASE Attribute	Default BLANKS Attribute
IGC <i>n</i>	<i>n</i>	<i>n</i>	32767	NONE	MIXED	RESPECT
GRAPHIC <i>w</i>	<i>w</i>	<i>w</i>	16383	NONE	MIXED	RESPECT
NAME <i>n</i>	<i>n</i>	<i>n</i>	255	UPPER	UPPER	IGNORE
OBJNAME <i>n</i>	<i>n</i>	<i>n</i>	255	NONE	See text	IGNORE
PACKED <i>t f</i> where <i>t=f</i>	<i>t</i> +3	<i>f</i> +3	255	UPPER	n/a	n/a
PACKED <i>t f</i> where <i>t=f</i> and <i>f</i> >0	<i>t</i> +2	<i>f</i> +2	255	UPPER	n/a	n/a
PACKED <i>t f</i> where <i>t=f</i> and <i>f</i> =0	<i>t</i> +1	1	255	UPPER	n/a	n/a
ZONED <i>t f</i> where <i>t=f</i>	<i>t</i> +3	<i>f</i> +3	255	UPPER	n/a	n/a
ZONED <i>t f</i> where <i>t=f</i> and <i>f</i> >0	<i>t</i> +2	<i>f</i> +2	255	UPPER	n/a	n/a
ZONED <i>t f</i> where <i>t=f</i> and <i>f</i> =0	<i>t</i> +1	1	255	UPPER	n/a	n/a
DATE	8	8	255	UPPER	n/a	n/a
TIME	8	8	255	UPPER	n/a	n/a
ACTION	6 (See text)	1	255	UPPER	UPPER	IGNORE

Optional Attributes

WIDTH=display-width.

The width of a display field in which values of this class are presented. For a BASETYPE of GRAPHIC, this value is the number of DBCS characters. The defaults and allowable values for the display width depend on the BASETYPE attribute, as specified in Table A-4 on page A-16.

For variables that use this class, a value larger than the default for the BASETYPE may be needed to support the external display form of values appearing in a translation list. For more information on translation lists, see "TL (Translation List)" on page A-152.

CHRID=NONE | PNLGRP

- | If the CHRID parameter on the CRTPNLGRP
- | command is *JOBCCSID, the compiler issues

a warning message and the CHRID attribute on the CLASS tag is ignored. All variables are converted from the job CCSID to the device CHRID when *JOBCCSID is specified.

If NONE is specified, the data is assumed to be in the correct character set and code page for the display or printer device.

If PNLGRP is specified, the data associated with this class is interpreted with the character set and code page specified on the CHRID parameter on the CRTPNLGRP control language command. For devices that do not allow the downloading of this code page to handle the display of such data, character conversion occurs on both output and input for variables of this class. The conversion table for such cases is determined by the following rules:

	Character set	Code page
Panel group	xxx	yyy
Device	aaa	bbb

Output conversion table = QUSRSYS/Qyyyyaabbb
Input conversion table = QUSRSYS/Qbbbxxxyyy

If the conversion table is not found, no conversion takes place. This conversion is done before any validity checking or inbound processing of a translation list.

For a BASETYPE of GRAPHIC, CHRID=PNLGRP is not allowed on this tag. The UIM does not perform character set and code page conversion on GRAPHIC fields, because there is no single-byte part of a GRAPHIC field.

Character set and code page conversion is not performed when dialog variables are substituted into the command string for the CMD dialog command.

| When CHRID=PNLGRP is specified for a class
| with BASETYPE of IGC, the UIM converts only
| the single-byte portion of the field. No conver-
| sion is done on the DBCS portion of the field.

SHIFT=NONE | UPPER

If NONE is coded, no special keyboard shift is used for fields of this class.

If UPPER is coded, the keyboard is shifted to uppercase for data entry for display input fields associated with variables of this class. The default keyboard shift is determined by the BASETYPE. For a summary of the BASETYPE and corresponding default, see Table A-4 on page A-16.

CASE=MIXED | UPPER

MIXED indicates that characters from any field of this class are preserved when assigned to the variable pool.

UPPER indicates that lowercase characters (a through z) are uppercased before assignment to the pool. This translation takes place after any processing for the CHRID attribute on this tag and before any validity checking or inbound processing of a translation list. For a BASETYPE of GRAPHIC, CASE=UPPER is not allowed. The default case is determined by the BASETYPE. For a summary of the BASETYPE and corresponding default, see Table A-4 on page A-16.

BLANKS=RESPECT | IGNORE

RESPECT indicates that blanks in the input field are preserved when the value is assigned to the variable pool.

IGNORE indicates that the value is left justified when it is assigned to the variable pool. The default is determined by the BASETYPE. The processing to remove leading blanks takes place after any processing for the CHRID and CASE attributes on this tag, and before validity checking or inbound processing of a translation list. For a summary of the BASETYPE and corresponding default, see Table A-4 on page A-16.

When BLANKS=IGNORE is specified for a BASETYPE of IGC, only leading SBCS blanks are removed from the field value. The processing to remove leading blanks stops at the first shift-out character in the field.

SUBST=DISPLAY | QUOTED

If DISPLAY is specified, the substitution values used on the CMD dialog command for this class of variables is the same as their displayed values.

If QUOTED is specified, the substitution values used on the CMD dialog command for this class of variables are enclosed in apostrophes, and apostrophes within the values are doubled. Values translated with the translation list (TL) tag are not quoted.

BIDI=PNLGRP | LTR | RTL

Sets the left-to-right or right-to-left orientation for variables of this class. This attribute is ignored when BIDI=NONE is specified on the PNLGRP tag.

PNLGRP indicates that the parameter from the BIDI attribute on the PNLGRP tag should be used to set the orientation for variables of this class.

LTR indicates that a left-to-right orientation should be used for variables of this class.

RTL indicates that a right-to-left orientation should be used for variables of this class.

The orientation defaults to PNLGRP for classes with a BASETYPE of CHAR and IGC. Orientation defaults to LTR for classes with a BASETYPE of NAME, OBJNAME, BIN, PACKED, ZONED, DATE, TIME, and ACTION.

The cursor direction is reversed for any input field which has an orientation opposite the panel's orientation. The cursor direction can be changed later when the `CONXTREV` attribute of this tag is processed.

CONXTREV=NO | YES

Specifies that a context-sensitive reversal is performed for bidirectional variables of this class. This attribute is ignored when `BIDI=NONE` is specified on the `PNLGRP` tag.

For `CONXTREV=NO`, when the orientation of a variable does not match the orientation of the panel group, the value for each display line of the variable is reversed before it is displayed. On entry, the contents of each display line of a field that has an orientation opposite to the panel is also reversed before it is moved from the display field to the variable pool. `NO` is the default.

For `CONXTREV=YES`, the contents of dialog variables are checked to determine the ultimate display orientation of the variable. The dialog variable value is checked before it is displayed. If the dialog variable is used in an input field, the value is checked again before the input value is copied to the variable pool. A description of the checking follows:

- When `BIDI=LTR` is specified on the `PNLGRP` tag,
 - The dialog variable is inverted if and only if the dialog variable value contains at least one Arabic or one Hebrew alphabetic character, *or* if it contains no Latin characters and `BIDI=RTL` is specified on the `CLASS` tag.
- When `BIDI=RTL` is specified on the `PNLGRP` tag,
 - The dialog variable is inverted if and only if the dialog variable value does not contain any Arabic or Hebrew alphabetic characters, and if either it contains Latin characters or `BIDI=LTR` is specified on the `CLASS` tag.

The Arabic and Hebrew code pages used to determine if the variable must have its display orientation flipped are described as follows:

- For code page 420

- The following hex values represent Arabic characters: 42 through 49, 51, 52, 55 through 59, 62 through 69, 70 through 79, 80, 8A through 8F, 90, 9A through 9F, A0, AA through AF, B0 through B5, B8 through BF, CB, CD, CF, D0, and DA through DE.
 - The following hex values represent Latin characters: 6F, 81 through 89, 91 through 99, A2 through A9, C1 through C9, D1 through D9, DF, E2 through EB, ED, EE, EF, F0 through F9, and FB through FE.
 - The remaining characters are not considered to be Arabic and Latin.
- For code page 424
 - The following hex values represent Hebrew characters: 41 through 49, 51 through 59, 62 through 69, and 71.
 - The following hex values represent Latin characters: 81 through 89, 91 through 99, A2 through A9, C1 through C9, D1 through D9, E2 through E9, and F0 through F9.
 - The remaining characters are not considered to be Hebrew and Latin.

For a `CONXTREV=YES` input field, the initial cursor direction is determined the same way as for a `CONXTREV=NO` input field. Then it is further processed and redetermined, based on the results of the following content inversion:


- `BIDI=LTR` is specified on the `PNLGRP` tag:
 - When `BIDI=LTR` is specified on the `CLASS` tag:
 - The cursor direction is inverted if and only if the content of the dialog variable is inverted.
 - When `BIDI=RTL` is specified on the `CLASS` tag:
 - The cursor direction is inverted if and only if the content of the dialog variable is *not* inverted *and* if it contains at least one Latin alphabetic character. (This prevents the inversion of the cursor direction in an empty field.)

CLASS Tag

- BIDI=RTL is specified on the PNLGRP tag:
 - When BIDI=LTR is specified on the CLASS tag:
 - The cursor direction is inverted if and only if the content of the dialog variable is *not* inverted.
 - When BIDI=RTL is specified on the CLASS tag:

- The cursor direction is inverted if and only if the content is inverted *and* if the variable contains at least one Latin alphabetic character. (This prevents the inversion of the cursor direction in an empty field.)

For a detailed summary of how CONTXTREV=YES works for various fields and panels, see the following decision tree.



Result 1:
Right-to-left
cursor motion.
Invert value
of dialog
variable.

Result 2:
Right-to-left
cursor motion.

Result 3:
Left-to-right
cursor motion.

Result 4:
Left-to right
cursor motion.
Invert value
of dialog
variable.

RV2W060-0

NBRSHAPE=PNLGRP | ARABIC | HINDI

Controls the display shape of application-generated numbers for bidirectional variables of this class. This attribute is ignored when `BIDI=NONE` is specified on the `PNLGRP` tag, or when any code page other than 420 (Arabic) is used by the display device.

When `PNLGRP` is specified, the parameter from the `NBRSHAPE` attribute on the `PNLGRP` tag should be used for variables of this class. `PNLGRP` is the default.

When `ARABIC` is specified, the normal digits `X'F0'` through `X'F9'` are used for numbers.

When `HINDI` is specified, the translation of digits is performed with a set of two translation tables defined for each national language. The first table is used for output operations, and the second table is used for input operations.

The `NBRSHAPE` attribute allows the application program to not know the actual code points used to display the numeric digits.

SYMSWAP=NO | YES

Controls the exchange of symmetric characters for bidirectional variables of this class. This attribute is ignored when `BIDI=NONE` is specified on the `PNLGRP` tag. An example of two pairs of symmetric characters are:

'(' with ')'
'<' with '>'

When `YES` is specified, the symmetric character exchange is performed for both input and output operations on any field displayed with a right-to-left orientation. The situations where this can occur are:

- `CONXTREV=NO` is specified on this tag for a variable that has a right-to-left orientation.

- `CONXTREV=YES` is specified on this tag for a variable that has a right-to-left orientation, and the contents of the field causes the resulting field orientation to stay right-to-left.
- `CONXTREV=YES` is specified on this tag for a variable that has a left-to-right orientation, and the contents of the field causes the resulting field orientation to change to right-to-left.

When `SYMSWAP=NO` is specified, symmetric character exchanges are not performed. `NO` is the default.

The complete list of symmetric characters for Hebrew (code page 424) is:

- (with) Right and left parentheses, 4D with 5D
- { with } Right and left braces, C0 with D0
- [with] Right and left square brackets, BA with BB
- < with > Less than and greater than signs, 4C with 6E
- « with » Double less than and double greater than signs, 8A with 8B

The complete list of symmetric characters for Arabic (code page 420) is:

- (with) Right and left parentheses, 4D with 5D
- < with > Less than and greater than signs, 4C with 6E

All symmetric characters generated by the UIM are processed as if `SYMSWAP=YES` is specified. At this time, the symmetric characters include:

- > Greater than symbol. Used to mark menu options and used in the command line prompt
- () Right and left parentheses symbols. Used around an empty list message.

Example: Class Definitions

UIM Source

```

.* Class of options whose only legal values
.* are Y, N, and blank.
.* These values are translated to an
.* internal form.
: class name=option
    basetype='bin 15'
    case=upper width=1.
: tl msgid=MMM1234.
: ti value=1.Y
: ti value=2.N
: ti value=3.
: etl.
: eclass.
.*
.* class of object names or the special
.* value *all
: class name=object
    basetype='objname 10 generic'.
: tl.
: ti value=' '*ALL '*ALL
: etl.
: eclass.
.*
.* Class of options from 1-5 or 7-9,
.* in a field of width 1.
: class name=listoption
    basetype='bin 15' width=1.
: check range='1 5' range='7 9'.
: eclass.

```


Display Forms of Numeric Values

Numbers are usually displayed without leading zeros. If the absolute value of the number is less than one, a leading zero before the decimal point is supplied or suppressed, based on the QDECFMT system value. Numbers are signed only if the number is negative. A decimal point is displayed only if there are fractional digits. The decimal point character used is the one defined by the system value QDECFMT. Numbers are displayed preserving all fraction digits.


If a value is too large to fit in the display field on output, the field is filled with plus signs. If a field consists entirely of plus signs on entry, no validity

checks are performed on the field and the value of the variable in the variable pool is left unchanged.

Numeric literals must be of the form:



or



A comma may be used in place of a period for decimal point on input. If conversion to the internal form loses significant digits, the field is considered in error and the UIM displays an error message to the user without altering the contents of the variable pool. All nonzero digits after the decimal point are considered significant, and attempts to truncate result in an error. Leading zeros before the decimal point and trailing zeros after the decimal point are not considered significant. If a sign is not supplied, the value is assumed to be positive.

Binary values can also be translated to character strings on output and from character strings on entry. In this case, the value specified for the WIDTH attribute on this tag must allow for the width of the translated character string specified on the translation list item (TI) tag. For more information on translation lists, see "TL (Translation List)" on page A-152 and "TI (Translation List Item)" on page A-151.

Any variable with a BASETYPE of ACTION is handled with editing rules for a numeric value, except that a zero value is displayed as blanks, and a zero input value is not valid. Plus signs are not allowed on entry. Translation lists and validity check processing are not allowed for variables whose BASETYPE is ACTION.

Some examples of the display for numeric values are shown in the following table.

BASETYPE	WIDTH	Internal Value	Dis- played Value	Notes
BIN 15	1	1	1	
BIN 15	1	-1	+	(Value too large to display)
BIN 15	5	1	1	
BIN 15	5	-1	-1	
BIN 15	5	-3456	-3456	
BIN 15	5	-32768	+++++	(Value too large to display)
PACKED 2 2		.45	.45	Calculated field width is 5
PACKED 2 2		-.45	-.45	Calculated field width is 5
PACKED 5 2		000.45	0.45	Calculated field width is 7
PACKED 5 2		-000.45	-0.45	Calculated field width is 7
PACKED 5 2	8	000.45	0.45	
PACKED 5 2	8	-000.45	-0.45	
PACKED 5 2	8	123.45	123.45	
PACKED 5 2	8	-123.45	-123.45	
PACKED 5 2	4	-123.45	++++	(Value too large to display)
PACKED 5 2	4	003.45	3.45	
PACKED 5 0		00001	1	Calculated field width is 6
PACKED 5 0		00000	0	Calculated field width is 6
PACKED 5 0		-00000	0	Calculated field width is 6
PACKED 5 0		-00001	-1	Calculated field width is 6

Display Forms of Character, Date, and Time Values

Character values are displayed as they appear from the variable pool, padding with nulls on the right as necessary. If the value entered into the input field is not translated using a translation list, an error is reported to the user and the dialog variable is not updated if the value is longer than the BASETYPE of the variable after trailing blanks are removed. Only trailing SBCS blanks are removed; DBCS blanks are considered significant.

Dates are always displayed in the form specified by the date format and date separator of the current job. When a date is entered, it must be in

the format specified by the date format of the current job, but the separator characters specified by the date separator of the current job are optional. Because the date formats do not allow the entry of the century digit, it is assumed to be 1 unless the year number is greater than or equal to 40. If the year number is less than 40, the century digit is assumed to be 0.

Times are always displayed in a 24-hour time format, with the time separator as specified by the time separator of the current job. The separator characters specified by the time separator of the current job are optional. If a time is entered without a time separator, either four or six digits must be supplied.

CMDLINE (Command Line)

```

▶▶:CMDLINE—SIZE=—SHORT—LONG—NAME=command-line-name—.instruction-text▶▶

```

The command line (CMDLINE) tag specifies that the panel has a command line and provides additional command line information. This tag is allowed only for display panels. A command line may appear on any panel and may be independent of all areas on the panel, or it may be associated with an action list or menu area on the panel.

Only system commands can be entered on the command line, unless the panel contains a menu area or an action list area. If the panel contains a menu area, the user enters either a menu option or a command on the command line. For an action list, the user enters a string that is either run as a command or acts as parameter information for action list processing.

This tag must be the final tag in the panel, and is placed just before the end of the display panel. The CMDLINE tag and the option line (OPTLINE) tag are mutually exclusive.

Required Attribute

SIZE=SHORT | LONG

A SHORT command line takes up only one line of the display and fills up that line.

A LONG command line takes up two lines on the display.

SIZE=SHORT must be specified if a panel width other than 80 bytes is specified on the display panel (PANEL) tag. SIZE=LONG is

valid only for a 27-row by 132-byte panel or a 24-row by 80-byte panel.

When BIDI=RTL is specified on the panel group (PNLGRP) tag, all SIZE=LONG command lines are automatically formatted by the compiler to a one-line command line with a blank line separator between the command line and the function key area.

Optional Attribute

NAME=*command-line-name*

The name associated with the command line. This name can be used later with the Add Pop-Up Window (QUIADDPW) API to position a window near the command line.

For more information on the rules for naming, see "Name Syntax" on page A-4.


Optional Text

instruction-text

The text appearing as instructions for the command line. The text is an implied paragraph.

When the display is formatted, any text that does not fit on one display line is formatted on multiple lines as necessary and indented two display positions. The text can be a maximum of 255 characters and can only contain the reverse text (RT) tag. If no text is provided, no instruction line is displayed above the command line.

COND (Condition Definition)



The condition definition (COND) tag defines a condition that must be true if certain processing is to take place. Other tags may refer to this condition, which is evaluated before a panel is displayed. If the condition is true, the action or formatting specified by the referring tag is performed.

Required Attributes


NAME=condition-name

The name of the condition specified in the expression. The name must be unique within the panel group.

For more information on the rules for naming, see “Name Syntax” on page A-4.

EXPR='conditional-expression'.

A conditional expression is a true or false expression in the following form:



where A is an operand which can be one of the following:


- A conditional expression
- A comparison between a dialog variable and a literal value
- A comparison between two dialog variables
- A built-in function

When operand A is a conditional expression, the *AND and *OR logic becomes more complex.

The logical OR character (|) can be used in place of *OR, the ampersand character (&) can be used in place of *AND, and the logical NOT character (¬) can be used in place of *NOT. Since the logical OR and logical NOT characters are not in the invariant character set, their use is not recommended. For code

page 00037, the common USA code page, the hexadecimal value of the logical OR character is X'4F', and the hexadecimal value of the logical NOT character is X'5F'. The UIM compiler uses these hexadecimal values regardless of the code page of the source.

When operand A is a comparison between a dialog variable and a literal value, or between two dialog variables, it must be in the following form:



The relational operator may be specified as =, ≠, >, <, >=, or <=, if the code page of the source maps the not character (¬) to X'5F'. Otherwise, it is suggested that the special values *EQ, *NE, *GT, *LT, *GE, or *LE be used, respectively for the relational operator.

Comparisons may take place only between items of matching BASETYPE and precision as defined on the class definition (CLASS) tag. Comparisons between two literals are not allowed.


Character string literals must be enclosed in quotation marks ("). The UIM does not automatically uppercase character strings.

Hexadecimal strings are allowed as character strings. Hexadecimal strings cannot be used for comparison with dialog variables defined with a BASETYPE of GRAPHIC on the CLASS tag. For more information about specifying hexadecimal strings, see “Hexadecimal Literals” on page A-6.


For a comparison between a dialog variable whose BASETYPE is GRAPHIC (as defined on the CLASS tag) and a literal, a double-byte character set (DBCS) graphic literal must be

used. For more information about specifying a DBCS graphic literal, see "DBCS Graphic Literals" on page A-6.

Numeric literals must be of the form:



or




where *d* is a digit from 0 through 9.

This attribute is repeatable so that an expression can span several lines.

When operand A is a built-in function, it can be used as follows:

CHKOBJ

Evaluates to true if the object is found on the system and the current job possesses at least the level of authorization to the object specified by the authorities. Arguments must be character strings enclosed in quotation marks ("). The object name follows OS/400 object naming conventions. The object type is any of the allowable object types for the DSPOBJD command and the authorities must be a single value or a list of authorizations to be checked for. The values of these authorizations are separated by blanks. The following syntax diagram illustrates the authorities and how to use them:



Note:


- ¹ Each value can be used only once, with a maximum of 7.

If no authorities are specified, no authorization check is performed and the function becomes an existence check.

CHKUSRCLS

The user class argument specified for the function is compared to the user class parameter from the user profile of the current job. The function evaluates to true if the user profile has the same or greater value than the function argument. The function argument must be enclosed in quotation marks (").

The following syntax diagram illustrates the valid argument values for the user class:



```
CHKOBJ("OBJECT", "*FILE", "*USE")
```

```
CHKOBJ("PANELGRP", "*PNLGRP")
      *AND CHKUSRCLS("*PGMR")
```

```
CHKOBJ("DOCUMENT", "*DOC", "*READ *UPD")
      *OR CHKUSRCLS("*SYSOPR")
```

```
*NOT(CHKOBJ("PROGRAM", "*PGM"))
```

Optional Attribute

EVAL=ALWAYS | ONCE

Indicates whether or not the expression specified on the EXPR attribute of this tag must be evaluated every time the condition is referred to, or if it needs to be evaluated only once.

If EVAL=ALWAYS is used, the expression is evaluated to determine a new truth value every time the condition is referred to. All EVAL=ALWAYS conditions in a panel group or menu are evaluated each time a panel or menu is displayed. ALWAYS is the default.

If EVAL=ONCE is specified, the expression is evaluated only once for every open application that uses the panel group. The UIM only evaluates the expression for a condition of this type the first time the condition is referred to. Every reference after the first one uses the same truth value determined by the first reference. ONCE may be specified to improve performance for conditions that do not change

while the application is open, particularly if the expression requires the evaluation of a function (like CHKOBJ) that may be costly.

Example: Conditioning an Option

The following example shows how the COND tag might be used to condition menu items. The first condition uses a complex expression which is split onto two source lines. The second condition checks for the application user's authority to use a menu on the system, and the third condition checks for the user class of the application user.

UIM Source

```

:
:cond name=a
    expr='(var1 = 100 *AND var2 > 0)'
    expr='*OR *NOT(var3 = 0)'.
:cond name=b
    expr='chkobj("MENU2","*MENU","*READ,*UPD")'.
:cond name=c
    expr='chkusrc1s("*PGMR")'.

:
:menui
    cond=a
    help='option1/help'
    action='CMD CALL PGM01'
    option=1.Run report
:menui
    cond=b
    help='option2/help'
    action='MENU MENU2'
    option=2.Administration
:menui
    cond=c
    help='option30/help'
    action='MENU UTIL'
    option=30.Utilities

:

```

COPYR (Copyright)

►►:COPYR.—*notice-text*◄◄

The copyright (COPYR) tag provides a way to present a copyright notice. Only one COPYR tag is allowed. The copyright notice is displayed in the message area of the first panel displayed after the panel group is opened. This tag must be coded immediately after the panel group (PNLGRP) tag.


Required Text

notice-text


The text of the copyright notice that is displayed. The text must be between 1 to 76 characters.

DATA (Data Presentation Area)

Syntax for Display Panels



Syntax for Print Panels



The data presentation area (DATA) tag describes a data presentation area in a panel. This tag is allowed for display panels and print panels. This area can be used for data entry items or output data items, or any combination of the two.

Other tags can be nested within the DATA tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both

(specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-5. Tags Allowed Between the DATA and EDATA Tags

Tag Name	Order	Use	Page
TOPINST (Top instruction line)	1	D	A-154
DATA COL (Data column)	2	B	A-37
DATAGRP (Data item group)	3	B	A-38
DATAI (Data item)	3	B	A-40
DATASLT (Data selection field)	3	D	A-49
BOTINST (Bottom instruction line)	4	D	A-10

Required Attribute

DEPTH=*area-depth* | '*'

The depth of the area in lines, including separators if any are specified. This attribute is required for display panels but is not allowed for print panels. If '*' is specified, the space remaining on the display after all else is allocated is given to this area. Only one area in the panel may have '*' coded.

Optional Attributes

HELP=*help-module-name*

Identifies online information explaining all items in the area. This attribute is allowed only for display panels. The help module name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for naming, see "Name Syntax" on page A-4.

A single help module name must be associated with every item in the area. If the HELP attribute is specified on the DATA tag, the help applies to all groups and items in the area, and the HELP attribute is not allowed on any data group (DATAGRP), data item (DATAI), data selection field (DATASLT), and data selection field choice (DATASLTC) tags in the area.

If no HELP attribute is specified on the DATA tag, a help module name must be associated with each item in the area by specifying the HELP attribute on the DATAGRP tags or the DATAI and DATASLT tags.

To provide the user with easy access to the online information for a data area with the LAYOUT=HORIZ attribute specified on this tag, specify the HELP attribute on the DATA tag instead of the HELP attribute on the individual DATAI tags.

BOTSEP=SPACE | NONE | RULE

Defines the bottom separator for the data presentation area. If SPACE is specified, a line of spaces is used. SPACE is the default.

NONE indicates that no separator line exists.

RULE indicates that a line of underscored spaces is used.

SCROLL=NO | YES

Specifies whether or not the area is scrollable. This attribute is allowed only for display panels. NO indicates that the area is not scrollable. NO is the default.

YES indicates that the data presentation area is scrollable. SCROLL=YES is not allowed when LAYOUT=HORIZ is specified. A line of spaces is used by the UIM to provide a line for the scroll information. If BOTSEP=SPACE, only one line of spaces is used unless this area also contains bottom instructions.

LAYOUT=1 | 2 | HORIZ

Indicates either the number of layout columns for a vertically formatted area or that a horizontal format should be used.

For LAYOUT=1, there is only one column of data items. For panels with WIDTH=80 bytes on the panel definition (PANEL) tag, the single column of data items is in positions 2 through 79. For panels with WIDTH=132, the single column of data items is in positions 2 through 131.

For LAYOUT=2, two layout columns of equal width are used for data items. The data items specified within the area appear in order, from top to bottom within a layout column and from left to right between layout columns. For panels with WIDTH=80, the two layout columns are in positions 2 through 38 and 43 through 79. For panels with WIDTH=132, the two layout

columns of data items are in positions 2 through 64 and 69 through 131.

For LAYOUT=HORIZ, the data fields are listed horizontally across the width of the panel, with five spaces between items. This layout is useful if only two or three short values are necessary. It should be limited to a single display line, because the UIM does not vertically align items appearing on different lines within the area.

MAXHEAD=0 | 1 | 2 | 3 | 4

The maximum number of lines that can be used for column headings. The column headings are specified using the data column (DATACOL) tag. From zero to four lines can be specified. Zero is the default, meaning that no column headings are allowed. Only MAXHEAD=0 is valid for a data presentation area with a horizontal layout, because column headings are not allowed in horizontal presentation. For more information on column headings, see "DATACOL (Data Column)" on page A-37.

When column headings are used, you may want to provide expansion space for national language translation by specifying a MAXHEAD value larger than the number of heading lines required. If this is not done, expansion space must be provided within the column widths determined by the DATACOL tag.

BODYSEP=SPACE | INDENT | BOTH | NONE

The type of visual separation distinguishing the body of the area from other elements on the display, particularly any top and bottom instruction lines within the area.

SPACE leaves a blank line after the last top instruction line and before the first bottom instruction line. Items in the body of the area begin in the leftmost position of the layout column. They are not indented with respect to instruction lines. If the area contains no top or bottom instruction lines, no blank lines are reserved before or after the area body.

INDENT is used to indent items in the body of the area by two bytes from the leftmost position in the layout column where the instruction lines begin. If the area contains top or bottom instruction lines, no blank line is reserved between the instructions and the area body

except if the area is scrollable. If the area is scrollable, a blank line is reserved to provide a line for the scroll information.

BOTH leaves a blank line after the last top instruction line and before the first bottom instruction line, and also indents items in the body of the area by two bytes from the leftmost position in the layout column where the instruction lines begin. If the area contains no top or bottom instruction lines, no blank lines are reserved before or after the area body.

NONE does not leave a blank line between the instruction line and the body, and does not indent the body with respect to the layout column except if the area is scrollable. If the area is scrollable, a blank line is reserved to provide a line for the scroll information.

COMPACT

If COMPACT is specified, no blank lines are left between column headings and all items and outer groups in the area. If COMPACT is not specified, a blank line appears after the area column headings and between all items and outer groups.

TYPE=NORMAL | PROLOG

Indicates whether or not this data area is a prolog area. The prolog area is printed only once after the title line on the first page. This attribute is allowed only for the print head panel (PRTHEAD) tag. NORMAL is the default value.

Optional Text

area-title

The title of the area. If no text is specified, no title line is allocated to the area. The text must appear on the same or next line as the tag, can contain only the reverse text (RT) tag, and is a maximum of 55 characters long.

Print Formatting Considerations

Printed data areas are formatted similarly to data areas that are displayed, with the following exceptions:

- When printing, there is a minimum of two lines of data entries on a page besides the data group headings and the data column headings.

DATA Tag

- If two lines of data entries do not fit on a page, a page eject occurs and the data entries are printed on the next page.

```
| For formatting of data areas with LAYOUT=2, the
| UIM balances the data entries across the page
| and ignores keep processing.
```

This format may not look good in some cases, but LAYOUT=2 data areas should only be used on small data areas or when the user is not concerned about keep processing.

If there are data column headings, they are repeated on each page if the data area is continued onto another page.

Example 1: Data Entry Panel

The following example shows a sample data entry panel. The panel has 5 prompts; 4 prompts have defaults supplied to the calling program by previously setting the dialog variables for the function.

UIM Source

```
:panel name=entry1
      help=hentry1
      topsep=space
      key1=keys
      .Sample Entry Panel
:data depth='*'
      maxhead=2.
:topinst.Type choices, press Enter:
:datacol width=20.Item
:datacol width=10.Choice
:datacol width='*'. 'Possible Choices'
:datai usage=inout
      help=hfname
      var=fname.File name
:datac.Name of document to be printed
:datai usage=inout
      help=hstyle
      var=prtstyle.Type style for printing
:datac.1=Prestige Elite (12 pitch)
:datac.2=Courier (10 pitch)
:datac.3=Essay Standard (proportional)
:datac.4=Essay Bold (proportional)
:datai usage=inout
      help=hmargn
      var=margin.Left margin
:datac.Number of spaces from the left
edge of the paper (1-20)
:datai usage=inout
      help=hcopy
      var=copies.Copies
```

```
:datac.Number of copies (1-99)
:datai usage=inout
      help=hduplx
      var=duplex.Duplex
:datac.1=Yes (Print both sides of paper)
:datac.2=No (Print one side only)
:edata.
:epanel.
```

Results

Sample Entry Panel	
Type choices, press Enter:	
Item	Choice
File name	_____ Name of document to be printed
Type style for printing	<u>1</u> 1=Prestige Elite (12 pitch) 2=Courier (10 pitch) 3=Essay Standard (proportional) 4=Essay Bold (proportional)
Left margin	<u>6</u> Number of spaces from the left edge of the paper (1-20)
Copies	<u>1</u> Number of copies (1-99)
Duplex	<u>1</u> 1=Yes (Print both sides of paper) 2=No (Print one side only)
F3=Exit F12=Cancel	

Example 2: Two-Column Format in a Data Entry Panel

The following example shows a data area using two-column format containing output items, and a form of data entry field that has no prompt.

UIM Source

```
:panel name=panelx
      help=helpx
      topsep=space
      key1=keys
      .Another Sample Panel
:data depth=14 layout=2.
:datacol width='24'.
:datacol width='*'.
:datagrpf compact.Compact data group
:datai usage=out
      help=hvar1
      var=var1.First element
:datai usage=out
      help=hvar2
      var=var2.Second element
:edatagrpf.
:datai usage=out
      help=hvar3
      var=var3.Third element
:datagrpf grpsep=qindent
      compact.
:datai usage=out
```

```

        help=hvar4
        var=var4.Fourth element
:datai usage=out
        help=hvar5
        var=var5.Fifth element
:datai usage=out
        help=hvar6
        var=var6.Sixth element
:edatagr.
:datagr compact.Another compact group
:datai usage=out
        help=hvar7
        var=var7.Seventh element
:datai usage=out
        help=hvar8
        var=var8.Eighth element
:datai usage=out
        help=hvar9
        var=var9.Ninth element
:edatagr.
:datagr help=hvar1012
        grpsep=none compact.
:datai usage=out
        var=var10.Tenth element
:datai usage=out
        var=var11 cond=cond11.
:datai usage=out
        var=var12 cond=cond12.
:edatagr.
:datagr grpsep=none
        compact.
:datai usage=out
        help=hvar13
        var=var13.Thirteenth element
:datai usage=out
        help=hvar14
        var=var14.Fourteenth element
:datai usage=out
        help=hvar15
        var=var15.Fifteenth element
:edatagr.
:edata.
:data depth=3
        bodysep=none.
:datacol width=0.
:datacol width='*'.
:datagr.Sixteenth element
:datai usage=inout
        help=hvarx
        var=varx.
:edatagr.
:edata.
:epanel.

```

Results

Example 3: Two Presentation Areas for Data Items

The following two examples show three data areas, which are initialized from the dialog variables in the variable pool. The first two areas are aligned horizontally, and the third area is formatted vertically.

UIM Source

```

:panel name=xmp3
        key1=x1
        help=hxmp3
        .Data Item Extenders
:data depth=2
        layout=horiz
        botsep=space.
:datai usage=out
        var=date
        help=hdatetime.Date and time
:dataix usage=out
        var=time
        newline=no
        itemsep=1.
:edata.
:data depth=2
        layout=horiz
        botsep=space.
:datai usage=out
        var=jobname
        help=hdatetime.Job name
:dataix usage=out
        var=user
        newline=no
        itemsep=1.
:dataix usage=out
        var=jobnbr
        newline=no itemsep=1.
:edata.
:data depth='*'
        layout=1

```

DATA Tag

```

        botsep=space
        compact.
:datacol width=0.
:datacol width='*'.
:datagrpf grpsep=indent
        help=dependptfs
        compact.Dependent PTFs
:datai usage=out
        var=ptf1.
:dataix usage=out
        var=ptf2.
:dataix usage=out
        var=ptf3.
:dataix usage=out
        var=ptf4
        newline=yes.
:dataix usage=out
        var=ptf5.
:edatagrpf.
:edata.
:epanel.

```

Results

```

Data Item Extenders

Date and time: 12/31/99 12:59:59

Job name: DSP01 QSECOFR 012345

Dependent PTFs:
XXXXXXXXXXXXXXXX XXXXXXXXXXXXXXXXXXXX XXXXXXXXXXXXXXXXXXXX
XXXXXXXXXXXXXXXX XXXXXXXXXXXXXXXXXXXX XXXXXXXXXXXXXXXXXXXX

```

Example 4: Data Presentation Area with a Menu Area

UIM Source

```
:panel name=xxx
      key1=x1
      help=hxxx
      .Work with Files
:data depth=2
      layout=horiz.
:data1 var=fname
      help='filename'.File
:data1 var=lname
      help='libname'.Library
:edata.
:menu depth='*'.

```

```
:topinst.Select one of the following:
:menui action='return 1'
      help='hoption1'
      option=1.Display file attributes
:menui action='return 2'
      help='hoption2'
      option=2.Display file contents
:menui action='return 3'
      help='hoption3'
      option=3.Change ownership
:menui action='return4'
      help='hoption4'
      option=4.Change authorizations
:menui action='return 5'
      help='hoption5'
      option=5.Destroy
:menui action='return 6'
      help='hoption6'
      option=6.Backup to tape
:emenu.
:optline.Selection
:epanel.
```

Results

```

Work with Files
System: xxxxxxxx
File: MEM047123 Library: QGPL
Select one of the following:
1. Display file attributes
2. Display file contents
3. Change ownership
4. Change authorizations
5. Destroy
6. Backup to tape

Selection
-
F3=Exit F12=Cancel

```

Example 5: Data Entry Panel with a Nested Data Group

UIM Source

```
:panel name=nestg
      help=helpn
      topsep=space
      keyl=keys
      .Nested Data Group
:data depth='*'
      scroll=no.
:topinst.Type choices, press Enter.
:datacol width=40.
:datacol width=10.
:datacol width='*'.
:datagrps compact
```

```

        grpsep=none.
:datai usage=inout
        help=hjobq
        var=jobq.Place on job queue
:datac.Y=Yes, N=No
.* The following "datagr" tag is
.*needed to cause indentation for
.* the "For choice Y=Yes" data group.
:datagr compact
        grpsep=indent.
:datagr compact
        grpsep=indent.For choice Y=Yes:
:datai usage=inout
        help=hcmpmsg
        var=cmpmsg.Send completion message
:datac.Y=Yes, N=No
:edatagr.
:edatagr.

```

```

:edatagr.
:epanel.

```

Results


Nested Data Group

Type choices, press Enter.

Place job on job queue	-	Y=Yes, N=No
For choice Y=Yes:		
Send completion message	-	Y=Yes, N=No

F3=Exit F12=Cancel

DATAAC (Data Item Choices)



The data item choices (DATAAC) tag provides the text for the possible choices column of a data presentation area. This tag is allowed for display panels and print panels. It is not valid if only two data column (DATACOL) tags are specified for the area, or if LAYOUT=HORIZ is specified on the data presentation area (DATA) tag for the area.

The DATAAC tag must appear after the corresponding data item (DATAI) tag. More than one DATAAC tag may be specified after the DATAI tag to provide several lines of text. If no DATAAC tags are entered, no text exists in the possible choices column for the data item.

Optional Attribute

CHOICE=*dialog-variable-name*

The name of a dialog variable containing the choices text to be displayed. The dialog variable must be defined with a width less than or equal to the width specified on the third DATACOL tag for the data area, the possible choices column. If the CHOICE attribute is used, no *text-for-choices* can be specified after the period of this tag.

Dialog variables must be defined with a BASETYPE of CHAR, IGC, or BIN on the class definition (CLASS) tag.

The error state of the dialog variable is not used for determining the highlighting of the text.

Special formatting for IGC. (The abbreviation IGC is used in commands and keywords to represent double-byte character set functions.) When a dialog variable with a BASETYPE of IGC is specified on the CLASS tag, the UIM does special formatting. If the variable value begins with a shift-out character (X'0E'), the UIM shifts the value one byte to the left to preserve vertical alignment with data choices on other lines.

Optional Text

text-for-choices

The text is an implied paragraph. Lines are formatted as necessary onto multiple lines within the column and indented two spaces from the beginning of the column. The text is a maximum of 255 characters and can only contain the reverse text (RT) tag. The *text-for-choices* is required unless the CHOICE attribute is specified on this tag.

DATACOL (Data Column)

►►:DATACOL—WIDTH=column-width_{'*'}.column-heading►►

The data column (DATACOL) tag specifies the width of the item, choice, and possible choices columns, and can also provide column headings. This tag is allowed for display panels and print panels. It is not valid if LAYOUT=HORIZ is specified for the data presentation area. It must appear after the data presentation area (DATA) tag for the area and before the first data item (DATAI), data selection field (DATASLT), or data group (DATAGRP) tag.

Two or three DATACOL tags must be specified when the LAYOUT attribute of on the DATA tag specifies 1 or 2. If only two DATACOL tags are used, the area has no possible choices column and no data item choices (DATAC) tags are allowed in the area. If three DATACOL tags are specified, all three columns are allocated, including the possible choices column.

Required Attribute

WIDTH=*column-width* | '*'

The width, in bytes, for the column. The width specified must be a positive integer, and the sum of the widths of the columns and separators in the data presentation area must not exceed the width of the layout column determined by the DATA tag. WIDTH=0 is allowed only for the first DATACOL tag; it formats the area without an item column for data item or data selection field prompt text.

If '*' is coded, the remainder of the area width is used for the column. Only one DATACOL in the area may have '*' specified. A three-column separator is maintained between columns, except when WIDTH=0 is specified for the first DATACOL tag. In this

case, the item column is not allocated and there is no separator in front of the choice column.

The value for any data item may span columns, but must begin on the correct column boundary. The possible choices text for that item, assuming three DATACOL tags are specified, begins in the location assigned to the possible choices. This possible choices text may be on the same or next line as the data item field.

Optional Text

column-heading


The column heading placed above the data items in the data area. If no column heading is specified, none is displayed.

The text may appear on more than one line and can contain only the reverse text (RT) tag. Each word of the column heading is placed on a new line. If multiple words are necessary in a line of the column heading, they must be enclosed in apostrophes (''). Each word or quoted string must fit within the column width defined by the WIDTH attribute on this tag. The maximum number of words or quoted strings allowed is specified by the MAXHEAD attribute on the DATA tag. Column headings are not allowed if MAXHEAD=0 is used for the data area.


The column headings are left-justified. If no column heading text is specified on any DATACOL tag for the area, no lines are reserved on the display for heading information.

DATAGRP (Data Group)

Syntax for Display Panels



Syntax for Print Panels



The data group (DATAGRP) tag is used to group data items and data selection fields in a data presentation area. This tag is allowed for display panels and print panels. One data group may be nested within another data group; up to four levels of data group nesting are allowed, including the outermost group. This tag is not valid if LAYOUT=HORIZ is specified for the data presentation area (DATA) tag.

The UIM does keep processing for data item groups. When data groups are nested within other data groups, keep processing is done for all the groups. If an outer group must be split, keep processing is attempted for groups nested within it. If the number of lines required for an entire group exceeds the number of lines remaining in the layout column, the entire group is forced to the next column. In the case of single-column layout, the entire group is forced to the next scrollable page. Any data group that becomes too large for one layout column begins at the top of one column and continues onto as many columns or pages as required for all items.

Optional Attributes

HELP=help-module-name

Identifies online information explaining all items in the group. This attribute is allowed only for display panels. The help module

name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for naming, see "Name Syntax" on page A-4.

A single help module name must be associated with every item in the area. If the HELP attribute is specified on the DATA tag, the help applies to all groups and items in the area, and the HELP attribute is not allowed on any data group (DATAGRP), data item (DATAI), data selection field (DATASLT), and data selection field choice (DATASLTC) tags in the area.

If the HELP attribute is specified on the DATAGRP tag, the help applies to all items in the group, and the HELP attribute is not allowed on any DATAI, DATASLT, DATASLTC, or nested DATAGRP tags within the data group.

If no HELP attribute is specified on the DATA tag or on any outer or nested DATAGRP tags, the HELP attribute is required on all DATAI and DATASLT tags within the group.

NAME=data-group-name

The name associated with the group. This name can be used with the Add Pop-Up Window (QUIADDPW) API to position a

window near this data group. This attribute is allowed only for display panels.

For more information on the rules for naming, see “Name Syntax” on page A-4.

GRPSEP=INDENT | NONE | QINDENT

Specifies what type of visual separation should be used to distinguish the items in the group.

INDENT is used to indent the left-most column, prompt, or value for every data item, group heading of a nested data group, or data selection field within the group by two positions. Only the left-most column is indented. The group heading is not indented.

QINDENT is used to indent each data item or nested data group or data selection field, except the first one in the group. The first item or imbedded group within this data item group are not indented. All other items, fields, and imbedded groups are indented. Both the prompt column and the value column of a data item or data selection field are indented by two positions. The group heading of an nested data group and all items within it are indented by two positions.

The determination of which data items, selection fields and groups are indented is made when the panel group is created and is unaffected by conditioning. This option presents data items in the same format the control language (CL) prompter uses for qualified names. Because qualified name indenting of a value would be backward for a BIDI=RTL panel group, the value column is not indented when QINDENT is specified for a BIDI=RTL panel group. The prompt text of each item after the first one is still indented.

NONE does not indent any data items, data selection fields, or nested data item groups in

the group. This option is not recommended when group heading text is specified. It can be used to group related data items, data item groups, and data selection fields together without a group heading. It does this by defining a compact group of items and nested groups in a non-compact area.

COND=condition-name

The group is displayed or printed only if the condition specified is true. All tags within the group appear only if this data group appears. The condition must be defined in the panel group prolog with the condition definition (COND) tag.

COMPACT

If COMPACT is specified, then no blank lines are left between individual items or nested data group headings. If this data group is nested inside another data group for which COMPACT is specified, COMPACT is implied for this data group whether it is specified or not.

Optional Text

group-heading


The heading placed above the data items of the group. The text occupies only one line of the panel, but may span several columns. The text must appear on the same line or next line as the tag and can only contain the reverse text (RT) tag.

If the text is omitted, no lines are allocated on the display for a group heading, but the items between the DATAGRP and EDATAGRP tags are processed as a group with respect to keep processing on the display and other UIM operations.


A colon is added to the end of the text if one is not already specified and if there is room for it.

DATAI (Data Item)

Syntax for Display Panels



Syntax for Print Panels



The data item (DATAI) tag defines an item placed in a data presentation area. This tag is allowed for display panels and print panels.

The data item extender (DATAIX) tag can be used to specify additional dialog variables, which are displayed as part of the data item. The data selection choices (DATAC) tag can be used to specify possible choices text, which is displayed as part of the data item. The DATAIX and DATAC tag are considered part of the DATAI tag with respect to formatting, conditioning, scrolling, and help.

Note that the prompt, field and extenders, and possible choices text must fit within the data area.

The UIM does not allow an individual data item to be split while scrolling.

Required Attributes

VAR=dialog-variable-name

The name of the dialog variable constructing the data item. The current value of the dialog variable is displayed or printed.

If the item appears in an area with LAYOUT=1 specified on the data presentation area (DATA) tag, its value can exceed the width of the choice column. In this case, the value is presented as a single field that wraps onto as many display lines as necessary. If LAYOUT=2 is specified on the DATA tag, the width of the value must fit between the starting position

determined from the second data column (DATACOL) tag and the ending position for the layout column.

For a data presentation area specified with LAYOUT=HORIZ, if there are already data items on the display line and if the length of the prompt plus the value does not fit on the current line and allow a five column separator between data items, the prompt and values are placed on the next display line. For horizontal layout, the prompt plus the value must fit on a single line of the panel.

USAGE=OUT | INOUT

Indicates the display use of the data item. This attribute is required for display panels and is optional for print panels.

USAGE=OUT defines an output data item. OUT indicates that the variable displayed is for output only and cannot be changed by the user.

USAGE=INOUT defines a data entry item. INOUT indicates that the variable is for data entry and can be changed by the user.

Optional Attributes

HELP=*help-module-name*

Identifies online information which explains the data item. This attribute is allowed only for display panels. The name of the help module can be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see “Name Syntax” on page A-4.

A single help module name must be associated with every item in the area. If the HELP attribute is specified on the DATA tag, the help applies to all groups and items in the area, and the HELP attribute is not allowed on any data group (DATAGRP) and DATAI tags in the area.

If the HELP attribute is specified on the DATAGRP tag, the help applies to all data items in the group and the HELP attribute is not allowed on DATAI tags within the group.

If no HELP attribute is specified on the DATA tag or on DATAGRP tags containing a data item, the HELP attribute is required on the DATAI tag.

To provide the user with easy access to the online information for a LAYOUT=HORIZ data area, use the HELP attribute on the DATA tag instead of the HELP attribute on the individual DATAI tags in the horizontal area.

The HELP attribute applies to all DATAIX tags associated with this data item.

NAME=*data-item-name*

The name associated with the item. This name can be used with the Add Pop-Up Window (QUIADDPW) API to position a window near this data item. This attribute is allowed only for display panels.

For more information on the rules for naming, see “Name Syntax” on page A-4.

PMTLOC=BEFORE | ABOVE

Governs the placement of the variable value in relationship to the prompt text for the data item.

BEFORE indicates that the prompt text is placed before (to the left of) the variable value. The variable value begins on the line the prompt text ended on.

ABOVE indicates that the prompt text is placed above the data item variable. The variable is indented two spaces from the beginning of the prompt text. ABOVE is not allowed when LAYOUT=HORIZ is specified on the DATA tag.

If the prompt text is placed above the data item variable as a result of ABOVE, the ALIGN attribute on this tag is not used for formatting.

All data item extenders placed on a new line as a result of NEWLINE=CALC or NEWLINE=YES on the DATAIX tag begin in the same column as the data item variable.

CHCLOC=AFTER | ABOVE

Governs the placement of the data choices text in relationship to the variable value for the data item.

AFTER indicates that the data choices text is placed after the variable value. This is either on the same line or on the line below the end of the variable value.

ABOVE indicates that the data choices text is placed above the data item variable. ABOVE is allowed only if PMTLOC=ABOVE is specified.

DATAI Tag

This attribute is not allowed when LAYOUT=HORIZ is specified on the DATA tag.

This attribute governs placement of data choices text only for DATAC tags immediately following the DATAI tag. DATAC tags following a DATAIX tag are not affected by this attribute.

ALIGN=LEFT | RIGHT | START | END

Governs how the display value of the variable is positioned within the choice column defined by the second DATACOL tag.

ALIGN=LEFT positions the leftmost character of the display value with the left edge of the choice column.

ALIGN=RIGHT positions the rightmost character of the display value with the right edge of the choice column. ALIGN=RIGHT is not allowed when LAYOUT=HORIZ is specified on the DATA tag. If the width of the display value, set by the WIDTH attribute on the class definition (CLASS) tag, exceeds the width of the choice column, ALIGN=RIGHT will work the same way as ALIGN=LEFT.

START is a synonym for LEFT, and END is a synonym for RIGHT.

JUSTIFY=LEFT | RIGHT | START | END

Governs how the dialog variable is edited into the display value. The default for this attribute is the same value as was specified on the ALIGN attribute for this tag.

For JUSTIFY=LEFT, the dialog variable is left-justified into the display value and leading blanks are preserved.

For JUSTIFY=RIGHT, the dialog variable is right-justified into the display value and trailing blanks are stripped.

START is a synonym for LEFT, and END is a synonym for RIGHT.

REQUIRED=NO | YES

Indicates whether or not the item is required. This attribute is allowed only for display panels. NO indicates that the item is not required.

YES indicates that the item is required on the display and that the field is highlighted accordingly. YES is only valid if USAGE=INOUT is specified on this tag for the data item.

When REQUIRED=YES is coded, no explicit checks are made for user entry. However, REQUIRED=YES causes the UIM to do input editing and validity check processing, even if the user does not enter anything into the field. This allows you to use the validity checking (CHECK) tag to ensure that the user enters data into a required field.

CSRLOC=YES | NO

Indicates whether or not the cursor is allowed on the input field when the UIM does default cursor positioning. This attribute is allowed only for display panels.

YES does not guarantee that the cursor is placed on the input field; it only indicates to the UIM that the cursor may be placed on the input field when the UIM does default cursor positioning.

NO indicates that the cursor should not be placed on the field. CSRLOC=NO is intended for input fields such as the position-to field found in a data area above a list area. The cursor should not be placed on a position-to field when the panel is first displayed or after a position-to operation completes. When CSRLOC=NO is coded, it is still possible for the UIM to place the cursor on the field when default cursor positioning is performed. This may occur in the following situations:

- All input fields on the current page of the panel are marked with CSRLOC=NO.
- The input field is marked in error.
- The cursor positioning under an application program's control specifies that the cursor should be placed on the field.

The CSRLOC attribute applies to all DATAIX tags associated with this data item.

DISPLAY=YES | NO

Indicates whether or not the contents of the field are visible when the panel is displayed. This attribute is allowed only for display panels.

YES indicates that the field is visible.

NO indicates that the field is not visible. DISPLAY=NO is intended for input fields, such as a password field, which should not be visible.

AUTOENTR=NO | YES

Indicates whether or not the field is an automatic enter input field. This attribute is allowed only for display panels. An automatic enter input field returns from the device to the host when the user enters a character, including a blank, into the last position of the field. This has the same effect as the user pressing the Enter key.

NO indicates that the field is not an automatic enter field.

YES indicates that the field is an automatic enter field. If YES is specified, USAGE=INOUT must also be specified on this tag.

Although the UIM does not restrict its usage, AUTOENTR=YES is intended for input fields that are one character wide.

COND=condition-name

The item is in effect on a display only if the condition specified is true. All associated DATAC and DATAIX tags are displayed only if this data item appears on the display. The condition must be defined in the panel group with the condition definition (COND) tag.

PROMPT='action-text'

The action occurring when F4=List is requested through the PROMPT dialog command. This attribute is allowed only for display panels. The PROMPT attribute is only allowed when USAGE=INOUT is specified for this data item. The valid forms of action-text are:

- *'CALL program-reference'*
For a description of the interface between the UIM and the exit program for the cursor-sensitive prompt, see *System Programmer's Interface Reference*, SC41-8223.
- *'RETURN positive-integer'*

For a description of these actions, see Appendix B, "UIM Dialog Commands" on page B-1.

DSPVALUE=dialog-variable-name

The dialog variable containing the current data entered in this data item. This attribute is allowed only for display panels and when the PROMPT attribute is coded on this tag. This variable is updated regardless of whether or not VARUPD processing is performed. The vari-

able pool is updated based on the VARUPD attribute used to define the function key. This updating is independent of the display value variable processing.

The dialog variable specified must be defined on the CLASS tag as a CHAR or IGC variable whose length is the same as the width of the dialog variable specified on the VAR attribute of this tag. No translation list processing or value checking is performed for the value before it is placed in this variable. Character set and code page conversion are performed for this variable if the class of the variable named on the VAR attribute of this tag specifies that character set and code page conversion should be performed.

Optional Text*data-item-text*

The text describing the data item. The text may appear on more than one line and can only contain the reverse text (RT) tag.

If the item appears in a data item group, it is indented as specified by the GRPSEP attribute on the DATAGRP tag. If the text is too long to fit in the prompt column, it is formatted onto additional lines as necessary to fit within the item column and is indented two spaces.

If no text is specified, the data value appears without a prompt. Prompt text should be specified for all DATAI tags, except for the following special cases:

- When the data item is described completely by the instruction or group heading text appearing above the item.
- When the data item contains a value that is a logical continuation of the value for a data item appearing immediately before it in the panel. Conditioning may be used to present only as many lines on the panel as there are values available.

The set of DATAI tags presenting this type of information should always be specified in a data group to ensure that the UIM keeps related values together on the display, and to present appropriate information in extended help for the panel. Prompt text should be specified for the first data item in the group, or heading text should be specified on the DATAGRP tag

DATAI Tag


to describe the entire group. Help should be specified for the group or for the entire area.

When data groups are not used, the UIM may present items in different layout


columns or even on different scrollable pages. If the same help module is specified for multiple data items, extended help for the panel repeats the online information for each item on the panel.

DATAIX (Data Item Extender)

Syntax for Display Panels



Syntax for Print Panels



The data item extender (DATAIX) tag provides an additional dialog variable to be associated with a data item (DATAI) tag. This tag is allowed for display panels and print panels.

The DATAIX tags must appear after the corresponding DATAI tag. More than one DATAIX tag may be specified after the DATAI tag to provide several dialog variables. If no DATAIX tags are entered, only one dialog variable, specified on the DATAI tag, appears for the data item.

The DATAIX and data choices (DATAC) tags can be specified in any order. The order in which they

are specified determines where they appear in relationship to the dialog variable of the DATAI tag.

Required Attributes

VAR=*dialog-variable-name*

The name of the additional dialog variable displayed with the previous DATAI tag. The current value of the dialog variable is displayed or printed.

For a LAYOUT=1 data presentation area, the display value can exceed the width of the

panel. In this case, the value is presented as a single field that wraps onto as many lines as necessary. For a LAYOUT=2 data presentation area, the display value must fit on one line.

For a LAYOUT=HORIZ data presentation area, the data item prompt, value, and all DATAIX values must all fit on a single line of the panel. If there are already data items on one line of the panel and if the prompt text and dialog variable for the DATAI tag plus the value of this dialog variable do not fit on the current line and still allow a five-column separator between data items, the entire data item, including this item extender, are placed on the next line of the panel.

USAGE=OUT | INOUT

The display use of the data item. This attribute is required for display panels but is optional for print panels.

USAGE=OUT defines an output data item. OUT indicates that the variable displayed is for output only and cannot be changed by the user.

USAGE=INOUT defines a data entry item. INOUT indicates that the variable is for data entry and can be changed by the user.

Optional Attributes

NEWLINE=CALC | NO | YES

Governs the placement of the variable for the data item extender in relationship to the variable value for the data item, possible choices text, and previously-defined data item extenders.

NEWLINE=CALC indicates that the UIM determines the placement of the variable. The variable is placed on the same line as the previous dialog variable if all of the following conditions are true:

- The variable fits within the value column, defined by the second data column (DATACOL) tag of the current line.
- The DATAIX tag is not immediately followed by a DATAC tag.
- The current line is not wrapped from the previous line

If any of the above conditions are not true, the data item extender is placed on the next

display or print line. It is positioned according to the ALIGN attribute of this tag.

When NEWLINE=CALC is specified in a data presentation area with LAYOUT=HORIZ specified, the value is placed on the same line as the previous value.

NEWLINE=NO indicates that the value should be placed on the same line and to the right of the previous value. The previous value is the dialog variable for either the DATAI tag or a previous DATAIX tag. If the DATAIX tag appears immediately after a DATAC tag, NEWLINE=NO is not allowed.

NEWLINE=YES indicates that the value should be placed on the next display or print line. NEWLINE=YES is not allowed for data presentation areas with LAYOUT=HORIZ specified.

ITEMSEP=2 | *item-separator-value*

Indicates how many spaces separate the dialog variable of this data item extender and the previous dialog variable.

For data presentation areas with LAYOUT=1 or LAYOUT=2, the maximum value for this attribute is the width of the choice column, as defined by the second DATACOL tag. For data presentation areas with LAYOUT=HORIZ specified, the maximum value for this attribute is 5. The default value is 2, and the minimum value is 1.

The ITEMSEP attribute is not allowed when NEWLINE=YES is specified on this tag, and has no effect when NEWLINE=CALC is specified and the extender variable is placed on a new line.

ALIGN=LEFT | RIGHT | START | END

Governs how the display value is positioned within the choice column defined by the second DATACOL tag.

If the dialog variable is preceded by the dialog variable for the DATAI tag or by a previous DATAIX tag, the ALIGN attribute has no effect on the position of the display value within the choice column.

If the dialog variable is the first variable on the display or print line, the ALIGN attribute formats text as follows:

- ALIGN=LEFT positions the leftmost character of the display value with the left edge of the choice column.

- **ALIGN=RIGHT** positions the rightmost character of the display value with the right edge of the choice column. If the width of the display value exceeds the width of the choice column, **ALIGN=RIGHT** works the same as **ALIGN=LEFT**.

ALIGN=RIGHT is not allowed for data presentation areas with **LAYOUT=HORIZ** specified.

START is a synonym for **LEFT** and **END** is a synonym for **RIGHT**.

JUSTIFY=LEFT | RIGHT | START | END

Governs how the dialog variable is edited into the display value. The default for this attribute is the same value as was specified or defaulted to on the **ALIGN** attribute of this tag.

For **JUSTIFY=LEFT**, the dialog variable is left-justified into the display value. Leading blanks are preserved.

For **JUSTIFY=RIGHT**, the dialog variable is right-justified into the display value and trailing blanks are stripped.

START is a synonym for **LEFT** and **END** is a synonym for **RIGHT**.

REQUIRED=NO | YES

NO indicates that the item is not required. This attribute is allowed only for display panels.

YES indicates that the item is required on the display and that the field is highlighted accordingly. **YES** is only valid if **USAGE=INOUT** is specified for the data item extender.

When **REQUIRED=YES** is coded, no explicit checks are made for user entry. **REQUIRED=YES** causes the UIM to perform input editing and validity check processing, even if the user does not enter anything into the field. This allows you to use the validity checking (**CHECK**) tag to ensure that the user enters data into a required field.

DISPLAY=YES | NO

Indicates whether or not the field is visible when the panel is displayed. This attribute is allowed only for display panels. **YES** indicates that the field is visible.

NO indicates that the field is not visible. **DISPLAY=NO** is intended for input fields such as a password field, which should not be visible.

PROMPT='action-text'

The action occurring when **F4=List** is requested through the **PROMPT** dialog command. This attribute is allowed only for display panels, and when **USAGE=INOUT** is specified on this tag for this data item extender. The valid forms of action text are:

- **'CALL program-reference'**
For a description of the interface between the UIM and the exit program for the cursor-sensitive prompt, see the *System Programmer's Interface Reference*, SC41-8223.
- **'RETURN positive-integer'**

For a description of these actions, see Appendix B, "UIM Dialog Commands" on page B-1.

DSPVALUE=dialog-variable-name

The dialog variable containing the current data entered into this data item extender. This attribute is allowed only for display panels and when the **PROMPT** attribute is coded on this tag.

This variable is updated regardless of whether or not **VARUPD** processing is performed. The variable pool is updated based on the **VARUPD** attribute used to define the function key. This updating is independent of the display value variable processing.

The dialog variable specified must be defined on the class definition (**CLASS**) tag as a **CHAR** or **IGC** variable whose length is the same as the width of the dialog variable specified on the **VAR** attribute of this tag.

No translation list processing or value checking is performed for the value before it is placed in this variable. Character set and code page conversion are performed for this variable if the class of the variable named on the **VAR** attribute of this tag specifies that character set and code page conversion should be performed.

AUTOENTR=NO | YES

Indicates whether or not the field is an automatic enter input field. This attribute is allowed only for display panels. An automatic enter input field returns from the device to the host when the user enters a character, including a blank, into the last position of the


DATAIX Tag

field. This has the same effect as the user pressing the Enter key.

NO indicates that the field is not an automatic enter field. This is the default value.

YES indicates that the field is an automatic enter field. If YES is specified, USAGE=INOUT must also be specified on this tag. Although the UIM does not restrict its usage, AUTOENTR=YES is intended for input fields that are one character wide.

DATASLT (Data Selection Field)



The data selection field (DATASLT) tag defines a selection field in the data presentation area. This tag is allowed only for display panels.

The DATASLT may be a single- or multiple-choice selection field. The selection field is fixed in content and number of choices. A data selection field can only be specified when LAYOUT=1 or 2 on the data presentation area (DATA) tag.

The data selection field choice (DATASLTC) tag specifies the choices for the selection field. The DATASLTC tag is part of the DATASLT tag with respect to formatting, conditioning, scrolling, and help.

The prompt, field, and choices must fit within the data area. The UIM does not allow a selection field to be split while scrolling.

Other tags can be nested within the DATASLT tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-6. Tag Allowed Between the DATASLT and EDATASLT Tags

Tag Name	Order	Use	Page
DATASLTC (Data selection field choice)	1	D	A-53

Required Attributes

TYPE=SINGLE | MULTI

Specifies whether or not the selection field is a selection field for single or multiple choices.

SINGLE indicates that the selection field is for a single choice.

MULTI indicates that the selection field is for multiple choices.

Optional Attributes

VAR=dialog-variable-name

The name of the dialog variable used to construct the single-choice selection field. This attribute is required for TYPE=SINGLE. The variable is presented on the display if TYPE=SINGLE, and must be declared with a BASETYPE of BIN(31) on the class definition (CLASS) tag. This variable contains the option number of the choice selected by the user. If no choices are selected, the variable returns a zero. The current value of the dialog variable is presented on the display.

If TYPE=MULTI is specified on this tag, this attribute is not allowed.

HELP=help-module-name

Identifies online information explaining the purpose of the data selection field. The name

of the help module may be a name imported from another panel group, but the name must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see "Name Syntax" on page A-4.

A single help module name must be associated with every item in the area. If the HELP attribute is specified on the DATA tag, the help applies to all groups and items in the area, and the HELP attribute is not allowed on any data group (DATAGRP) and DATASLT tags in the area.

If the HELP attribute is specified on the DATAGRP tag, the help applies to all data selection fields in the group, and the HELP attribute is not allowed on DATASLT tags within the group.

If no HELP attribute is specified on the DATA tag nor on DATAGRP tags containing a data selection field, the HELP attribute is required on the DATASLT tag.

NAME=*selection-field-name*

The name associated with the selection field. This name can be used later with the Add Pop-Up Window (QUIADDPW) API to position a window associated with this selection field. For more information on the rules for naming, see "Name Syntax" on page A-4.

PMTLOC=BEFORE | ABOVE

Governs the placement of the prompt text in relationship to the input field associated with the selection field.

BEFORE indicates that the prompt text is placed before (to the left of) the variable value of the data field. The variable value begins on the same line on which the prompt text ended. BEFORE is the default.

ABOVE indicates that the prompt text is placed above the data item variable. The variable is indented two spaces from the beginning of the prompt text.

REQUIRED=NO | YES

This attribute is allowed only for TYPE=SINGLE. NO indicates that the field is not required. NO is the default value.

YES indicates that the field is required on the display, and the field is highlighted accordingly. When REQUIRED=YES is coded, no

explicit checks are made for user entry. However, YES causes the UIM to perform input editing and validity check processing even if the user does not enter anything into the field. This allows you to use the validity checking (CHECK) tag to ensure that the user enters data into a required field.

REQUIRED=YES cannot be specified when TYPE=MULTI is specified on this tag.

AUTOENTR=NO | YES

Indicates whether or not the field is an automatic enter input field. An automatic enter input field returns the screen from the device to the host when the user enters a character, including a blank, into the last position of the field. This has the same effect as the user pressing the Enter key.

NO indicates that the field is not an automatic enter field. This is the default value.

YES indicates that the field is an automatic enter field. Although the UIM does not restrict its usage, AUTOENTR=YES is intended to be used only on input fields that are one character wide. YES is not allowed when TYPE=MULTI is specified on this tag.

COND=*condition-name*

The selection field is displayed only if the condition specified is true. Associated DATASLTC tags are displayed only if this selection field appears on the display. The condition must be defined in the panel group with the condition definition (COND) tag.

Optional Text

selection-field-prompt-text

The text which describes the selection field. The text may appear on more than one line and can contain only the reverse text (RT) tag. The length of the text is 255 bytes or less.

If the selection field appears in a data item group, it is indented as specified by the GRPSEP attribute on the DATAGRP tag. If the text is too long to fit in the prompt column, it is formatted on the following lines as necessary to fit within the column and indented two spaces from the beginning of the first line.

If no text is specified, the selection field appears without a prompt. Prompt text should be specified for all DATASLT tags, except for

when the selection field is described completely by the instruction or group heading text appearing above the item.

Example 1: Data Entry Panel

The example shows a sample data entry panel. The panel has 2 selection fields with the defaults supplied by the calling program by previously setting the dialog variables for the function.

UIM Source

```
:class name=select
  basetype='bin 31'.
:var name=prtstyle
  class=select.
:var name=duplex
  class=select.
:
:panel name=entry1
  help=hentry1
  topsep=space
  ...
  .Sample Entry Panel
:data depth='*'
  bodysep=both.
:topinst.Type choices, press Enter.
:datacol width=30.
:datacol width='*'.
:dataslt help=hstyle
  var=prtstyle
  type=single
  .Type style for printing
:datasltc help=hstylep
  option=1
  .Prestige elite (12 pitch)
:datasltc help=hstylec
  option=2
  .Courier (10 pitch)
:datasltc help=hstylees
  option=3
```

```
.Essay standard (proportional)
:datasltc help=hstyleeb
  option=4
  .Essay bold (proportional)
:edataslt.
:dataslt type=single
  help=hduplx
  var=duplex
  .Duplex
:datasltc help=hduplx
  option=1
  .Print both sides of paper
:datasltc help=hduplxn
  option=2
  .Print one side only
:edataslt.
:edata.
:epanel.
:invellip.
```

Results

Sample Entry Panel

Type choices, press Enter.

Type style for printing . . .	1. Prestige elite 2. Courier (10 pitch) 3. Essay standard (proportional) 4. Essay bold (proportional)
Duplex	1. Print both sides of paper 2. Print one side only

In this example, the *PRTSTYLE* and *DUPLEX* dialog variables must be BIN 31, and the option value selected is returned to the calling program in these variables.

Example 2: Multiple-Selection Field


This example shows a multiple-selection field. The user selects the values by typing a slash (/) or the country-designated character into the entry field preceding the desired options. More than one heading option may be selected.

UIM Source

```
:class name=sfield
    basetype='char 1'.
:var name=hdoptsb
    class=sfield.
:var name=hdoptsu
    class=sfield.
:var name=hdoptsuc
    class=sfield.
:var name=hdoptssn
    class=sfield.
:var name=hdoptstm
    class=sfield.
:var name=hdoptsdt
    class=sfield.
:panel name=xxx
    keyl=x1.Heading Options
: data depth='*'
    bodysep=both.
:topinst.Select one or more
choices, press Enter.
: datacol width=30.
: datacol width='*'.
: dataslt type=multi
    help=haward.Heading options
: datasltc var=hdoptsb
    help=hbold.Bold
: datasltc var=hdoptsu
    help=hundl.Underline
: datasltc var=hdoptsuc
    help=hupperc.Uppercase
: datasltc var=hdoptssn
```

```
    help=hsecn.Section numbers
: datasltc var=heoptstm
    help=htime.Time
: datasltc var=hdoptsdt
    help=hdate.Date
: edataslt.
: edata.
```

Results




```
Heading Options
System: xxxxxxx
Select one or more choices, press Enter.
Heading options . . . . . - Bold
                        - Underline
                        - Uppercase
                        - Section numbers
                        - Time
                        - Date
```

If the user chooses *Underline*, *Section numbers*, and *Date* in this example, the value in the dialog variables are:

- hdoptsb=0
- hdoptsu=1
- hdoptsuc=0
- hdoptssn=1
- hdoptstm=0
- hdoptsdt=1

DATASLTC (Data Selection Field Choice)



The data selection field choice (DATASLTC) tag defines a possible choice for a single- or multiple-choice selection field. This tag is allowed only for display panels. It is not valid if LAYOUT=HORIZ is specified on the data presentation area (DATA) tag for the area.

The DATASLTC tags must appear after the corresponding data selection field (DATASLT) tag and at least one DATASLTC tag must be specified between the DATASLT and the EDATASLTC tags. The DATASLTC tag defines the choices for the selection field.

Optional Attributes

CHOICE=dialog-variable-name

The name of a dialog variable containing the possible choices text to be displayed. The dialog variable must be defined so that the text fits on a single line.

Dialog variables must be defined with a BASETYPE of CHAR, IGC, or BIN on the class definition (CLASS) tag.

The error state of the dialog variable is not used for determining the highlighting of the text.

If the CHOICE attribute is specified, the *text-for-choices* cannot be specified.

Special formatting for IGC. (The abbreviation IGC is used in commands and keywords to represent double-byte character set functions.) When a dialog variable with a BASETYPE of IGC is specified on the CLASS tag, the UIM does special formatting. If the variable value begins with a shift-out character (X'0E'), the UIM shifts the value one char-

acter to the left to preserve vertical alignment with data choices on other lines.

OPTION=option-number

The number assigned to this option. Option numbers are integers in the range of 1 to 99. This attribute is required if specified within a DATASLT tag that has TYPE=SINGLE specified, but cannot be used if TYPE=MULTI is specified.

Selection field choices are displayed in the order defined in the selection field. If the numbering of two choices is not consecutive, a blank line is automatically placed between the two choices. If two choices have the same option number and both are conditioned-on at the same time, the choice defined first is displayed.

VAR=dialog-variable-name

The name of the dialog variable used to indicate whether or not the selection field choice is selected. This attribute is required for TYPE=MULTI. The variable must be declared with a BASETYPE of CHAR 1 on the CLASS tag.

If the choice is not selected, the value of the dialog variable is '0'. If the choice is selected, a value of '1' is returned in the dialog variable. If the current value of the variable is '1' when the screen is displayed, a slash (/) is displayed on the screen. The user may enter either a slash or the country-designated character and a '1' is returned to the user. Whichever character is used for selection by the user is shown when the panel is redisplayed. If the current value of the dialog variable is something other than '1' when the panel is displayed, the variable is presented as unselected.

The VAR attribute is required if TYPE=MULTI on the DATASLT tag. If TYPE=SINGLE is specified, the VAR attribute is not allowed.

HELP=*help-module-name*

Identifies online information explaining the purpose of the selection field choice. The name of the help module may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see "Name Syntax" on page A-4.

This attribute is allowed only when the HELP attribute is specified on the DATASLT tag that contains this DATASLTC tag.

If the HELP attribute is specified on a DATASLTC tag within a selection field, all DATASLTC tags within that selection field must have the HELP attribute specified.

For multiple-choice selection fields with SELECT=MULTI specified on the DATASLT tag, the online information identified by this attribute is included as part of the contextual help displayed when the cursor is positioned anywhere within the selection field.

For single-choice selection fields with SELECT=SINGLE specified on the DATASLT tag, the online information identified by this attribute is displayed when help is requested while the cursor is positioned on the choice text for this tag. This online information is also included as part of the contextual help displayed when the cursor is positioned within the selection field but not on the text for one of the choices within the field. This includes when the cursor is positioned on the prompt text for the selection field or in the entry field for the selection field. If the cursor is in the entry field and a valid choice is entered, when help is requested, the help for that choice is displayed.

COND=*condition-name*

The selection field choice is in effect on the panel only if the condition specified is true. The condition must be defined in the panel group prolog with the condition definition (COND) tag. When the choice is conditioned-off, the selection field choice does not appear in the selection field and the help

for the choice is not included in requests to display help.

AVAIL=*condition-name*

The name of a condition indicating whether or not the selection field choice is available. The condition must be defined in the panel group prolog with the COND tag.

When the condition is true, the selection field choice is available. When the condition is false, the selection field choice is not available. Any condition specified on the COND attribute on this tag takes precedence over this attribute.

Unavailable choices are displayed with a color change and an asterisk (*) overlaying the first part of the choice option number.

The AVAIL attribute cannot be specified if the selection field is specified as TYPE=MULTI on the DATASLT tag.

AVLMSGID=*message-identifier*

The message identifier of the message displayed when the selection field choice is selected when it is not available as specified by the AVAIL attribute on this tag. This attribute is allowed only when the AVAIL attribute is specified.

If this attribute is not specified, the UIM displays a default message stating that the choice is not currently available.

AVLMSGF= '*qualified-message-file-name*'


The message file name containing the message identifier. This attribute is allowed when the AVLMSGID attribute on this tag is specified. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag and the AVLMSGID attribute on this tag is specified, this attribute must be specified.

Optional Text

text-for-choices

This text is an implied paragraph. When the display is formatted, any text that does not fit onto one line is formatted on the following lines and indented two columns. The text can be a maximum of 255 characters and can only contain the reverse text (RT) tag. *Text-for-choices* is required unless the CHOICE attribute is specified on this tag.

DL (Definition List)



The definition list (DL) is a list of words or phrases and their corresponding definitions, descriptions, or explanations. This tag requires a matching end tag. A definition list is only allowed in information areas and help areas.

The terms being defined and their definitions are identified by the definition term (DT) tag and the definition description (DD) tag. A heading for the column of terms and the column of definitions can be identified by the definition term heading (DTHD) tag and the definition description heading (DDHD) tags, respectively.

Definition lists can occur anywhere in text; they can be nested within other lists or definition lists, and other lists can be nested within definition lists.

Two DT or DD tags cannot be used consecutively.

Other tags can be nested within the DL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-7. Tags Allowed Between the DL and EDL Tags

Tag Name	Order	Use	Page
FIG (Figure)	1	B	A-57

Table A-7. Tags Allowed Between the DL and EDL Tags

Tag Name	Order	Use	Page
LINES (Unformatted lines)	1	B	A-75
XMP (Example)	1	B	A-164
NT (Note)	1	B	A-115
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128
LP (List part)	1	B	A-105
OL (Ordered list)	1	B	A-116
SL (Simple list)	1	B	A-149
UL (Unordered list)	1	B	A-157
PARML (Parameter list)	1	B	A-126
DL (Definition list)	1	B	A-55

Optional Attribute

COMPACT

Formats the list without the blank line between the items.

Required Tags

DT.definition-term

The text for the definition term. The term formats the way it is entered, in highlight phrase 2 (HP2).

The term is assumed to be 10 single-byte character set (SBCS) characters or 4 double-byte character set (DBCS) characters, and starts at position 2 relative to the left margin. If the term is longer than the assumed number of characters, it is extended into the description line.

DD.definition

The text for the definition. The description of the term is an implied paragraph and can contain text items. Additional paragraphs can be inserted following the description paragraph, using the paragraph (P) tag.

The description starts at position 14 relative to the left margin, unless the term extends into the description area.

Optional Tags**DDHD.definition-header**

The text for the definition header. The header formats the way it is entered, in highlight phrase 2 (HP2).

DTHD.definition-term-header

The text for the definition term header. The header formats the way it is entered, in highlight phrase 2 (HP2).

Example 1: Definition List

This example illustrates how a definition list with headings will format.

UIM Source

```
:DL.
:DTHD.Term
:DDHD.Description
:DT.DL
:DD.This is a sample
definition list term
and description.
:DT.EDL
:DD.Here is another.
:EDL.
```

Results

Term	Description
DL	This is a sample definition list term and description.
EDL	Here is another.

Example 2: Compact Definition List

This is a definition list using the COMPACT attribute.

UIM Source


```
:DL compact.
:DT.COMPACT
:DD.This causes the list
to be compacted, so the
blank lines are removed.
:DT.ANOTHER
:DD.Here is another.
:EDL.
```

Results

COMPACT	This causes the list to be compacted, so the blank lines are removed.
ANOTHER	Here is another.

Care should be taken when using unformatted lines (LINES), figure (FIG), and example (XMP) tags within a definition list, because text that does not fit on one line wraps to column one of the next line. Lines and figures start at the current left margin and examples are indented four spaces from the current left margin. The current left margin changes when nested lists are formatted. If there is an information source containing the LINES, FIG, or XMP tag imbedded at various locations, including within lists, it may not look the same each time.

FIG (Figure)



The figure (FIG) tag identifies a diagram, chart, or other illustration. This tag requires a matching end tag. The figure tag is only allowed in information areas and help areas. A figure can also contain a figure caption, which is identified by the figure caption (FIGCAP) tag.

Figures turn off automatic formatting, so the text is formatted the same way it is entered. The figure formats where it is entered, across the full width of the screen or window.

Care should be taken when using figures within lists, because figure text that does not fit on one line wraps to column one of the next line.

- | Figures are always formatted with the left margin
- | set to column 2. The formatting width is two
- | columns less than the width specified on the help
- | module. When the FIG tag appears in an informa-
- | tion area, the formatting width initially is two bytes
- | less than the width specified on the panel tag.

The figure caption begins at the left margin. There are two spaces between the figure tag, "Figure:", and the figure caption text if either the figure tag or the figure caption text are single-byte characters. There are four spaces between the figure tag and the figure caption if both are double-byte characters. If the figure caption does not fit on one line, it wraps onto the second line starting at position 4 relative to the left margin.

Optional Attribute

FRAME=RULE | NONE

The type of frame to put around the figure.

RULE is the default. A row of hyphens is displayed above and below the figure.

NONE indicates that no frame is used; a blank line is placed ahead of and behind the figure.

Optional Tag

FIGCAP.figure caption text

A caption for the figure, if needed. The caption may appear on more than one line in the source. The FIGCAP tag must appear immediately before the EFIG tag.

Example: Sample Figure

This example shows how text formats the way it is entered with a FIG tag, and how a FIG tag can specify a frame to set the figure off from the rest of the text.

UIM Source

```

:FIG frame=rule.
some
    sample
        text
:FIGCAP.A Sample Figure
:EFIG.
  
```


Results

```

some
    sample
        text
  
```

Figure: A Sample Figure

HELP (Help Module)



The help module (HELP) tag indicates the beginning of a help module. An EHELP tag must be specified at the end of the help module. A help module can be used for help displays and for index search topics. For more information on the index search function, see “ISCH (Index Search)” on page A-68. Help modules may also be linked to each other. For more information on how help modules may be linked together, see “LINK (Hypertext Link Definition)” on page A-76.

Any tag that has a HELP attribute may refer to this module.

Required Attribute

NAME=*help-module-name*

The name of this help module. For more information on the rules for naming, see “Name Syntax” on page A-4.

This name can be referred to from:

- The HELP attribute on UIM panel definition tags.
- The NAME attribute on an import (IMPORT) tag.
- The NAME attribute on an imbed help (IMHELP) tag within another help module.
- The TOPICS attribute on an index search subtopic (ISCHSUBT) tag.
- The HLPPNLGRP keyword in data description specifications (DDS) specifications.
- A control language (CL) command definition.
- The help identifier array parameter on the Display Help (QUHDSPH) API.
- The DSPHELP dialog command.

The maximum length of the value for the NAME attribute is 32 characters. A slash (/) can be used in the name as a delimiter or separator character. The slash is used to separate a command name from a parameter name when naming a help module for commands. If the slash is used, the name must be enclosed in apostrophes ('). Help modules may not be nested.

Optional Attributes

WIDTH='*' | **help-window-depth**

The width of the help window when it is displayed. A value specified for the WIDTH attribute must include 2 bytes of space for the right and left margin. The minimum width is 32 bytes, and the maximum width is 74 bytes.

Help modules that are displayed as full screen or in an extended help window are indented by 4 bytes. Therefore, the formatting width is 6 bytes less than the width. For example, a help module formatted with the maximum width of 74 bytes has a formatting width of 68 bytes.

The UIM does not increase or decrease the width of the window if a value other than '*' is specified. The width should be specified only if the text between the HELP and EHELP tags depends on a window of a particular width.

If the help is for the function keys or a list area and if WIDTH='*', the UIM uses a width of 38 bytes. If the help is for a menu area or data area, the UIM uses a width of 60 bytes. The UIM finds a location for the window using this width, then expands the window to a size which displays the online information in the most appropriate fashion.

The width used is that of the first HELP tag found when the UIM assembles the online help information.

DEPTH='*' | help-window-depth

The depth of the help window when it is displayed. The value specified for the depth may not be less than nine lines, and must include the following:

- One line for a help title
- One line for a top separator line
- One line for a bottom separator
- Two lines for the function keys
- One line for the message line

For help displayed in a pop-up window, the maximum value for the DEPTH attribute is 21.

The UIM does not increase or decrease the depth of a window if a value other than '*' is specified. A specific depth should be specified only if the text between the HELP and the EHELP tags depends on a particular window width.

If the help is for a data area, menu area, or the function keys, and if DEPTH='*', the UIM chooses a depth of 9. If the help is for a list area, the UIM chooses a depth of 14. The UIM finds a location for the window using this depth, then expands the window to a size designed to display the online help information in the most appropriate fashion.

The depth used is that of the first HELP tag found when the UIM assembles the online help information.

Optional Text*help-title-text*

The title used on the help panel. The text must appear on the same or next line as the tag and can only contain the reverse text (RT) tag. If the *help-title-text* is longer than the pop-up window width, the title text is truncated to the width of the pop-up window. If the value for the WIDTH attribute on this tag is greater than 57 or equal to '*', the maximum length of the *help-title-text* is 55 characters. Otherwise, the maximum length is the value specified for the WIDTH attribute minus two.

The help panel title displayed depends on whether contextual or extended help is

requested and whether the help is displayed as a full screen or in a pop-up window.

Help information presented in pop-up windows is titled as follows:

- For contextual help, the title of the HELP tag for the associated item is used. If no title is defined on the HELP tag, a default title of "Help" is used.
- For extended help, the title from the first HELP tag for the panel is used. If no title is defined on the HELP tag, the default title or the full display title of the QUHDSPH API is used.

If the text for the help title is longer than the pop-up window width, the title text is truncated at a word boundary to the width of the pop-up window. The default title or the full display title of the QUHDSPH API is used.

Help information presented in full screen mode is titled as follows:

- For contextual help, the title from the HELP tag is used.
- For extended help, the title from the first HELP tag is used.
- If no title is defined on the HELP tag, the default title or the full display title of the QUHDSPH API is used.

Help modules must be coded so that each module can be individually formatted. Help modules must begin with one of the following tags:

DL	Definition list
FIG	Figure
H1-H4	Headings
IMHELP	Imbed help
ISCH	Index search
LINES	Unformatted lines
NT	Note
OL	Ordered list
P	Paragraph
PARML	Parameter list
SL	Simple list
UL	Unordered list
XH1-XH4	Extended help headings
XMP	Example


Example: Help Panel Definition

This example shows how a help panel is defined and how the text is displayed.


UIM Source

```
:help name=hmain.Main System Menu - Help
:p.
This panel allows you to ...
  (extended description of the panel)
:ehelp.
```

Results



HP0 through HP9 (Highlighted Phrase)



These highlighted phrase (HP0-HP9) tags identify a word or phrase which is highlighted. All HP*n* tags require matching end tags. These tags are only allowed in help areas and in information areas that are not in the print head (PRTHEAD) or print panel (PRTPNL) tags.

The HP*n* and EHP*n* tag phrase should be specified on word boundaries. If the two characters immediately following the EHP*n* tag are a punctuation mark and a blank, the UIM automatically extends the emphasis attribute to include the

punctuation mark. This allows the punctuation mark and the text associated with it to be displayed using the same emphasis.

Highlighting tags may be nested. For example, :HP1.text:HP2.text2:EHP2.text3:EHP1. is valid.

Optional Text


text
Although the word or phrase to be highlighted is not required, the tag has no meaning when no text is specified.

HP0 through HP9 Tags

Tag	Color Device Formatting	Monochrome Device Formatting	Print Formatting For Help
HP0	Green	Normal	Normal
HP1	<u>Green, underscored</u>	<u>Underscored</u>	<u>Underlined</u>
HP2	White	High intensity	Bold
HP3	<u>White, underscored</u>	<u>High intensity, underscored</u>	<u>Bold, underlined</u>
HP4	Green	Normal	Normal
HP5	Green, reverse image	Normal, reverse image	<u>Underlined</u>
HP6	<u>Green, underscore, reverse image</u>	<u>Underscore, reverse image</u>	<u>Underlined</u>
HP7	White, reverse image	High intensity, reverse image	<u>Bold, underlined</u>
HP8	White, reverse image	High intensity, reverse image	<u>Bold, underlined</u>
HP9	White, reverse image	Normal, reverse image	<u>Underlined</u>

RV2W062-0

H1 through H4 (Heading)



The heading (H1-H4) tags identify main topics and subtopics of information. These tags are only allowed in information areas and help areas.

In a help area, text after the headings is indented four spaces from the margin to separate the headings from the text. In an information area, text formats flush left, against the left margin.

Headings have one blank line formatted before and after the heading text.

Specific formatting rules are as follow:

- H1** Centers and formats text as underscored and highlighted, like the HP3 tag. This tag causes a page eject when it appears in a printed help module.
- H2** Left justifies and formats text as underscored and highlighted, like the HP3 tag.
- H3** Left justifies and formats text as highlighted text, like the HP2 tag.
- H4** Left justifies and formats text as underscored, like the HP1 tag.

Required Text

heading-text

The text for the heading. The text of a heading must be entered on a single line and is formatted as entered. It cannot contain any other tags. A common practice is to enter the

text according to the current publishing style, with significant words in initial caps.

Example: Heading Tags

This example illustrates how the different headings are justified and formatted.

UIM Source

```
:H1.A One Heading
:p.Here's a paragraph.
:H2.A Two Heading
:p.Another paragraph.
:H3.A Three Heading
:p.Still another paragraph.
:H4.A Four Heading
:p.Still another paragraph.
```

Results:

A One Heading

Here's a paragraph.

A Two Heading

Another paragraph.

A Three Heading

Still another paragraph.

A Four Heading

Still another paragraph.

IMHELP (Imbed Help)

►►:IMHELP—NAME=*help-module-name*—◄◄

- | The imbed help (IMHELP) tag embeds a help
- | module from another panel group object. This tag
- | can occur only in help modules within the help
- | module (HELP) and EHELP tags.

Required Attribute

NAME=*help-module-name*

The name of a help module imbedded where this tag occurs. For more information on the rules for naming, see “Name Syntax” on page A-4. The name must be the name of another help module defined within the same panel group, or it must be imported from another panel group using the import (IMPORT) tag. IMHELP tags have a nesting limit of 16.

- | If the index search (ISCH) or index search
- | synonym (ISCHSYN) tags are a part of the
- | embedded help module, they are not part of
- | the module where the the IMHELP tag occurs.

An active highlight phrase (HP*n*) tag is not allowed when an IMHELP tag is coded. Any

active HP*n* tags must be ended with EHP*n* tags before coding the IMHELP tag.


Example: Imbedded Help

This example uses imported help for the help on function keys.

UIM Source

```
:HELP name='menu1'.
:H2.Purpose of MENU1
Menu1 is intended for the use of...
:
:IMHELP name='keydefs'.
:
:EHELP.
:
:HELP name='keydefs'.
:PARML.
:PT.F1=Help
:PD.This key...
:PT.F3=Exit
:PD.This key...
:EPARML.
:EHELP.
```

IMPORT (Import)



The import (IMPORT) tag makes help modules defined in another panel group object available in the current panel group. This tag must appear in the prolog section of the panel group source following the panel group (PNLGRP) tags and the copyright (COPYR) tag. An IMPORT tag must be specified before any references by other tags to the help modules it defines.

This tag may also assign a private name to the imported help module. If a private name is assigned, the private name replaces the imported name in the scope of the current panel group. This allows names to be imported that would have conflicted with other names within the current panel group.

Required Attributes

NAME=*imported-name* | '*'

The internal name of the help module imported for use within the current panel group. For more information on the rules for naming, see "Name Syntax" on page A-4.

If '*' is coded, all unresolved names are assumed to be imported from this panel group. Only one IMPORT tag may be coded with NAME='*'.

PNLGRP=*panel-group-name*

The name of the panel group that contains the help module specified by NAME. This is an OS/400 object name which obeys all object name rules. This name may be fully qualified.

Optional Attributes

NEWNAME=**SAME** | *private-name*

A new name used instead of the imported name within the current panel group. The new name suppresses the visibility of the imported name and serves as its replacement. Only NEWNAME=SAME is allowed when NAME='*' is specified.


PRDLIB=*product-library-name*

The name of the library added into the library search list as a product library, used to locate the panel group defining the help module specified by the NAME attribute on this tag. This attribute is not allowed when the PNLGRP attribute is fully qualified.


The product library is only used when imbedding help information using the imbed help (IMHELP) tag. The product library is ignored when referring to a help module using the HELP attribute on other UIM tags.

INFO (Information Area)

Syntax for Display Panels



Syntax for Print Panels



An information area (INFO) tag provides textual information to explain the operation of an application or panel. This tag is allowed for display panels and print panels. It can construct a detailed instruction area on a panel.

- | Information areas are formatted with a width of 72
- | columns unless the width attribute on the panel
- | tag is less than 74 columns. In this case, the
- | information area is formatted with a width of two
- | columns less than the width attribute on the panel
- | tag.

Required Attribute

DEPTH=*area-depth* | '*'

The depth of the area in lines, including separators if any are specified. This attribute is required for display panels, but not allowed for print panels. If '*' is specified, the space remaining on the display after other panel elements are allocated is given to this area. Only one area in the panel may have '*' coded.

Optional Attributes

BOTSEP=SPACE | NONE | RULE

Defines the bottom separator for the information area. If SPACE is specified, a line of spaces is used.

NONE indicates that no separator line exists.

If RULE is specified, a line of underscored spaces is used.

SCROLL=NO | YES

Indicates whether or not this area is scrollable. This attribute is allowed only for display panels. NO indicates that the area is not scrollable.

YES indicates that the area is intended to be scrollable. For a SCROLL=YES area, a line of spaces is used by the UIM to provide a line for the scroll information. If BOTSEP=SPACE is specified also, one line is used for both the separator and the scroll information line.

TYPE=NORMAL | PROLOG

Indicates whether or not this information area is a prolog area. The prolog area is printed only once after the title line on the first page. This attribute is allowed only for the print head (PRTHEAD) tag. This attribute is valid only when the INFO tag appears between the PRTHEAD and the EPRHEAD tags for information areas in a PRTHEAD panel. NORMAL is the default value.

Optional Text

area-title

The title of the area. If no text is specified, no title line is allocated to the area. The text must appear on the same or next line as the tag, can contain only the reverse text (RT)

tag, and cannot exceed a maximum length of 55 characters long.

Print Formatting Considerations

Printed information areas are formatted like displayed areas, except when four lines of an information area do not fit on a page when printing. If this is the case, a page eject occurs and the information area is printed on the next page. Informa-

tion areas are formatted to a width of 72 columns, as is done for information areas on display panels, regardless of the width specified on the PRTHEAD or print panel (PRTPNL) tag.

ISCH (Index Search)

```
►►: ISCH—ROOTS='root-word-list'—.—index-entry-text—►►
```

The index search (ISCH) tag identifies the text displayed by the index search function if the user enters a word that matches a synonym. The ISCH tag is only allowed in source code for panel group objects and is not allowed in the source for menu objects. The placement of the ISCH tag determines the help module displayed when the index entry is selected. The ISCH tags should appear immediately after the help module (HELP) tag it refers to.

Required Attribute

ROOTS='root-word-list'

A list of up to 50 root words that apply to the index entry. Each root word may be up to 20 characters and can contain only the characters A through Z, a through z, and 0 through 9. One or more blanks must be specified between words, so the entire list must be enclosed in apostrophes. The ROOTS attribute may be repeated, allowing you to define more root words for an index entry than fits on one source line.

The root words serve as a link between the ISCH tags and the index search synonym (ISCHSYN) tags, and do not appear to the user. To allow the user to search for an index entry, each root word specified here must have a matching root word on an ISCHSYN tag.

Required Text

index-entry-text

The text of the index entry presented when one of the synonym words is selected. The text may contain up to 72 characters. It must appear on the same or next line as the period

which ends the tag definition and cannot span two lines in the source.

If the index entry is a subtopic, the index-entry-text is indented two spaces from the text of the first higher index entry in the hierarchy of index entries.

The text which is provided is used as the topic title when topics are presented for selection. If no text is specified on the HELP tag of the topic, the text provided on the ISCH tag is also used as the panel title when the topic is selected for presentation. When used as a panel title, no more than 55 characters of the text is shown. If the text contains more than 55 characters, it is truncated at a blank and an ellipsis (...) is placed after the text to indicate that truncation has occurred.

Example: Index Search

This example shows some ISCHSYN tags and the ISCH tags that use them:

UIM Source

```
:ISCHSYN ROOT='copy'.copy copying copies
:ISCHSYN ROOT='delete'.delete deleting deletes
:ISCHSYN ROOT='delete'.remove removes removing
:ISCHSYN ROOT='folder'.folder folders
:ISCHSYN ROOT='folder'.document documents
:
:help name=fldcpy.
:ISCH ROOTS='copy folder'.Copying folders
:
:ehelp.
:help name=flddlt.
:ISCH ROOTS='delete folder'.
Deleting folders
:ehelp.
```


ISCHSUBT (Index Search Subtopic)

►►: ISCHSUBT—TOPICS='help-module-name-list'—.◄◄

The index search subtopic (ISCHSUBT) tag identifies the help modules within the same panel group that are subtopics under the preceding topic specified on an index search (ISCH) tag. The ISCHSUBT tag must appear after the ISCH tag. This tag is repeatable.

Any help module with an ISCH tag that is not identified by an ISCHSUBT tag is a primary topic in the index search hierarchy. Therefore, if no ISCHSUBT tags are used, all help modules are primary topics and there is no hierarchy in the index search. The ISCHSUBT tag is allowed only in source code for panel group objects; it is not allowed in the source code for menu objects.

Required Attribute

TOPICS='help-module-name-list'

Identifies the help modules within the same panel group that are subtopics under the preceding topic specified on an index search (ISCH) tag. The order in which the help modules appear on the TOPICS attribute is the order in which they are displayed in the index search hierarchy. A help topic name cannot be specified twice in this list. For more information on the rules for help modules names, see “Name Syntax” on page A-4. This attribute is repeatable.

A topic can be the subtopic of more than one topic.

Topics can be nested to no more than 16 levels.

Example: Index Search Hierarchy

The following example shows how the ISCH tags and ISCHSUBT tags work together to form an index search hierarchy:

UIM Source

```
:HELP name=mainhelp.
:ISCH roots='root words'.
Main Help Topic
:ISCHSUBT topics='help1'
               topics='help2'.
:
:EHELP.
:HELP name=help1.
:ISCH roots='root words'.
Help number 1
:ISCHSUBT topics='help3 help4'.
:
:EHELP.
:HELP name=help2.
:ISCH roots='root words'.
Help number 2
:ISCHSUBT topics='help3'
:
:EHELP.
:HELP name=help3.
:ISCH roots='root words'.
Help number 3
:
:EHELP.
:HELP name=help4.
:ISCH roots='root words'.
Help number 4
:
:EHELP.
```

This UIM source creates the following index search hierarchy:

Title of this index

```
Main Help Topic
  Help number 1
    Help number 3
    Help number 4
  Help number 2
    Help number 3
```

ISCHSYN (Index Search Synonym)

►►: ISCHSYN—ROOT=*root-word*—.—*synonym-words*—►►

The index search synonym (ISCHSYN) tag identifies the variations and synonyms for the root words used in the index search function. The ISCHSYN tag is only allowed in source for panel group objects and is not allowed in the source for menu objects.

The text must be entered on one line. If more than one line is needed, multiple ISCHSYN tags may be coded. This text, when combined with the index search (ISCH) tag, determines the index entries displayed when the user enters words for the index search function.

The ISCHSYN tags build a table of synonyms, which serves as a link to the ISCH tags. As words are entered for an index search, they are matched with the words in the synonym table to link to the entries displayed.

There is no restriction on the placement of the ISCHSYN tags, but to make maintenance and translation easier, they should be placed in one area, such as the beginning of the panel group or in a panel group object which contains only ISCHSYN tags.

Required Attribute

ROOT=*'root-word'*

The root word to which the synonyms apply. If a real word is used for the root word, like "copy," that word should also be entered in the *synonym-words* field.

The root word is used in the ROOTS attribute of the ISCH tag and may be up to 20 characters. A root word can contain only the characters A through Z, a through z, and 0 through 9.

Required Text

synonym-words

Special Format. Specifies variations and synonyms for the root word. The synonym words must be separated by blanks. If additional synonyms are needed for a root word,

additional ISCHSYN tags should be entered specifying the same root word. The additional synonyms are added to the previous synonyms.

Each synonym word must be 40 characters or less and can contain no spaces. It cannot contain a period, left or right parenthesis, a semicolon, a comma, question mark, or colon.

Different languages have a larger or smaller number of synonyms for each word. To provide meaningful results, the translation of a root word must be done by providing a list of synonym words and by not translating each English synonym.

The UIM automatically handles lowercase, single-byte character set (SBCS) synonym words the same way as uppercase words, using the code page specified on the TXTCHRID attribute of the panel group (PNLGRP) tag.

Example: Index Search Synonyms

This example shows several ISCHSYN tags and how they are referred to by ISCH tags.

UIM Source

```
:pnlgrp...
:
: ISCHSYN ROOT='copy'.copy copying
: ISCHSYN ROOT='copy'.duplicate duplicating
: ISCHSYN ROOT='copy'.model
: ISCHSYN ROOT='root1'.remove removing
: ISCHSYN ROOT='root1'.delete deleting
: ISCHSYN ROOT='root1'.trash discard
: ISCHSYN ROOT='folder'.folder folders
: ISCHSYN ROOT='folder'.document documents
: ISCHSYN ROOT='folder'.data information
:
: help name=fldcpy.
: ISCH ROOTS='copy folder'.Copying a folder
: h2.Copying a Folder
:
: ehel.
:
```

```
:help name=flddlt.
:ISCH ROOTS='root1 folder'.Deleting a folder
:h2.Deleting a folder
:
:ehelp.
```

In this example, the ISCHSYN tags builds a synonym table containing the following entries:


Root Word	Synonym Words
copy	copy copying duplicate duplicating model
root1	remove removing delete deleting trash discard

folder	folder folders document documents data information
---------------	---

The ISCH tag for the "Copying a folder" entry points to the "copy" and "folder" search synonym lists.

When the user requests "copy folders," the entry is found and displayed because "copy" and "folders" are both listed as matches in the ISCHSYN table. If the user entered "copy folders," "folders, copy," or "copying documents," the entry "Copying a folder" is displayed.

KEYI (Key List Item)



The key list item (KEYI) tag defines a single function key. This tag must occur between the KEYL and EKEYL tags. It assigns displayable text for a specified key and identifies the action to take place when that key is pressed.

Required Attributes

KEY=key-name

The names for the engraved or software defined function keys are Attn, Enter, F1-F24, Help, Home, Print, Pagedown, Pageup, and Sysreq.

HELP=help-module-name

The associated help module for the key description. The help module name may be a name imported from another panel group, but it must follow the rules for names outlined earlier in this chapter. For more information on the rules for naming, see “Name Syntax” on page A-4.

ACTION='action-text'

The action occurring when the function key is pressed. This attribute is conditionally required. For certain keys, the ACTION attribute must not be specified since the UIM does not handle that particular key. For all other keys, the ACTION attribute is required.

The valid forms of action text are:

- 'ACTIONS'
- 'CALL program-reference'
- For a description of the interface between the UIM and the function key CALL program, see *System Programmer's Interface Reference*, SC41-8223.
- 'CANCEL'
- 'CHGVIEW'
- 'CMD command-string'

Any dialog variable in the command string must be preceded by an ampersand to denote variable substitution.

- 'CMDLINE'
- 'ENTER'
- 'EXIT'
- 'HELP'
- 'HOME'
- 'MENU qualified-menu-name RTNPNTINORTNPNT'
- 'MOREKEYS'
- 'MOVETOP'
- 'PRINT'
- 'PROMPT'
- 'RETRIEVE'
- 'RETURN positive-integer'
- 'PAGEUP'
- 'PAGEDOWN'

For a description of each of these actions, see Appendix B, “UIM Dialog Commands” on page B-1.

Engraved key assignments are enforced by the compiler. These keys are the keys listed, except for F1 through F24. If engraved keys are assigned anything but their corresponding dialog function (or no action in certain cases), a compile error results. The following is a list of the engraved keys and their corresponding actions:

Key	Action
Attn	No action
Enter	'ENTER'
Help	'HELP'
Home	'HOME'
Print	'PRINT'
Pageup	'PAGEUP'
Pagedown	'PAGEDOWN'
Sysreq	No action

Optional Attributes

COND=*condition-name*

The key is in effect on the panel only if the condition specified is true. The condition must be defined in the panel group with the condition definition (COND) tag.

VARUPD=YES | NO

If YES is coded, validity checking occurs and the variable pool is updated with values entered by the user before the action takes place.

If NO is coded, the action is performed immediately and no variable pool updating occurs. If the VARUPD attribute is not specified and the EXIT or CANCEL dialog command is specified on the ACTION attribute of this tag, a warning message is generated at compile time stating that VARUPD=YES is assumed. This is done as a reminder to you, because you may not want to check for valid input data before allowing the user to exit a screen through these dialog commands. To avoid this message, specify VARUPD=YES or VARUPD=NO on the key assignment.

If no ACTION attribute is specified, this attribute is ignored.

PRIORITY=*priority-number*

The order in which keys should be displayed when the MOREKEYS dialog command is performed.

Key items with a lower number priority are displayed before key items with a higher number priority. A specified priority number must be greater than or equal to one and less than or equal to 99.

If a priority is not specified for a key, the default value depends on the action specified:

Action	Default
EXIT	1
CANCEL	2
All others	99
No action	99

The PRIORITY attribute is used only within a key list that has ACTION=MOREKEYS specified on one of the KEYI tags. Otherwise, the priority attribute is ignored.

Optional Text

key-description-text

The displayable description for the associated key. For example, "F5=Refresh" or "F12=Cancel". If no text is specified, a description of the key is not displayed on the panel, although the key is active. The text must appear on the same or next line as the tag and can only contain the reverse text (RT) tag.

The function key area is formed by concatenating the text from the various key list items, with each key separated by at least three spaces. If the text does not fit on the rest of a line, it is placed on the next line.

Example: Key Definitions

The following example defines the function keys F3, F5, F11, and F12.

UIM Source

```
:keyl name=keylist
      help=hkeylist.
:keyi key=f3
      action='exit set'
      help=exit
      .F3=End task
:keyi key=f5
      action='return 5'
      help=refresh
      .F5=Refresh
:keyi key=f11
      action=chgview
      help=chgview
      .F11=Alternate view
&gms.keyi key=f12
      action='cancel set'
      help=cancel
      .F12=Cancel
:ekeyl.
```

Results

F3=End task F5=Refresh F11=Alternate view F12=Cancel

KEYL (Key List)

```

▶▶:KEYL—NAME=key-list-name—HELP=help-module-name—.—:EKEYL.▶▶

```

The key list (KEYL) tag indicates the beginning of a list of key definitions. Each list may be referred to by one or more panel definitions. An EKEYL tag must be specified at the end of the key list.

Other tags can be nested within the KEYL tag. These tags are listed in the following table. The table defines the order in which the tags must appear and specifies on which page more information can be found for each tag.

Table A-8. Tag Allowed Between the KEYL and EKEYL Tags.

Tag Name	Order	Page
KEYL (Key list item)	1	A-74

Required Attribute

NAME=key-list-name

The name assigned to the key list. For more information on the rules for naming, see "Name Syntax" on page A-4.

Optional Attribute

HELP=help-module-name

Identifies online help information explaining the purpose of the function keys. The name of the help module can be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see "Name Syntax" on page A-4.

Example: Key List

This is an example of a key list.


UIM Source: An example of a key list follows:

```

:keyl name=keylist.
:keyi key=f1
      help='key/helpf1'
      action=help.
:keyi key=f3
      help='key/exit'
      action='exit set'.F3=Exit
:keyi key=f12
      help='key/cancel'
      action='cancel set'.F12=Cancel
:keyi key=f24
      help='key/morekeys'
      action=morekeys.F24=More keys
:keyi key=enter
      help='key/enter'
      action=enter.
:keyi key=help
      help='key/help'
      action=help.
:keyi key=pagedown
      help='key/pagedown'
      action=pagedown.
:keyi key=pageup
      help='key/pageup'
      action=pageup.
:keyi key=print
      help='key/print'
      action=print.
:ekeyl.

```

LINES (Unformatted Lines)



The unformatted lines (LINES) tag identifies an area of user-controlled line entry where the lines are not automatically concatenated. Text is formatted the same way it is entered. This tag is only allowed in information areas and help areas. The LINES tag requires a matching end tag.

Note: Care should be taken when using unformatted lines within lists, because text that does not fit on one line wraps to column one of the next line. The current left margin changes when nested lists are being formatted. If there is online help information containing unformatted lines imbedded at various locations, including within lists, it may not look the same each time.

- | Help modules displayed in full-screen format or in
- | an extended help window are indented by 4 bytes.
- | Therefore, the formatting width initially is 6 bytes
- | less than the width specified on the help module.
- | When the LINES tag appears in an information
- | area, the formatting width initially is two bytes less
- | than the width specified on the panel tag.

Optional Text

unformatted-lines

Although the text for the unformatted lines is not required, the tag has no meaning when no text is specified.

Example: Unformatted Lines

This example illustrates how text is formatted the same way it is entered.

UIM Source

```


:LINES.
First line
Second line
:ELINES.
  
```

Results

```

First line
Second line
  
```

LINK (Hypertext Link Definition)



The hypertext link definition (LINK) tag identifies the reference phrase text which is the anchor of a static hypertext link. A reference phrase may appear in any UIM help area, but may not appear in an information area. This tag requires a matching end tag. It also identifies action taken when the reference phrase is selected. The only type of action supported is to display a help module.

The LINK and ELINK tag must be specified on word boundaries. If the two characters immediately following the ELINK tag are a punctuation mark and a blank, the UIM automatically extends the emphasis attribute to include the punctuation mark. This allows the punctuation mark and the text associated with it to be displayed using the same emphasis.

On a monochrome device, the reference phrase text is displayed as highlighted, underscored text. On a color device, the reference phrase text is displayed as underscored, yellow text. Because of hardware limitations, the underscore is not visible on a PS/2* computer or on a personal computer with a color device.

The only tag that can be used within a link tag is the reverse text (RT) tag. LINK tags may not be used within other LINK tags, but may be used within any of the following tags:

CIT	Title citation
DD	Definition
FIG	Figure
FIGCAP	Figure caption text
HP_n	Highlighted phrase
LI	List item

LINES	Unformatted lines
LP	List part
NT	Note
P	Paragraph
PC	Paragraph continuation
PD	Parameter description
PK	Programming keyword
PV	Programming variable
XMP	Example

Required Attribute

PERFORM= 'action-text'

The action occurring when the reference phrase is selected and all of the condition expressions for the UNLESS_n attributes have evaluated to false. The valid form of action text is:

- 'DSPHELP help-module-name [panel-group-name]'

Note: The brackets in the option text above indicate that the panel group name is optional. They are *not* required in the UIM source.

For a description of the DSPHELP action, see Appendix B, "UIM Dialog Commands" on page B-1.

Optional Attributes

UNLESS_n= 'conditional-expression'.

The only allowed values for *n* are 1 through 4.

The UNLESS_n and THEND0_n attributes must be coded as pairs. The expressions on the UNLESS_n attributes are evaluated in numeric

order. If one evaluates to true, the corresponding THEN0n action is performed and all higher-numbered UNLESSn and THENn attributes and the PERFORM attribute on this tag are ignored.

For information on using conditional expressions with the UNLESSn attribute, see “Conditional Expressions.”

THEN0n=*'action-text'*

The only allowed values for *n* are 1 through 4.

This attribute specifies the action occurring when the reference phrase is selected and the conditional expression for the corresponding UNLESSn attribute evaluates to true and all the conditional expressions for the lower-numbered UNLESSn attributes evaluate to false.

The UNLESSn and THEN0n attributes must be coded as pairs. The UNLESSn attributes are evaluated in numeric order. If one evaluates to true, the corresponding THEN0n action is performed and all higher-numbered UNLESSn attributes and the PERFORM attribute on this tag are ignored.

The valid form of action text is:

- *'DSPHELP help-module-name [panel-group-name]'*

Note: The brackets in the option text above indicate that the panel group name is optional. They are *not* required in the UIM source.

For a description of the DSPHELP action, see Appendix B, “UIM Dialog Commands” on page B-1.


LINKWHEN=*'conditional-expression'*.

When the LINKWHEN expression evaluates to true or is not coded, the reference phrase is made available and a user is allowed to select it. When the LINKWHEN expression evaluates to false, the reference phrase is not activated and may not be selected.

For more information on using conditional expressions with the LINKWHEN attributes, see “Conditional Expressions.”

Conditional Expressions

Although the set of conditions that can be formed with the LINKWHEN attribute is identical to the set of conditions that can be formed with the UNLESSn attributes, the significance of those conditions is different. The LINKWHEN attribute activates or deactivates the LINK tag, while the UNLESSn attribute selects the action performed when an active LINK tag is selected. A conditional expression is a true or false expression in the following form:



where *A* is an operand which can be one of the following:

- A conditional expression
- A built-in function


The logical OR character (|) can be used in place of *OR, the ampersand character (&) can be used in place of *AND, and the logical NOT character (–) can be used in place of *NOT. Because the logical OR and logical NOT characters are not in the invariant character set, their use is not recommended. For code page 00037, the common USA code page, the hexadecimal value of the logical OR character is X'4F', and the hexadecimal value of the logical NOT character is X'5F'. The UIM compiler uses these hexadecimal values regardless of the code page of the source.

There are two built-in functions:

CHKOBJ

Evaluates to true if the object is found on the system and the current job possesses at least the level of authorization to the object specified by the authorities. Arguments must be character strings enclosed in quotation marks ("). The object name follows OS/400 object naming conventions. The object type is any of the allowable object types for the DSPOBJD command and the authorities must be a single value or a list of authorizations to be checked for. The values of these authorizations are separated by blanks. The following syntax diagram illustrates the authorities and how to use them:

LINK Tag



Note:

- ¹ Each value can be used only once, a maximum of 7

If no authorities are specified, no authorization check is performed and the function becomes an existence check.


When a program adopts the authority of its owner, that authority is normally used to authorize operations performed by that program. However, when help is requested, those adopted authorities are ignored while the UIM displays the online help information. Therefore, no adopted authorities are used when the CHKOBJ function is used on the UNLESS or LINKWHEN attributes on the LINK tag.

For more information about programs adopting the authority of the owner, see the USRPRF(*OWNER) parameter on the CRTCLPGM command.

CHKUSRCLS

The user class argument specified for the function is compared to the user class parameter from the user profile of the current job. The function evaluates to true if the user profile has the same or greater value than the function argument. The function argument must be enclosed in quotation marks (").

The following syntax diagram illustrates the valid argument values for the user class:



Examples of conditional expressions follow:

```
CHKOBJ("OBJECT","*FILE","*USE")
CHKOBJ("PANELGRP","*PNLGRP")
    *AND CHKUSRCLS("PGMR")
CHKOBJ("DOCUMENT","*DOC","*READ *UPD")
    *OR CHKUSRCLS("SYSOPR")
*NOT (CHKOBJ("PROGRAM","*PGM"))
```

Bidirectional Considerations

The value of the BIDI attribute on the panel group (PNLGRP) tag of all possible panel groups that can be reached by taking hypertext links should be the same. If they are not the same, it is possible that the resulting screen or pop-up window is displayed with the opposite orientation when a reference phrase is selected.

Example: Hypertext Link

This example shows how hypertext links can be used to provide definitions for terms.

UIM Source

```
:HELP NAME='hyper/help'.Hypertext in OS/400
:P.
Hypertext lets users explore
the online help information in a way that is most
natural for them.
Hypertext links can be used within :LINK
PERFORM='DSPHELP item/specific/help'
    .item specific help:ELINK.,
:LINK PERFORM='dsphelp extended/help'
    .extended help:ELINK., and
:LINK PERFORM='dsphelp infoseeker/help'
    .Infoseeker help:ELINK..
:EHELP.

:HELP NAME='item/specific/help'
    .Definition of Item Specific Help
:P.
Item specific help is . . .
:EHELP.

:HELP NAME='extended/help'
    .Definition of Extended Help
:P.
Extended help is . . .
:EHELP.

:HELP NAME='infoseeker/help'
    .Definition of InfoSeeker
:P.
InfoSeeker allows you to tell the
```

```

| system to search for specific information.
| InfoSeeker information is made more
| useful by the addition of
| :LINK PERFORM='dsphelp hyper/help'
| .hypertext:ELINK. because
| it allows you to link to additional help
| topics.
| :EHELP.

```

Results

```

: .....Hypertext on OS/400.....
:
: Hypertext lets users explore the online information in a way
: that is most natural for them. Hypertext links can be used
: within item specific help, extended help, and
: Infoseeker help.
:
: F2=Extended help F10=Move to top F11=InfoSeeker Bottom
: F13=Information Assistant F24=More keys F12=Cancel
: .....

```

When the cursor is moved to *INFOSEEKER HELP* and the Enter key is pressed, the following screen is shown.


```

: .....Definition of InfoSeeker.....
:
: InfoSeeker allows you to tell the system to search for specific
: information. InfoSeeker information is made more useful by the
: addition of > hypertext because it allows you to link to
: additional help topics.
:
: F6=Viewed topics F10=Move to top F11=InfoSeeker Bottom
: F13=Information Assistant F24=More keys F12=Cancel
: .....


```

LIST (List Area)

Syntax for Display Panels



Syntax for Print Panels



The list area (LIST) tag defines a list area on a panel.

This tag is allowed for display panels and print panels, except for the print head panel (PRTHEAD) tag. A **list area** consists of an arbitrary number of rows of like columns, and can be scrolled up and down if the number of rows exceeds the area in which the list is displayed.

A list area presents a view of a UIM list, which is manipulated by the UIM application programming interfaces (APIs). UIM lists are named and

described by the list definition (LISTDEF) tag. The UIM displays the entries in the list, handling the scroll operations which allow the user to see all the entries.

The area may have multiple views, which are selected by the CHGVIEW dialog command. The CHGVIEW dialog command can be assigned to a function key which alternates between the views.

Other tags can be nested within the LIST tag. These tags are listed in the following table. The table defines the order in which the tags must

appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-9. Tags Allowed Between the LIST and ELIST Tags

Tag Name	Order	Use	Page
TOPINST (Top instruction line)	1	D	A-154
LISTACT (List action)	2	D	A-88
LISTGRP (List column group)	3	B	A-101
LISTCOL (List column)	3	B	A-94
LISTVIEW (List view)	4	B	A-103
BOTINST (Bottom instruction line)	5	D	A-10

Required Attributes

DEPTH=*area-depth* | '*'

This attribute is required for display panels but is not allowed for print panels. The depth of the area in lines, including separators if any are specified. If '*' is specified, the space remaining on the display after all other panel elements are allocated is given to this area. Only one area in the panel may have '*' coded.

LISTDEF=*list-name*

The name of the UIM list from which the data for this list area is taken. The list must be defined in the panel group using the LISTDEF tag.

Optional Attributes

BOTSEP=SPACE | NONE | RULE

Defines the bottom separator for the list area. If SPACE is specified, a line of spaces is used.

NONE indicates that no separator line exists.

If RULE is specified, a line of underscored spaces is used as a separator line.

SCROLL=YES | NO

Indicates whether or not the list area is scrollable. This attribute is allowed only for display panels. YES indicates that the list area is intended to be scrollable. For SCROLL=YES, a line of spaces is used by the UIM to provide a line for the scroll information.

NO indicates that the list is not scrollable. Ordinarily, NO would not be used, but for short lists it can be specified to disable the scrolling keys for the list area.

If BOTSEP=SPACE is specified and there are no bottom instructions for both the separator and scroll information line, one line is used.

MAXHEAD= 0 | 1 | 2 | 3 | 4

The maximum number of lines for column headings. From 0 to 4 lines can be specified. The default is 0, indicating that no column headings are allowed. For more information on column headings, see "LISTCOL (List Column)" on page A-94. This attribute includes any heading line required by the column group headings.

When column headings are used, provide expansion space for national language translation by specifying a MAXHEAD value larger than the number of heading lines required. If this expansion space is not provided, it must be provided within the column width determined by the MAXWIDTH attribute of each list column (LISTCOL) tag.

This attribute cannot be specified if the HEADSIZE attribute on this tag is specified for use with variable column headings.

BODYSEP=SPACE | INDENT | BOTH | NONE

The type of visual separation distinguishing the body of the area from other elements in the area, particularly any top and bottom instruction lines within the area.

SPACE leaves a blank line after the top instruction lines and before the bottom instruction lines. List columns in the body of the

LIST Tag

area begin in the leftmost position of the layout column and are not indented with respect to instruction lines. If the area contains no top or bottom instruction lines, no blank lines are reserved before or after the area body.

INDENT is used to indent list columns in the body of the area by two positions from the leftmost position in the layout column where the instruction lines begin. If the area contains top or bottom instruction lines, no blank line is reserved between the instructions and the area body except if the area is scrollable. If the area is scrollable, a blank line is reserved for the scroll information.

BOTH leaves a blank line after the top instruction lines and before the bottom instruction lines, and indents the body two positions from the leftmost position in the layout column where the instruction lines begin. If the area contains no top or bottom instruction lines, no blank lines are reserved before or after the area body.

NONE does not leave a blank line between instruction lines and the body and does not indent the body with respect to the layout column except if the area is scrollable. If the area is scrollable, a blank line is reserved to provide a line for the scroll information.

VIEW=*dialog-variable-name*

This is a BIN 15 dialog variable which determines the view of the list which appears to the user. Valid values are 0 through one less than the number of views defined. The UIM changes this variable to match the number of the view that is active (where 0 is the first view) when the value is not valid or when the CHGVIEW dialog command is run for the list area.

The first list view (LISTVIEW) tag for the list area defines view 0, the second LISTVIEW tag for the list area defines view 1, and so on for each LISTVIEW tag in the list area.

For more information on list views, see "LISTVIEW (List View)" on page A-103. The VIEW attribute must be specified if more than one LISTVIEW tag is specified for the list area.

ACTOR=NONE | UIM | CALLER.

If ACTOR=NONE is used, the list is not an action list. This attribute is allowed only for display panels. No list action (LISTACT) tags can be specified and the UIM does not do action list processing for the list area.

If ACTOR=UIM is specified, the actions indicated by the LISTACT tags are performed by the UIM and must have the ENTER attribute specified. If ACTOR=CALLER, the actions indicated by the LISTACT tags must be performed by the calling program of the display panel (QUIDSPP) API.

EXTACT=NO | YES

Specifies whether or not an action list has extended action capability. This attribute is allowed only for display panels. With an extended action list, the first line below the column headings is used for an extended action entry. This line contains the action option column, along with input-capable fields for additional list columns.

The user can enter a list action option in the option field for the extended action entry, along with data in the other columns. The action identified by the list action tag is performed using the data entered for the other list columns. The data entered into the extended action entry columns does not have to match the data in an existing list entry.

EXTACT=NO indicates that the list does not have extended action capability.

EXTACT=YES indicates that the list does have extended action capability. This is allowed only if ACTOR=UIM or ACTOR=CALLER is specified on this tag. The action list option column and at least one other list column defined in each list view must be defined for extended action use with EXTACT=YES on the LISTCOL tag. Any LISTACT tags which can operate on the extended action field must have ACTFOR=BOTH or ACTFOR=EXTACTE specified.

When a panel is displayed which has an extended action list but the list is not currently active in the open application, the list is activated by the QUIDSPP API.

| SELECT=NONE | SINGLE | MULTI

| If SELECT=NONE is used, the list is not a selection list. This attribute is allowed only for display panels.

If `SELECT=SINGLE` is specified, the list area is a single-choice selection list. When a single-choice selection list is displayed, a period (.) precedes each list entry. The user can select only one list entry by typing the slash (/) or the country-designated character over the period.

If `SELECT=MULTI` is specified, the list is a multiple-choice selection list. Multiple list entries may be chosen by entering the slash (/) or the country-designated character into the entry field preceding each list entry to select. To deselect a choice, the user should type a blank over, or delete the slash or country-designated character, in the list entry.

A value of 1000 is set in the action variable for the selected list entries.

`ACTOR=NONE` must be specified or made a default on this tag if the value of `SELECT` is either `SINGLE` or `MULTI`. An action variable must be declared for each view of the list.

MAXACTL= 2 | 1 | 3

The maximum number of lines used for list action descriptions. From 1 to 3 lines can be specified; 2 is the default. Only as many list action lines as needed are used. This attribute is allowed only for display panels.

The only time that `MAXACTL=1` would be useful is when there are two or more list actions and you do not want two lines of list actions after national language translation.

When the UIM formats the first two list action lines, it attempts to align the start of each action with the line above or below it. This is done by moving text a few columns to the right on either the first or second line. When the text for the third list action line is formatted, the text for the first two lines is not moved, but the UIM tries to align the text on the third line with the text on the second line.

PARMS=dialog-variable-name

This attribute must name a CHAR 255 dialog variable, used by the UIM to store parameter information for action list processing. This attribute is allowed only for display panels and is only valid when the `ACTOR` attribute on this tag has a value other than `NONE`. It must be used when the list area operates in conjunction with a command line on the same panel. This provides a way for the user to specify parameters that affect action list processing.

The UIM stores the contents of the command line in this variable when the command line contains parameters for action list processing. The UIM sets the variable to blanks before action list processing when the command line does not contain parameter information.

This dialog variable is intended for use in the action string for a CMD dialog command specified on the `ENTER`, `EXTENTER`, `PROMPT`, or `EXTPROMPT` attribute on the `LISTACT` tag.

Note: This variable only contains command line contents when the command line is interpreted as specifying parameters for action list processing. It does not provide generalized access to the contents of the command line.

HEADSIZE=dialog-variable-name

This dialog variable specifies the number of dialog variables specified on the `COLHEAD` attribute of the `LISTCOL` tag that should be used for the list column headings. This attribute is not allowed if `MAXHEAD` is specified.

This dialog variable can only contain the values 0 through 10, as these are the valid number of lines for heading text. If this dialog variable is not a valid value from 0 through 10, the maximum of 10 is used. When using the dialog variables from the list specified on the `COLHEAD` attribute of the `LISTCOL` tag, the variables are used in the order defined on the `COLHEAD` attribute. This dialog variable must be defined with a `BASETYPE` of 'BIN 15' on the class definition (`CLASS`) tag.

The dialog variables on the `HEADSIZE` attribute and the `COLHEAD` attribute of the `LISTCOL` tag are evaluated like normal dialog variables. It is recommended that you set the `HEADSIZE` dialog variable before calling the `QUIDSPP` API and not change it when changing from one view to another. It is up to the application programmer to not let the list and headings shift up and down on panels.

Optional Text

area-title

The title of the area. If no text is specified, no title line is allocated to the area. The text must appear on the same or next line as the tag, can only contain the reverse text (`RT`) tag, and cannot exceed a maximum length of 55 characters.

Print Formatting Considerations

Printed list areas are formatted like those displayed with the following changes:

- Printing always starts with the first entry in the list.
- For lists which are incomplete at the top, the UIM starts printing with the first entry in the list and does not require the list to be marked complete at the top.
- For lists which are incomplete at the bottom, the UIM formats and prints until it runs out of list entries, then calls the exit program for processing the incomplete list for more entries. In general, the exit program is asked for a large number of list entries, and if the list is not marked complete at the bottom, the exit program is called again for more list entries.
- For layouts greater than one, the UIM formats as many entries as can be printed on one page, then prints that page. If there are not enough entries to fill up a page, the entries are balanced across the layout columns. There is always a minimum of two entries in the first column before putting entries into subsequent columns. This helps the user understand how to read the list. For example, a list with LAYOUT=2 and only two list entries would print as follows:

Column 1	Column 2
xxxxxxx	
xxxxxxx	

For list panels, there must be room for a minimum of two lines of list entries on a page besides the column headings. If two lines of list entries do not fit on a page, a page eject occurs and the list entries are printed on the next page. The following example would need to fit on one page, or a new page would be used.

Column 1	Column 2
xxxxxxx	xxxxxxxxx
xxxxxxx	xxxxxxxxx

List column headings and group headings are repeated on each page if the list area is continued onto another page.

Example 1: List Area

This example shows an action where the UIM performs the action requested by the user.

UIM Source

```
:listdef name=outflist
      vars='opt fil nbr usr pri pg sts co'.
:panel topsep=space
      ...
      .Output Files
:~list depth='*'
      listdef=outflist
      maxhead=2
      actor=uim
      parms=pvar.
:topinst.Type options, press Enter.
:~listact
      enter='CMD CHGSPLFA FILE(&FIL.)'
      enter='JOB(&USR./&SPID.) SPLNBR(&NBR.) &PVAR.'
      help=opt2
      option=2.2=Change
:~listact
      enter='CMD CNLSPLF FILE(&FIL.)'
      enter='JOB(&USR./&SPID.) SPLNBR(&NBR.)'
      help=opt4
      option=4.4=Cancel
:~listact
      enter='CMD DSPSPLF FILE(&FIL.)'
      enter='JOB(&USR./&SPID.) SPLNBR(&NBR.)'
      help=opt5
      option=5.5=Display
:~listact
      enter='CMD HLDSPFL FILE(&FIL.)'
      enter='JOB(&USR./&SPID.) SPLNBR(&NBR.)'
      help=opt7
      option=7.7=Hold
:~listact
      enter='CMD RLSSPLF FILE(&FIL.)'
      enter='JOB(&USR./&SPID.) SPLNBR(&NBR.)'
      help=opt8
      option=8.8=Release
:~listcol var=opt
      usage=inout
      maxwidth=6
      help=hopt.Opt
:~listcol var=fil
      usage=out
      maxwidth=10
      help=hfil.File
:~listcol var=nbr
      usage=out
      maxwidth=6
      help=hnbr.Nbr
:~listcol var=usr
```



```

        usage=out
        maxwidth=10
        help=huser.User
: listcol var=pri
        usage=out
        maxwidth=6
        help=hpri.Pty
: listcol var=pg
        usage=out
        maxwidth=8
        help=hpg.Pages
: listcol var=sts
        usage=out
        maxwidth=10
        help=hsts.Status
: listcol var=co
        usage=out
        maxwidth=10
        help=hco.Copies
: listview layout=1
        cols='opt fil nbr usr pri pg sts co'.
: elist.
: cmdline size=short.Parameters or command:
: epanel.

```

Results

[illegible]

Example 2: List Area with Three Layout Columns

This example shows a list area where three entries appear in each row of the display.

UIM Source

```
:listdef name=dist
    vars='name node'.
:panel panel-attributes.Distribution
:list listdef=dist
    depth=8
    maxhead=1.
:listcol var=name
    usage=inout
    maxwidth=10
    help=hxyy1.Name
:listcol var=node
    usage=inout
    maxwidth=10
    help=hxyy2.Node
:listview layout=3
    cols='name node'.
:elist.
:epanel.
```

Results

[illegible]

Example 3: List Area with List Column Groups

This example shows how list columns can be grouped together.

UIM Source

```
:listdef name=auth
    vars='user oper mgmt exist'
    vars='read add update delete'.
:panel panel-attributes.User Authorizations
:list listdef=auth
    depth='*'
    maxhead=3.
:listcol var=user
    usage=out
    maxwidth=10
    help=huser
    .User Name
:listarp col=objrights
```

LIST Tag

```

help=hobjaut.Object Rights
:listcol var=oper
      usage=out
      maxwidth=7
      .Oper
:listcol var=mgmt
      usage=out
      maxwidth=7
      .Mgmt
:listcol var=exist
      usage=out maxwidth=7
      .Exist

:elistgrp.
:listgrp col=dtarights
      help=hdttaut.Data Rights
:listcol var=read
      usage=out
      maxwidth=7
      .Read
:listcol var=add
      usage=out
      maxwidth=7
      .Add
:listcol var=update
      usage=out
      maxwidth=7
      .Upd
:listcol var=delete
      usage=out
      maxwidth=7
      .Dlt

:elistgrp.
:listview layout=1
      cols='user objrights dtarights'
:elist.
:epanel.

```

Results

[illegible]

Example 4: Dynamic List Column Heading Formatting

This example shows how the column headings are contained in dialog variables.


UIM Source

```
:listdef name=xmp4
    vars='var1 var2 var3'.
:panel panel-attributes.
Example of Dynamic Column Headings
:list listdef=xmp4
    depth='*'
    headsiz=colhsiz.
:listcol var=var1
    usag=inout
    maxwidth=10
    colhead='A B C D E F'.
:listcol var=var2
    usag=inout
    maxwidth=14
    colhead='G H'.
:listcol var=var3
    usag=inout
    maxwidth=10
    colhead='I J K L'.
:listview layout=1
    cols='var1 var2 var3'.
:elist.
:epanel.
```

Note: In this example, A B C D E F G H I J K and L are dialog variables that would each be set to one line of column heading text. In the screen that follows, the actual text appears instead of the dialog variable names. *COLHSIZE* is also a dialog variable, and in this example it is set equal to 4.

[illegible]

LISTACT (List Action)



The list action (LISTACT) tag defines an operation which takes place on individual items of a list. This tag is allowed only for display panels. Options entered by a user are not actually run until an Enter or Prompt function key is pressed, allowing the user to select several list items while using the Page Up or Page Down keys.

If ACTOR=UIM is specified on the list area (LIST) tag, all actions indicated by LISTACT tags are performed by the UIM. These actions must have the ENTER attribute specified, and may also have the PROMPT and USREXIT attributes specified. If ACTOR=CALLER is specified on the LIST tag, the actions are handled by the program which called the Display Panel (QUIDSPP) API. In this case, none of the following attributes can be specified on the LISTACT tag:

- CONFIRM
- ENTER
- PROMPT
- USREXIT
- EXTENTER
- EXTPROMPT
- NOEXT
- EXTMSGID
- EXTMSGF

There is no way to have the UIM perform some actions and the calling program perform others.

When the CMD dialog command is used as the action performed for the extended action entry in an action list, the command text should be a Control Language command, not a System/36 Environment OCL command. The value *N is substituted in the command text for any dialog variable from the extended action entry that has a blank value. An exception to this is when NOEXT=MSG is specified on this tag, indicating that the command should not be submitted when any of the values for the extended action entry are blank. This consideration applies to the following attributes of this tag:

- ENTER
- PROMPT
- EXTENTER
- EXTPROMPT

Required Attributes

HELP=*help-module-name*

Identifies the associated help module for this list action. The online help information for all actively-conditioned list actions is always added to the online help information for the action column.

OPTION=number

The value associated with the option selected for this item in the list. The value must be an integer value in the range of 1 through 999. The action field variable must be defined with a BASETYPE of ACTION on the class definition (CLASS) tag. The values of the action field are automatically limited to the valid options by the UIM. An error occurs when the user enters a number in the action field for which there is no active LISTACT tag.

Optional Attributes

ACTFOR=BOTH | LISTE | EXTACTE

Indicates whether the list action defined is allowed for the existing list entries, the extended action entry, or both. The default is BOTH.

If LISTE is specified, the action defined is valid only in the action fields associated with the existing list entries on the display.

EXTACTE indicates that the action defined is valid only in the action field for the extended action entry. For example, ACTFOR=EXTACTE might be used for Option 1=Create, because the create option is not allowed for an existing entry.

CONFIRM=panel-name

The confirmation panel displayed before the list action is performed. The confirmation panel must give the user the option to confirm or not confirm the list action. If the action is confirmed, the appropriate actions from the ENTER, EXTENTER, and USREXIT attributes of this tag are performed. If the action is not confirmed, none of those actions are performed.

The actions coded on the PROMPT and EXTPROMPT attributes of this tag are not confirmed. The prompt screen that results from the PROMPT and EXTPROMPT actions serves as the confirmation panel, allowing users to change their minds and cancel the action. The confirmation panel must be another panel defined within this panel group.

The CONFIRM attribute is only allowed when ACTOR=UIM is specified in the LIST tag.

When the CONFIRM attribute is specified, EXTACT=YES is specified on the LIST tag and if ACTFOR=BOTH or ACTFOR=EXTACTE is spec-

ified on this tag, NOEXT=MSG must also be specified on this tag.

A maximum of 20 different LISTACT tags for a single action list may specify the CONFIRM attribute. This does not impose any restriction on the number of list entries that any one of the actions may be applied to.

For more information on required and recommended conventions for this attribute, see "Confirmation Panel Requirements" on page A-92 and "Confirmation Panel Conventions" on page A-92.

ENTER='action-text'

Specifies the action occurring when the list action is requested through the ENTER dialog command. This attribute is required if ACTOR=UIM is specified on the LIST tag. The valid forms of action-text are:

- *'CALL program-reference'*
For a description of the interface between the UIM and the exit program for an action list option, see *System Programmer's Interface Reference*.
- *'CMD command-string'*
Any dialog variable name in the command string must be preceded by an ampersand and should be ended with a period to denote variable substitution.

For a description of each of these actions, see Appendix B, "UIM Dialog Commands" on page B-1.

This attribute is repeatable, allowing the construction of long command strings.

The PARMS attribute on the LIST tag identifies a dialog variable that can be substituted into a command string on the CMD dialog command. Additional functions are provided for list actions which use the CMD dialog command. When parameters from the command line are substituted into a command string, the parameters from the command line override the same parameter defined in the command string if the parameter in the command string is preceded by the "?<" or "???" selective prompting characters.

This function allows a prompt for a command to show the parameter values from the command line, or to show the current parameter values for the object when an overriding

LISTACT Tag

parameter is not on the command line. When the "?<" or "???" selective prompting characters are used, it is your responsibility to have the current parameter values substituted into the command string.

EXTENTER='action-text'

Specifies the action occurring when the list action for the extended action field is requested through the ENTER dialog command. This attribute is not allowed when ACTFOR=LISTE is specified on the LISTACT tag, or when EXTACT=NO is specified on the LIST tag.

The syntax and usage of this attribute is the same as the ENTER attribute for this tag. If the EXTENTER attribute is not specified, the action specified on the ENTER attribute is used.

PROMPT='action-text'

Specifies the action occurring when the list action is requested through the PROMPT dialog command. The valid forms of action text are:

- *'CALL program-reference'*
For a description of the interface between the UIM and the exit program for an action list option, see *System Programmer's Interface Reference*.
- *'CMD command-string'*
Any dialog variable name in the command string must be preceded by an ampersand to denote variable substitution.

For a description of these actions, see Appendix B, "UIM Dialog Commands" on page B-1.

This attribute is repeatable, allowing the construction of long command strings.

The PARMS attribute on the LIST tag identifies a dialog variable that can be substituted into a command string on the CMD dialog command. Additional command submission support is activated for list actions which use the CMD dialog command. When parameters from the command line are substituted into a command string, the parameters from the command line override the same parameter defined in the command string if the parameter in the command string is preceded by the "?<" or "???" selective prompting characters.

This function allows a prompt for a command to show the parameter values from the command line, or to show the current parameter values for the object when an overriding parameter is not on the command line. When the "?<" or "???" selective prompting characters are used, it is your responsibility to have the current parameter values substituted into the command string.

EXTPROMPT='action-text'

Specifies the action occurring when the list action for the extended action field is requested through the PROMPT dialog command. The EXTPROMPT attribute is not allowed when ACTFOR=LISTE is specified on the LISTACT tag, when EXTACT=NO is specified on the LIST tag, or when the PROMPT attribute is not specified on this tag.

The syntax and use of this attribute is the same as for the PROMPT attribute on this tag. If the EXTPROMPT attribute is not specified, the action specified on the PROMPT attribute is used.

NOCMD=ENTER | PROMPT

Specifies the action the UIM performs for the ENTER dialog command when the command line is blank.

ENTER indicates that the action on the ENTER attribute of this tag should be performed.

PROMPT indicates that the action on the PROMPT attribute of this tag should be performed.

This allows you to have a command prompted when the command line is empty, but not prompted if the command line contains parameters.

For an explanation of how this attribute interacts with the NOEXT attribute of this tag, see Table A-10 on page A-91.

NOEXT=ENTER | PROMPT | MSG

Specifies the action the UIM should perform for the ENTER dialog command when one or more of the input fields on the extended action entry are blank.

ENTER indicates that the action on the EXTENTER attribute of this tag should be performed.

PROMPT indicates that the action on the EXTPROMPT attribute of this tag should be performed.

MSG indicates that no action should be performed and that the message specified on the EXTMSGID attribute of this tag should be sent to the user. When MSG is specified, the EXTMSGID attribute is required.

For an explanation of how this attribute interacts with the NOCMD attribute, see Table A-10. This table shows how the NOCMD and NOEXT attributes operate when the command line is blank and one or more of the input fields on the extended action entry are blank.

Table A-10. NOCMD and NOEXT Attribute Interaction

NOCMD	NOEXT	Result
ENTER	ENTER	EXTENTER attribute is used
PROMPT	ENTER	EXTPROMPT attribute is used
ENTER	PROMPT	EXTPROMPT attribute is used
PROMPT	PROMPT	EXTPROMPT attribute is used
ENTER	MSG	EXTMSGID message is displayed
PROMPT	MSG	EXTMSGID message is displayed

This table is used only when all of the following are true:

1. A list action option is being processed for the extended action entry.
2. The command line is blank.
3. One or more of the input fields on the extended action entry are blank.

USREXIT='CALL program-reference'

Specifies the list exit program the UIM calls to update or delete this list entry after the action defined in either the ENTER, EXTENTER, PROMPT, or EXTPROMPT attribute of this tag is performed. The program is passed information that includes an indication of whether the option succeeded or failed.

For a description of the CALL dialog command, see Appendix B, "UIM Dialog Commands" on page B-1.

For a description of the interface between the UIM and the program for an action list, see the *System Programmer's Interface Reference*, SC41-8223.

EXTMSGID='message-identifier'

The message identifier of the message displayed when the action defined by this tag cannot be performed because one or more input fields on the extended action entry are blank. This attribute is required when NOEXT=MSG is specified on this tag; it is not allowed otherwise.

EXTMSGF='qualified-message-file-name'

The message file name that contains the message identifier. The attribute is allowed only when the EXTMSGID attribute is specified on this tag. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, this attribute must be specified when the EXTMSGID attribute on this tag is specified.

COND=condition-name

The list action is in effect on the panel only if the condition specified is true. The condition must be defined in the panel group prolog with the condition definition (COND) tag. If the conditions for all LISTACT tags are false, the action column still appears on the display, but no option numbers are valid. It is up to you to ensure that some options remain valid for the list.

AVAIL=condition-name

The list action is available only if the condition specified evaluates to true. The condition must be defined in the panel group prolog with the COND tag.

Unavailable actions are displayed with an asterisk (*) overlaying the first part of the action description. Online help information is displayed for unavailable list actions.

When the condition is true, the list action is available. When the condition is false, the list action is not available. Any condition specified on the COND attribute takes precedence over this attribute.

AVLMSGID=message-identifier

The message identifier of the message displayed when a number is entered and is not available as specified by the AVAIL attribute of this tag. This attribute is allowed only when the AVAIL attribute is specified.

If this attribute is not specified, the UIM displays a default message stating that the option number is not currently available.

AVLMSGF= *'qualified-message-file-name'*

The message file name that contains the message identifier. The attribute is allowed only when the AVLMSGID attribute of this tag is specified. If the DFTMSGF attribute is not specified on the PNLGRP tag, this attribute must be specified when the AVLMSGID attribute on this tag is specified.

Optional Text

action-description

The text shown as part of the top instructions for the list area. If no text is supplied, none is listed in the instruction part of the list area for this action. The text must appear on the same or next line as the tag and can only contain the reverse text (RT) tag.

The instruction line is formed by concatenating the text from the various list actions, separated by three spaces. If the text does not fit on the rest of a line, it is placed on the next line.

Confirmation Panel Requirements

The panel named on the CONFIRM attribute of this tag must follow these conventions:

- The ENTER attribute on the display panel (PANEL) tag of the confirmation panel must have 'RETURN 100' coded. This indicates to the UIM that the action is confirmed by the user.
- No ACTION attribute on a key list item (KEYI) tag can be assigned to the RETURN dialog command, because the UIM is handling the display of the panel and is not able to interpret the returned value.
- The confirmation panel must have a list area.
- The list used as the confirmation list must not be the same list displayed in the action list panel.
- The confirmation panel must not have a menu bar, action list, command line, menu area, or a menu bar.

Confirmation Panel Conventions

The panel named in the CONFIRM attribute of this tag should follow these conventions:

- It should have title text and top instructions to describe the panel.
- It should have a single list area with a list definition containing the same (or a subset of) the columns defined in the original action list.
- The list should be scrollable.
- If the action list has multiple views, the confirmation list should also have multiple views and the same dialog variable should be used for the view variable on both lists. The confirmation panel should have a function key defined for the CHGVIEW dialog command. When the same view variable is used for both lists, it allows a change view operation on the confirmation panel to change the view of the action list panel when it is redisplayed.
- It should have function key definitions for the ENTER, CANCEL, PAGEDOWN, PAGEUP, HELP, and PRINT dialog commands.
- If a general exit program is defined, it should avoid making changes to the action list and avoid changing condition values that affect the redisplay of the original action list panel.
- The list used on the confirmation panel should not be used on anything but a confirmation panel, because the UIM deletes and changes the contents of that list. If multiple confirmation panels are used within a UIM application, they use the same list definition.
- Most of the help information for the action list panel can be used for the confirmation panel, but separate help information should be provided for the action column and the extended help.
- The class definition for the list option variable defined with a BASETYPE of ACTION on the CLASS tag should have a WIDTH attribute on the CLASS tag to accommodate the largest list action option on the action list panel. For example, if the largest option number on the action list panel is 12, WIDTH=2 should be specified on the class definition for the action variable. This ensures that the option number is displayed in the same position under the

column heading on the confirmation panel as it was on the action list panel.


UIM Source

```
:listact option=2
    help='option/2'
    enter='CALL CHGPGM'
    .2=Change
:listact option=4
    help='option/4'
    enter='CALL DLTPGM'
    confirm=CONFDLT
    .4=Delete
:listact option=5
    help='option/5'
    enter='CALL DSPPGM'
    .5=Display
```

Example: List Actions

This example shows how the action options on a display are defined.


Results




Type choices, press Enter.
2=Change 4=Delete 5=Display

LISTCOL (List Column)

Syntax for Display Panels



Syntax for Print Panels



The list column (LISTCOL) tag defines a column that may belong to any of several list views. This tag is allowed for display panels and print panels. It specifies the dialog variable, whether the field allows the user to enter data or is for output only, the column width, and the column heading.

Required Attributes

VAR=list-object-variable-name

The name of the variable from the underlying list object to display in this column.

MAXWIDTH=column-width | '*'

The maximum width of the column. The width may allow for translation of the column heading into other languages. The minimum

size for a column heading is four characters. Specification of a width longer than that defined in the class definition (CLASS) tag allows more room for the formatting of column headings, but does not allow more data to be entered into the field. Specification of a width shorter than the class width on the CLASS tag is allowed only for CHAR or IGC variables, and is not allowed for input columns.

If '*' is coded, the remainder of the area width is used for the column, and values in that column can be truncated. Only one column may have '*' coded. A warning message is put in the compiler listing if the column with '*' specified is not the last column of all views. A two- to five-character separator is maintained between columns.

USAGE=OUT | INOUT

The display use of the column. This attribute is required for display panels, but is optional for print panels.

USAGE=OUT defines an output data column. OUT indicates that the variable displayed is for output only and cannot be changed by the user.

USAGE=INOUT defines a data entry column. INOUT indicates that the variable is for data entry and can be changed by the user. USAGE=INOUT fields are not allowed for print panels, but are required for the action column of an active list.

Optional Attributes**HELP=***help-module-name*

Identifies online help information which explains the purpose of the column in this list. This attribute is allowed only for display panels. The help module name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see “Name Syntax” on page A-4.

The HELP attribute is not allowed if this column is part of a list column group defined by the list group (LISTGRP) tag, but is required if the column is not part of a group.

COL=*column-identifier*

The identifier of the column, which can be referred to in the COLS attribute on the list view (LISTVIEW) tag. If the identifier is not supplied, it defaults to the dialog variable name specified on the VAR attribute of this tag. These names are in a separate name space from all other names and are meaningful only within the list area, not to the panel group.

A list column identifier cannot be specified and no default column name is assumed if the column is part of a list column group defined by the LISTGRP tag.

NAME=*list-column-name*

The name associated with the column. For more information on the rules for naming, see “Name Syntax” on page A-4.

This name can be used with the Add Pop-Up Window (QUIADDPW) API to position a

window near this list column. This attribute is allowed only for display panels.

If the list column is part of a list column group defined by the LISTGRP tag and both the LISTCOL and LISTGRP tags have the NAME attribute specified, the list column name is set in the dialog variable specified on the CSRNAME attribute of the display panel (PANEL) tag when the cursor is anywhere in the list column. The list group name is set for the CSRNAME attribute on the PANEL tag when the cursor is positioned between columns or on an unnamed list column within the named list group. For a description of the CSRNAME attribute, see “PANEL (Display Panel)” on page A-120.

JUSTIFY=LEFT | RIGHT | START | END

Indicates whether the dialog variable values should be left-justified or right-justified within the list column. If the ALIGN attribute of this tag is omitted, the default right-justifies values for numeric dialog variables and left-justifies nonnumeric dialog variables.

Leading blanks are preserved when the dialog variable is left-justified. Right-justification strips all trailing blanks. The UIM rules for editing a numeric dialog variable produces a displayable value which does not contain any leading blanks.

A common case where you might want to override the alignment default is for a column of values whose BASETYPE is defined as numeric on the CLASS tag, but whose displayable values are sometimes special values generated through a translation list. For more information on translation lists, see “TL (Translation List)” on page A-152.

START is a synonym for LEFT and END is a synonym for RIGHT.

EXTACT=NO | YES

Specifies whether or not this list column is input-capable for the extended action entry. This attribute is allowed only for display panels.

EXTACT=NO specifies that this list column does not have an input-capable field in the extended action entry.

EXTACT=YES specifies that this list column does have an input-capable field in the extended action entry. When EXTACT=YES is

LISTCOL Tag

specified on the list area (LIST) tag, EXTACT=YES must be specified on at least two columns in each list view, including the action column.

Any column with EXTACT=YES specified must be in every view of the list area.

PROMPT='action-text'

The action occurring when F4=List is requested through the PROMPT dialog command. This attribute is allowed only for display panels. This attribute is not allowed for a dialog variable defined with a BASETYPE of ACTION on the CLASS tag or for any USAGE=OUT list columns on this tag. The valid forms of action text are:

- 'CALL program-reference'
For a description of the interface between the UIM and the exit program for a cursor-sensitive prompt, see the *System Programmer's Interface Reference*, SC41-8223.
- 'RETURN positive-integer'

For a description of these actions, see Appendix B, "UIM Dialog Commands" on page B-1.

DSPVALUE='dialog-variable-name'

The dialog variable containing the current data entered in the list entry which contains the cursor. This attribute is allowed only for display panels and when the PROMPT attribute is coded on this tag. This variable is updated regardless of whether or not the variable pool is updated. The variable pool is updated based on the VARUPD attribute of the key item (KEYI) or pull-down field choice (PDFLDC) tag. This updating is independent of the normal updating of the variable pool.

The dialog variable specified must be defined on the CLASS tag as a CHAR or IGC variable whose length is the same as the width of the dialog variable specified on the VAR attribute of this tag. No translation processing or validity checking is performed for the value before it is placed in this variable. Character set and code page conversion is performed for this variable if the class of the variable named on the VAR attribute of this tag specifies that the character set and code page conversion should be performed.

COLHEAD='dialog-variable-name-list'

A list of dialog variables separated by blanks, specifying the column heading placed above the list items in the list area. Up to ten dialog variables can be specified. These dialog variables must have a BASETYPE of CHAR or IGC specified on the CLASS tag, and must have a width greater than or equal to the class width of the dialog variable specified on the VAR attribute of this tag, and less than or equal to the width specified on the MAXWIDTH attribute of this tag. All variables specified on a single COLHEAD attribute must be defined with the identical class.

Each dialog variable is used as a line of column heading text. The UIM does no aligning or justification on the contents of these dialog variables.

If this attribute is used, column heading text cannot be specified after the period for this tag, the MAXHEAD attribute must not be specified on the LIST tag, but the HEADSIZE attribute of the LIST tag must be specified.

DISPLAY=YES | NO

Indicates whether or not the fields in the list column are visible when the panel is displayed. This attribute is allowed only for display panels. YES indicates that the fields in the list column are visible.

NO indicates that the fields in the list column are not visible. NO can only be specified for a column in the list when USAGE=INOUT is specified on this tag and ACTOR=NONE is specified on the LIST tag.

AUTOSKIP=YES | NO

Indicates whether or not the cursor should automatically move to the next input field when data is entered in the last position of the list column field. This attribute is allowed only for display panels. YES is the default.

YES indicates that the cursor automatically moves to the next input field.

NO indicates that the cursor does not automatically move to the next input field. NO can only be specified for a column in the list when USAGE=INOUT is specified on this tag and ACTOR=NONE is specified on the LIST tag.

Optional Text

column-heading

The column heading placed above the column in the reserved part of the list area. If no column heading or the COLHEAD attribute is specified, no column heading is displayed.

The text may appear on more than one line and can only contain the reverse text (RT) tag.

Each word of the column heading is placed on a new line. If multiple words are necessary in a line of the column heading, they must be enclosed in apostrophes (''). Each word or quoted string must fit within the maximum column width defined by the MAXWIDTH attribute of this tag. The maximum number of words or quoted strings allowed is specified by the MAXHEAD attribute on the LIST tag. Column headings are not allowed if MAXHEAD=0 is used for the list area.

Column headings are justified according to the JUSTIFY attribute of this tag only if they are specified as text. No justification is done when the COLHEAD attribute is specified on this tag.

If no column heading text or COLHEAD attribute is specified on any LISTCOL tag for the area, no lines are reserved on the display for heading information.

Formatting Considerations

When the width of the column data is less than the width of the column heading text, the column data is centered under the column heading text. If the data does not center evenly under the heading, the additional space is placed on the

right for JUSTIFY=LEFT and on the left for JUSTIFY=RIGHT. The following example shows all three situations:

Center Data	Align Left	Align Right
xxxxxxx	xxxxxxx	nnnnnnnn
xxxxxxx	xxxxxxx	nnnnnnnn
xxxxxxx	xxxxxxx	nnnnnnnn
xxxxxxx	xxxxxxx	nnnnnnnn


When the width of the column data is greater than the width of the column heading text, the column heading text is adjusted to the left for JUSTIFY=LEFT and to the right for JUSTIFY=RIGHT. The following example shows these situations:

Align Left	Align Right
xxxxxxxxxxxx	nnnnnnnnnnnn
xxxxxxxxxxxx	nnnnnnnnnnnn
xxxxxxxxxxxx	nnnnnnnnnnnn
xxxxxxxxxxxx	nnnnnnnnnnnn

If the column heading text requires more than one line, the shorter lines of text are centered with respect to the longest line. If the shorter lines do not center evenly under the longer lines, the additional space is on the right for JUSTIFY=LEFT and on the left for JUSTIFY=RIGHT. The following example shows all situations:

	Line Up Head	Line Up Head	Line Up Head	Line Up Head
Line Up Right	Right	Right	Right	Left
nnnnnnnn	nnnnnnnn	nnn	nnnnnnnnnn	xx
nnnnnnnn	nnnnnnnn	nnn	nnnnnnnnnn	xx
nnnnnnnn	nnnnnnnn	nnn	nnnnnnnnnn	xx
nnnnnnnn	nnnnnnnn	nnn	nnnnnnnnnn	xx

LISTDEF (List Definition)



The list definition (LISTDEF) tag defines UIM lists which are data structures maintained by the UIM. These lists contain the data for list areas presented on the display. UIM lists consist of a variable number of rows. Each row contains one or more columns, and each column in the row contains a copy of one dialog variable value. These lists are manipulated by the program using the UIM application programming interfaces (APIs). Lists may be shared among panels which contain list areas.

Required Attributes

NAME=*list-name*

The name of the list object. This name must be unique within the panel group. For more information on the rules for naming, see “Name Syntax” on page A-4.

VARS=*'dialog-variable-list'*

The list of up to 50 variables which make up the columns of the list. All dialog variables in this list must be previously defined using the variable definition (VAR) tag in this panel group. Not all of these variables need to be displayed in a view defined with the list view (LISTVIEW) tag. The variable names in the list are separated by blanks.

The UIM automatically determines what column is used for action list or selection list processing by identifying the variable specified on the VARS attribute and defined with a BASETYPE of ACTION on the class definition (CLASS) tag. An action column is required for each list view when an ACTOR or SELECT value other than NONE is specified, or when SELECT=SINGLE or MULTI is specified on the

list area (LIST) tag. Only one column of a list may be specified as an action column.

Optional Attributes

CHGVAR=*dialog-variable-name*

Specifies that any list entry values entered by the user must be compared to values already in the list entry. This attribute also indicates where the comparison result should be stored. The dialog variable specified must be one of the variables listed on the VARS attribute of this tag, and must be defined with a BASETYPE of CHAR 1 on the CLASS tag.

List values are compared using the internal form of each dialog variable rather than its display form. If any values in the list entry are changed, the list value associated with the dialog variable specified on this attribute is set to '1'. If all the new list values are equal to the old list values, no special processing is performed; the dialog variable specified for this attribute is not changed.

Note: The dialog variable specified on this attribute is set to '1' each time the user changes the list entry, scrolls the list, or uses some other function key. The list value associated with the dialog variable specified on this attribute is set to '1' twice if a value in the list is changed, the list is scrolled, scrolled back again to the original position, and the list entry is changed back to its original value.

An application program can use the list value for the dialog variable specified on this attribute to determine which list entries are changed by the user. The application is responsible for setting and resetting the list entry value to something other than '1'. It

does this by updating the list entry after the input values are processed and before the list is redisplayed to make the comparison reliable.

MSGID=*message-identifier*

The message identifier of a message that is displayed to the user when the UIM list is empty. If no message identifier is specified with either the MSGID or MSGIDVAR attribute on this tag, no message is displayed when the list is empty. The MSGID and the MSGIDVAR attributes cannot both be used on the same LISTDEF tag.

MSGIDVAR=*dialog-variable-name*

A dialog variable containing the message identifier of a message displayed to the user when the UIM list is empty. The dialog variable specified must be defined with a BASETYPE of 'CHAR 7' on the CLASS tag. If no message identifier is specified with either the MSGID or MSGIDVAR attribute on this tag, no message is displayed when the list is empty. The MSGID and the MSGIDVAR attributes cannot both be used on the same LISTDEF tag.

MSGF=*'qualified-message-file-name'*

The message file name containing the message identifier specified on the MSGID or MSGIDVAR attribute. The attribute is allowed only when the MSGID or MSGIDVAR attribute is specified on this tag. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, this attribute must be specified when the MSGID or MSGIDVAR attribute on this tag is specified.

PRTFLAG=*dialog-variable-name*

Specifies the name of a dialog variable in the list definition containing a character printed on the first character of each list entry. For each list entry printed, the character stored in the dialog variable is printed on the first column. The dialog variable specified must be one of the variables listed on the VARS attribute of this tag, and must be defined on the CLASS tag with a BASETYPE of CHAR 1 and a width of 1. This attribute is intended to be used for output listing applications where a special character needs to be printed in column one.

EMPHASIS=*'dialog-variable-emphasis-list.'*

The list of dialog variables containing the emphasis or color associated with each of the variables listed on the VARS attribute of this

tag. The number of items in the list must be the same as the number of dialog variables specified on the VARS attribute. Only one emphasis is allowed for each variable listed, but a particular emphasis value may apply to more than one variable. A value of '*' should be specified to indicate that normal emphasis should be used with the corresponding variable listed on the VARS attribute, and also used for list columns not displayed in any list view.

The dialog variables specified on this attribute cannot be one of the variables listed on the VARS attribute of this tag.

Each variable in the list must be defined with a BASETYPE of CHAR 1 on the CLASS tag. When an entry is added to the list or an existing entry is updated, the values for these variables determine the emphasis used when that entry is displayed. The following table shows the values that can control the emphasis.

Table A-11. Emphasis Values		
Value	Output Field	Input Field
0	Normal	Normal
1	Emphasize	Emphasize
2	De-emphasize	Normal

Normal and de-emphasis are the same on a monochrome device.

If a dialog variable listed in this attribute has a value specified other than one of the above values, normal emphasis is used. If this attribute is not specified, normal emphasis is used.

This attribute does not control emphasis during printing.

PROTECT=*'dialog-variable-usage-list'*

The list of dialog variables containing the value used to override the USAGE attribute of the list column (LISTCOL) tag for each of the variables listed on the VARS attribute of this tag. The number of items in the list must be the same as the number of dialog variables specified on the VARS attribute. Only one protection value is allowed for each variable listed, but a particular protection value may apply to more than one variable.

LISTDEF Tag

A value of '*' should be specified to indicate that there is no override for the USAGE attribute on the LISTCOL tag for the corresponding variable listed on the VARS attribute. A value of '*' is also used for list columns not displayed in any list view.

The dialog variables specified on this attribute cannot be one of the variables listed on the VARS attribute.

Each variable in the list must be defined with a BASETYPE of CHAR 1 on the CLASS tag. When an entry is added to the list or an existing entry is updated, the values for these variables determine the protection whenever that entry is displayed. This attribute overrides the USAGE attribute from the LISTCOL

tag. The valid values for the dialog variables specified on this attribute are as follows:

- '1' The variable use is output-only.
- '0' The use is controlled by the USAGE attribute on the LISTCOL tag.

Changing a list option field for an action list or selection list to output-only does not affect list processing. If the action field contains an option number or selection value but is displayed as output-only, the option is processed.

If a dialog variable listed in this attribute is not specified or has a value specified other than '1' or '0', the use is controlled by the USAGE attribute of the LISTCOL tag.

LISTGRP (List Column Group)

Syntax for Display Panels

```

▶▶:LISTGRP—COL=column-identifier—HELP=help-module-name————▶
|NAME=list-column-group-name|. |group-heading|:ELISTGRP.————▶▶

```

Syntax for Print Panels

```

▶▶:LISTGRP—COL=column-identifier—. |group-heading|:ELISTGRP.————▶▶

```

The list column group (LISTGRP) tag groups columns in a list area together under a single heading that applies to all the columns. This tag is allowed for display panels and print panels. Columns may be defined within the list area that do not belong to any list column group. This tag cannot be used in a list area if MAXHEAD=0 is specified on the list area (LIST) tag for the area.

There are some restrictions on the kinds of columns that can exist within a column group.

- The action column of the list cannot be in a column group.
- All or none of the columns can have column headings.
- Column groups cannot be nested.
- At least one column must be defined within a column group.

Required Attributes

COL=*column-identifier*.

The identifier of the column group, which is referred to in the COLS attribute on the list view (LISTVIEW) tag. These names are in a separate name space from all other names and are meaningful only within the list area, not within the panel group.

HELP=*help-module-name*

Identifies online help information which explains the purpose of the column group in this list. This attribute is required for display panels; it is not allowed for print panels. The help module name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter.

For more information on the rules for names, see “Name Syntax” on page A-4.

Optional Attribute

NAME=*list-column-group-name*

The name associated with the group. This attribute is allowed only for display panels. For more information on the rules for naming, see “Name Syntax” on page A-4. This name can be used with the Add Pop-Up Windows (QUIADDPW) API to position a window near this list column group.

Optional Text

group-heading

The group heading text placed above the column group in the heading part of the list area. This heading must fit on one line over the columns in the group. It is centered over the group of columns and has a graphic indication of the number of columns over which it spans. The headings of the columns in a column group may span different numbers of lines. The group heading appears on the line immediately above the tallest column heading of the group.

No column in a column group may have MAXWIDTH='*' specified on the list column (LISTCOL) tag. The columns and the separators between the columns define the width allocated for the group heading. The group heading must be no longer than this width.


If no column headings are specified on any of the columns of the group, the group heading appears immediately above the column data.

LISTGRP Tag

The text must appear on the same or next line as the tag and can only contain the reverse text (RT) tag.

Note: Group heading text cannot be specified if dialog variables are used for column headings by specifying the COLHEAD attribute on the LISTCOL tag.

LISTVIEW (List View)



The list view (LISTVIEW) tag defines one of the views of a list presented in a list area. This tag is allowed for both display panels and print panels.

Multiple list views can be defined in an area and can be changed using the CHGVIEW dialog command, which can be assigned to a function key or to a pull-down choice. If there is more than one list view on the panel and the CHGVIEW dialog command is performed, the list area with the cursor in it changes views.

The view may also be established in a program by changing the value of the dialog variable specified on the VIEW attribute on the list area (LIST) tag. Views are numbered consecutively from zero to one less than the number of LISTVIEW tags defined in this area. The first LISTVIEW tag for the list area defines view zero, the second LISTVIEW tag defines view one, and so on for each LISTVIEW tag in the list area.

If the **ACTOR** attribute on the **LIST** tag has a value other than **NONE**, the action column of the list must appear in all views of the list area for the panel. If the **SELECT** attribute on the **LIST** tag has a value other than **NONE** or **MULTI**, the action column of the list must appear in all views of the list area.

Although multiple views can be defined for a print panel, only the view identified by the VIEW attribute on the LIST tag is printed when the Print Panel (QUIPRTP) API is called. To print more than one view, the QUIPRTP API must be called multiple times, updating the view dialog variable between each call to QUIPRTP.

Required Attribute

COLS=*'column-identifier-list'*

A list of column or column group identifiers which are separated by blanks. This list identifies columns and groups that are part of this view.

All variables used in this view must be distinct.

Optional Attribute

LAYOUT=1 | *number-of-layout-columns*

Indicates whether more than one set of columns should be presented on the display at one time. If the width of columns defined by the COLS attribute of this tag is small, it may be possible to position more than one set of the columns on the display or page.

The format used for multiple-column layout divides the entire display or page width into layout columns of equal size, with a separator of at least three characters between layout columns. All list columns specified on the COLS attribute of this tag must fit within a single layout column.

For all panels with WIDTH=132 on the display panel (PANEL) or print panel (PRTPNL) tags, a value from 1 through 10 is allowed. For panels with WIDTH less than 132, a value from 1 through 6 is allowed.

The following tables show the available column width and what positions are used for each layout column, depending on the value of the LAYOUT attribute. The first table applies to all panels with WIDTH=80 specified on the PANEL or PRTPNL tags. The second table applies to panels with WIDTH=132 specified.

LISTVIEW Tag

Table A-12. Layout Values for Width=80. Layout column widths and positions for panels with WIDTH=80.

Layout	Layout Width	Layout 1 Column Positions	Layout 2 Column Positions	Layout 3 Column Positions	Layout 4 Column Positions	Layout 5 Column Positions	Layout 6 Column Positions
1	78	2-79					
2	37	2-38	43-79				
3	24	2-25	29-52	56-79			
4	17	2-18	22-38	42-58	62-78		
5	13	2-14	18-30	34-46	50-62	66-78	
6	10	2-11	15-24	28-37	41-50	54-63	67-76

Table A-13. Layout Values for WIDTH=132. Layout column widths and positions for panels with WIDTH=132.

Layout	Layout Width	Layout 1 Column Positions	Layout 2 Column Positions	Layout 3 Column Positions	Layout 4 Column Positions	Layout 5 Column Positions	Layout 6 Column Positions
1	130	2-131					
2	63	2-64	69-131				
3	41	2-42	46-86	90-130			
4	30	2-31	35-64	68-97	101-130		
5	23	2-24	28-50	54-76	80-102	106-128	
6	19	2-20	24-42	46-64	68-86	90-108	112-130

Table A-14. Layout Values for WIDTH=132. Layout column widths and positions for panels with WIDTH=132.

Layout	Layout Width	Layout 7 Column Positions	Layout 8 Column Positions	Layout 9 Column Positions	Layout 10 Column Positions
7	16	97-112			
8	13	66-78	82-94		
9	11	86-96	100-110	114-124	
10	10	80-89	93-102	106-115	119-128

If a WIDTH of less than 80 or a width between 81 and 131 is specified on the PANEL tag, the following algorithm can be used to determine the layout width:

1. Subtract 2 from the width of the panel.
2. Subtract 3*(layout-1) from the result of step 1. This is the total separator space between the layouts.
3. Divide the result of step 2 by the layout; do not round up. This is the layout width.
4. If the remainder from step 3 is greater than (layout-1), the separator between the layouts is 4. Otherwise, the separator space is 3.

LP (List Part)

►►:LP.*list-part-text*◄◄

The list part (LP) tag identifies a comment or an explanation applying to a part of a list. This tag is only allowed in information areas and help areas. It can be placed anywhere within the list.

The text following the LP tag starts at the left margin of the current level of the list. It is not numbered or lettered. When used with the ordered list (OL) tag, the LP tag does not interrupt or increase the ordered sequence.

Example: List Part

This example uses a list part tag to keep the flow of the list from being interrupted.

UIM Source


```
:ol.
:li.First item
:lp.This is a list part.
:li.Second item
:eol.
```

Results

1. First item

This is a list part.
2. Second item

MBAR (Menu Bar)



The menu bar (MBAR) tag defines a menu bar area of a panel. The menu bar appears as the topmost element in a panel and consists of one or more menu bar choices. When the user positions the cursor at a menu bar choice and requests the ENTER dialog command, the pull-down menu for the selected menu bar choice is displayed below the text for the menu bar choice.

The resulting pull-down menu contains a selection field which has one or more pull-down choices. The user is allowed to choose only one pull-down menu choice. Each selection field has one or more pull-down menu choices.

All menu bars must be defined after any conditional statements and before the key lists.

When a menu bar is specified for a panel with a list action column, a slash (/) or country-designated selection character may be entered on the list action column to indicate the elements the menu bar choice is to act against. The slashes are processed in the same top-to-bottom processing as in normal list action processing. The slash (/) is not allowed on the extended action entry of an action list.

Other tags can be nested within the MBAR tag. These tags are listed in the following table. This table defines the order in which the tags must appear and specifies on what page more information can be found for each tag.

Table A-15. Tag Allowed Between the MBAR and EMBAR Tags.

Tag Name	Order	Page
MBARC (Menu bar choice)	1	A-108

Required Attribute

NAME=menu-bar-name

The name assigned to the menu bar. For more information on the rules for naming, see "Name Syntax" on page A-4.

Optional Attributes

HELP=help-module-name

The name of the help information explaining the purpose of the menu bar. The help module name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see "Name Syntax" on page A-4.

MAXBARL=1 | 2 | 3

The maximum number of lines that can be used for the descriptions of the menu bar. From 1 to 3 lines can be specified; 1 is the default. Only as many menu bar lines as needed up to the maximum number allowed by MAXBARL are used. If all the menu bar choices do not fit in the number of lines specified, a compiler error results.

Example: Menu Bar

This example defines the menu bar seen on the Work with Programs panel.

UIM Source

```
.* Menu bar for Work with Programs panel
:mbar name=mbarpgm
    help='mbarpgm/'
    .
.*
.* Menu bar choice for the "File" pull-down
:mbarc    help='mbarpgm/file'
    .File
:pdfld.
:pdfldc    option=2
    help='mbarpgm/file/change'
    action='cmd ?CHGPGM PGM(&var2./&var1.)'
    actfor=list
    .Change
:pdfldc    option=4
    help='mbarpgm/file/delete'
    action='cmd DLTPGM PGM(&var2./&var1.)'
    actfor=list
    confirm=confpgm
    usrexit='call exitpgm'
    .Delete
:pdfldc    option=5
    help='mbarpgm/file/display'
    action='cmd DSPPGM PGM(&var2./&var1.)'
    actfor=list
    .Display
:pdfldc    option=6
    help='mbarpgm/file/exit'
    action=exit
    varupd=no
    .Exit
:pdaccel.F3
:epdfld.
:embarc.
.*
.* Menu bar choice for the "Help" pull-down
:mbarc    help='mbarpgm/help'
    .Help
:pdfld.
:pdfldc    option=1
    help='mbarpgm/help/helphelp'
    action=helphelp
    varupd=no
    .Help for help...
:pdfldc    option=2
    help='mbarpgm/help/help'
    action=exthelp
    varupd=no
    .Extended help...
:pdfldc    option=3
    help='mbarpgm/help/keyshelp'
    action=keyshelp
    varupd=no
```

```
.Keys help...
:pdfldc    option=4
    help='mbarpgm/help/schidx'
    action=helpidx
    varupd=no
    .Help index...
:pdfldc    option=5
    help='mbarpgm/help/about'
    action='call logopgm'
    varupd=no
    .About...
:epdfld.
:embarc.
:embar.
```

Results

```
File Help
-----
Work with Programs                      System: SYSTEM01
Select items in list, press F10 to select action.

Opt Program Library Text
-----
- P P P P P P P P 1 L L L L L L L L L L Description text
- P P P P P P P P 2 L L L L L L L L L L Description text
- P P P P P P P P 3 L L L L L L L L L L Description text
- P P P P P P P P 4 L L L L L L L L L L Description text
```

The *File* pull-down is displayed as shown below.

```
File Help
-----
: 2. Change : Work with Programs                      System: SYSTEM01
:           : res F10 to select action.
: 4. Delete :
: 5. Display :
: 6. Exit   F3 : y Text
: .....: L L L L Description text
- P P P P P P P P 2 L L L L L L L L L L Description text
- P P P P P P P P 3 L L L L L L L L L L Description text
- P P P P P P P P 4 L L L L L L L L L L Description text
```

The *Help* pull-down is displayed as shown below.

```
File Help
-----
: 1. Help for help... : with programs
: 2. Extended help... :
Select : 3. Keys help... : select action.
: 4. Help index... :
Opt Pr : 5. About... :
- P P P P P P P P 2 L L L L L L L L L L Description text
- P P P P P P P P 3 L L L L L L L L L L Description text
- P P P P P P P P 4 L L L L L L L L L L Description text
```

When F10 (ACTIONS) is pressed, the cursor is positioned in the space before the first menu bar choice.

When a menu bar choice is selected, the cursor is located at the pull-down field and the tab key moves to the first unselected menu bar choice. Repeated pressing of the tab key moves the cursor through the menu bar area and then back to the pull-down menu.

MBARC (Menu Bar Choice)

►►:MBARC—HELP=*help-module-name*—.—*menu-bar-choice-text*—:EMBARC.◄◄

The menu bar choice (MBARC) tag defines one choice within a menu bar. The end of the menu bar choice must be indicated with an EMBARC tag.

Other tags can be nested within the MBARC tag. These tags are listed in the following table. This table defines the order in which the tags must appear and specifies on what page more information can be found for each tag.

Table A-16. Tags Allowed Between the MBARC and EMBARC Tags.

Tag Name	Order	Page
PDFLD (Pull-down field)	1	A-130
PDFLDC (Pull-down field choice)	2	A-131

Required Attributes

HELP=*help-module-name*

The name of the help information explaining the purpose of the menu bar choice. The help module name may be a name imported from another panel group, but must follow the rules

for names outlined earlier in this chapter. For more information on the rules for names, see "Name Syntax" on page A-4.

Required Text


menu-bar-choice-text

The displayable description for the menu bar choice. The text must appear on the same line or the next line as the tag, the text can contain only the reverse text (RT) tag, and the text must be no longer than 32 bytes.

The menu bar is formed by concatenating the text from the various menu bar choices. If the text does not fit on the rest of a line, it is placed on the next line. The menu bar is limited to the number of lines specified on the MAXBARL attribute on the MBAR tag.

The text is displayed with a tabable space in front of it. When the tab keys are used to position the cursor at one of the menu bar choices, the cursor appears one character to the left of the text. Two spaces are placed between each text field for the menu bar. The visual result has three spaces between choices.

MENU (Menu Area)



The menu area (MENU) tag defines a menu area. This tag is allowed only for display panels. The end of the menu area must have a EMENU tag.

The menu area is included in the panel with all the other areas that are defined on the panel. Only one menu area may be present on any panel.

Either the command line (CMDLINE) tag or the option line (OPTLINE) tag must be specified for a menu panel. The user selects a menu option by entering the option number on the command line or option line.

Other tags can be nested within the MENU tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-17. Tags Allowed Between the MENU and EMENU Tags

Tag Name	Order	Use	Page
TOPINST (Top instruction line)	1	D	A-154
APPFMT (Application formatted area)	2	D	A-8

Table A-17. Tags Allowed Between the MENU and EMENU Tags

Tag Name	Order	Use	Page
MENUGRP (Menu column group)	3	D	A-112
MENUI (Menu item)	3	D	A-113
BOTINST (Bottom instruction line)	4	D	A-10

Required Attribute

DEPTH=area-depth I '*'

The depth of the area in lines, including separators if any are specified.

If '*' is specified, the space remaining on the display after everything else is allocated is given to this area. Only one area in the panel may have '*' coded.

Optional Attribute

BOTSEP=SPACE I NONE I RULE

Defines the bottom separator for the menu area. If SPACE is specified, a line of spaces is used.

NONE indicates that no separator line exists.

If RULE is specified, a line of underscored spaces is used as a separator line.

SCROLL=NO I YES

NO indicates that the menu is not scrollable.

YES indicates that the menu area is intended to be scrollable. Ordinarily YES should not be used, but longer, scrollable menus can be constructed with SCROLL=YES. For a SCROLL=YES area, a line of spaces is used by the UIM to provide a line for the scroll information. If BOTSEP=SPACE is also specified on

MENU Tag

this tag, only one line of spaces is used unless this area also contains bottom instructions.

Optional Text

area-title

The title of the area. If no text is specified, no title line is allocated to the area. The text must appear on the same or next line as the tag, the text can contain only the reverse text (RT) tag, and cannot exceed a maximum length of 55 characters.


Example 1: Simple Menu Area

This example defines a menu area with three options.

UIM Source

```
:panel name=main
  help='menu/main'
  keyl=small
  panelid=zmenu
  topsep=space
  .My Main Menu
:menu depth='*'.
:topinst.Select one of the following:
:menui help=MNUSER
  option=1
  action='MENU X'
  .Display menu X
:menui help=MNSYS
  option=2
  action='MENU SYSOPR'
  .System operations
:menui help=MNOFF
  option=90
  action='CMD SIGNOFF'
  .Sign off
:emenu.
:cmdline size=long.Selection or command
:epanel.
```

Results



The screenshot shows a menu interface within a rectangular frame. At the top left, the word 'MAIN' is displayed. At the top right, the title 'My Main Menu' is shown. Below the title, the instruction 'Select one of the following:' is centered. A list of three options follows: '1. Display menu X', '2. System operations', and '90. Sign off'. At the bottom of the frame, there is a horizontal line. Below this line, the text 'Selection or command' is centered, followed by '==>' and a cursor. At the very bottom, a row of function key labels is displayed: 'F3=Exit', 'F4=Prompt', 'F9=Retrieve', and 'F12=Cancel'.

Example 2: Menu Area with Groups

This example has three menu areas, each of which has options that can be chosen.

UIM Source

```
:panel name=cfg2
  help='menu/cfg2'
  panelid=zmenu
  keyl=small
  .Configuration Templates
:menu depth='*'.
:topinst.Select one of the following:
:menugrp.Local Hardware:
:menui help='opt/lcl/wsprt'
  option=1
  action='MENU LCLWSPT'
  .Work stations and printers
:menui help='opt/lcl/ctl'
  option=2
  action='MENU LCLCTL '
  .Controllers
:menui help='opt/lcl/tapdkt'
  option=3
  action='MENU LCLTAPDKT'
  .Tape drives and diskette drives
:menugrp.
:menugrp.Remote Hardware:
:menui help='opt/rmt/wsprt'
  option=4
  action='MENU RMTWSPT'
  .Work stations and printers
:menui help='opt/rmt/ctl'
  option=5
  action='MENU RMTCTL '
  .Controllers
:menui help='opt/rmt/tapdkt'
  option=6
  action='MENU RMTTAPDKT'
```

```


.Tape drives and diskette drives
:emenugrp.
:menugrp.Communications Support:
:menui help='opt/cmn/lines'
      option=7
      action='MENU CMNLINES'
      .Communications lines
:menui help='opt/cmn/ctl'
      option=8
      action='MENU CMNCTL '
      .Communications controllers
:emenugrp.
:emenu.
:cmdline size=long.Selection or command
:epanel.

```

Results

CFG2	Configuration Templates	System: xxxxxxxx
Select one of the following:		
Local Hardware:		
1. Work stations and printers		
2. Controllers		
3. Tape drives and diskette drives		
Remote Hardware:		
4. Work stations and printers		
5. Controllers		
6. Tape drives and diskette drives		
Communications Support:		
7. Communications lines		
8. Communications controllers		
Selection or command		
====>		
F3=Exit F4=Prompt F9=Retrieve F12=Cancel		

MENUGRP (Menu Group)



The menu group (MENUGRP) tag groups menu items of a menu area together and supplies a heading for the group. This tag is allowed only for display panels.

If the number of lines required to display the first two items of the menu group exceeds the number of lines remaining in the current page, the entire group is forced to the next page. When all items in the menu group are not completely displayed on one page, the group is continued onto as many pages as required to display all items.

Other tags can be nested within the MENUGRP tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order

number of three cannot precede a tag with an order number of one or two.

Table A-18. Tag Allowed Between the MENUGRP and EMENUGRP Tags

Tag Name	Order	Use	Page
MENUI (Menu item)	1	D	A-113


Optional Attribute

COND=condition-name
The group is displayed and active on the panel only if the condition specified is true. If the condition is false, the entire group is not shown. The condition must be defined in the panel group prolog with the condition definition (COND) tag.

Optional Text

group-heading
The heading placed above the menu items of the group. The text must appear on the same or next line as the tag and can only contain the reverse text (RT) tag. The group heading always appears on one display line beginning in column four.

MENUI (Menu Item)



Required Attributes

HELP=help-module-name

Identifies online information explaining the purpose of the menu item. The help module name may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see “Name Syntax” on page A-4.

The online information identified by this attribute is displayed when help is requested while the cursor is positioned on the text for this tag or while the cursor is on the command or option line and a valid menu item number has been entered.

OPTION=option-number

The number to assign this option. Option numbers are integers in the range 0 through 999.

The menu items are displayed in the order defined for the menu area. If the numbering of two items is not consecutive, a blank line is automatically placed between the two items.

ACTION='action-text'

The action occurring when the menu item is selected by the user. The valid forms of action-text are:

- 'CALL program-reference'
 - 'CANCEL'
 - 'CMD command-string'
- Any dialog variable name in the command string must be preceded by an ampersand and should be ended with a period to denote variable substitution.
- 'EXIT'

- 'MENU qualified-menu-name RTNPNTINORTNPNT'
- 'RETURN positive-integer'

For a description of each of these actions, see Appendix B, “UIM Dialog Commands” on page B-1.

Optional Attributes

NAME=menu-item-name

The name associated with the menu item. This name can be used with the Add Pop-Up Window (QUIADDPW) API to position a window near this menu item. For more information on the rules for naming, see “Name Syntax” on page A-4.

COND=condition-name

The menu item is in effect on the panel only if the condition specified is true. The condition must be defined in the panel group prolog with the condition definition (COND) tag.

AVAIL=condition-name

The name of a condition indicating to the UIM whether or not the menu item is available for selection by the user. The condition must be defined in the panel group prolog with the COND tag.

Unavailable menu items are displayed with an asterisk (*) overlaying the first part of the menu item number.

When the condition is true, the menu item is available. When the condition is false, the menu item is not available. Any condition specified on the COND attribute of this tag takes precedence over this attribute.

AVLMSGID=*message-identifier*

The message identifier of the message displayed when the pull-down choice is selected but is not available as specified by the AVAIL attribute of this tag. This attribute is allowed only when the AVAIL attribute is specified.

If this attribute is not specified, the UIM displays a default message stating that the choice is currently not available.

AVLMSGF=*'qualified-message-file-name'*

The message file name containing the message identifier. This attribute is allowed only when the AVLMSGID attribute is specified on this tag. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, and if the AVLMSGID attribute is specified on this tag, then this attribute must be specified.

MARKER=*condition-name*

The name of a condition indicating whether or not the menu item is marked with a greater than sign (>). The marker is displayed only if the condition specified is true. The condition must be defined in the panel group prolog with the COND tag.

When the condition is true, a greater than sign is displayed to the left of the option number of the menu item. When the condition is false, the line is blank before the option number of the menu item. If this attribute is omitted, no marker appears on the menu item.

ITEM=*dialog-variable-name*

The name of a dialog variable containing the text for the menu item description when the panel is displayed. The dialog variable may be defined with a BASETYPE of CHAR, IGC, or BIN on the class definition (CLASS) tag. The declared length of the dialog variable must be no longer than what fits on one line of the panel, starting in column 10. Allowance must be made if there is an application formatted area.

If this attribute is used, no *menu-item-description-text* can be specified after the period for this tag.


Optional Text

menu-item-description-text

The descriptive text accompanying the option and shown on the menu. The text may appear on more than one line in the source. The text can contain only the reverse text (RT) tag, and cannot exceed 70 characters in length.

The item description text begins in column 10 of the panel. The option number, a period, and one blank appear immediately before the item description text. The item number begins in column 7, 6, or 5, depending on whether the option number has 1, 2, or 3 digits. The text is formatted onto additional lines as necessary, and the additional lines are not indented two spaces to fit on the panel.

NT (Note)



The note (NT) tag identifies a single- or multiple-paragraph note. This tag must have a matching end tag. These tags are only allowed in information areas and help areas. Notes cannot be nested.

Notes can occur anywhere in text that a paragraph is allowed. They can contain any basic text items, but cannot contain headings, figures, lines, examples, or any type of list. If this tag has not been ended when a heading tag is encountered, the note ends and a warning message is issued by the compiler.

The note is an implied paragraph. It is formatted as a block and indented 6 spaces from the current margin. The word *Note*, formatted in highlight phrase 2 (HP2) and followed by a colon, begins the paragraph. There are two spaces between the note tag and the text if either the note tag or the text are single-byte characters. There are four spaces between the note tag and the text if both are double-byte characters.

A note is aligned with the text of a list item when used within a list.

Other tags can be nested within the NOTE tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-19. Tags Allowed Between the NOTE and ENOTE Tags

Tag Name	Order	Use	Page
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128

Optional Text

note-text
Although the text of the note is not required, the tag has no meaning when text is not specified.

Example: Using a Note

The note tag makes important information stand out in a paragraph, as in this example.

UIM Source

```
:P.Here's a paragraph.  
:NT.  
Here's the first paragraph  
of the note.  
:P.  
Here's the second paragraph  
of the note.  
:ENT.  
:P.Here's a paragraph.
```

Results


Here's a paragraph.

Note: Here's the first paragraph of the note.

Here's the second paragraph of the note.

Here's a paragraph.

OL (Ordered List)



The ordered list (OL) tag identifies an ordered list of items. It requires a matching end tag. These tags are only allowed in information areas and help areas.

Ordered lists can occur anywhere in text and can be nested within other lists.

Note: Care should be taken when using unformatted lines (LINES), figure (FIG), and example (XMP) tags within ordered lists, because text that does not fit on one line wraps to column one of the next line. Lines and figures start at the current left margin, and examples are indented four spaces from the current left margin. The current left margin changes when nested lists are formatted. If online help information has the LINES, FIG, or XMP tag imbedded at various locations, including within lists, it may not look the same each time.

The OL tag is formatted as a hanging, indented list, with the item identifier (1,2,...a,b,...) at position four relative to the left margin. The text begins at position eight relative to the left margin.

Ordered lists are identified in a formatted document by sequential numbers or letters, depending on the definition for each level. The levels of definition are as follows:

- 1. 1., 2., 3., . . . ,11., 12., . . . , 99.
- 2. a., b., c., . . . , z., aa., bb., . . . , zz.
- 3. 1), 2), 3), . . . ,11), 12), . . . , 99)
- 4. a), b), c), . . . , z), aa), bb), . . . , zz)

Any additional levels repeat the sequence from the beginning.

Other tags can be nested within the OL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and spec-

ifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-20. Tags Allowed Between the OL and EOL Tags

Tag Name	Order	Use	Page
FIG (Figure)	1	B	A-57
LINES (Unformatted lines)	1	B	A-75
XMP (Example)	1	B	A-164
NT (Note)	1	B	A-115
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128
LP (List part)	1	B	A-105
OL (Ordered list)	1	B	A-116
SL (Simple list)	1	B	A-149
UL (Unordered list)	1	B	A-157
PARML (Parameter list)	1	B	A-126
DL (Definition list)	1	B	A-55

Optional Attribute

COMPACT

This attribute formats the list without a blank line between items.

Required Tag

:LI*item-text*

The text for the list item. The text is preceded by a number or a letter and a period.

Example: Ordered List

This example has two ordered lists, one imbedded within the other. The second ordered list uses the COMPACT attribute.

UIM Source

Some normal text...


```
:ol.
:li.First item (number)
:ol compact.
:li.First item (letter)
:li.Second item (letter)
:eol.
:li.Second item (number)
:eol.
```

Results

Some normal text...

1. First item (number)
 - a. First item (letter)
 - b. Second item (letter)
2. Second item (number)

OPTLINE (Option Line)



The option line (OPTLINE) tag specifies that a panel has a menu option field as opposed to a command line which allows commands or options to be entered. This tag is allowed only for display panels. The OPTLINE tag can be used only on a panel that has a menu area.

Any text associated with this tag is used as an instruction line, appearing immediately above the option field on the panel.

This tag must be the final tag in a panel, placed just before the EPANEL tag. The command line (CMDLINE) tag and the OPTLINE tag are mutually exclusive.

Optional Attribute

NAME=*option-line-name*

The name associated with the option line.

This name can be used with the Add Pop-Up

Window (QUIADDPW) API to position a window near the option line. For more information on the rules for naming, see "Name Syntax" on page A-4.

Optional Text

instruction-text

The text appearing as instructions for the option line. This text is an implied paragraph.

When the display is formatted, any text that does not fit onto one display line is formatted on the following blank lines and indented two columns. The text can be a maximum of 255 characters and can contain only the reverse text (RT) tag. If no text is provided, no instruction line is allocated or displayed above the option line.

P (Paragraph)

►►:P.*paragraph-text*◄◄

The paragraph (P) tag identifies a paragraph, which is one or more sentences related by their subject matter. This tag is only allowed in information areas and help areas.

Paragraphs can occur anywhere in text and can contain text items. A matching end tag is not allowed; a paragraph is ended by another paragraph or by a higher-level element.

Each paragraph is formatted as a block of text without indenting the first line. One blank line separates paragraphs from other text items.

Paragraphs inserted within a list align with the text of the list item.

Optional Text

Although the paragraph text is not required, the tag has no meaning when text is not specified.

Example: Paragraph Tag

This example illustrates how the paragraph tag is used.

UIM Source


```
:P.Here's a paragraph.  
Lines are formatted to  
fill the column.  
:P.Here's another  
paragraph.
```

Results

Here's a paragraph. Lines are formatted to fill the column.

Here's another paragraph.

PANEL (Display Panel)



The display panel (PANEL) tag is opened using the PANEL tag and closed using the EPANEL tag. It contains tags to define one or more panel area definitions.

Other tags can be nested within the PANEL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-21. Tags Allowed Between the PANEL and EPANEL Tag

Tag Name	Order	Use	Page
DATA (Data presentation area)	1	D	A-29
INFO (Information area)	1	D	A-66
LIST (List area)	1	D	A-80
MENU (Menu area)	1	D	A-109
CMDLINE (Command line)	2	D	A-24
OPTLINE (Option line)	2	D	A-118

Required Attributes

NAME=panel-name

The name of the panel. For more information on the rules for naming, see "Name Syntax" on page A-4.

HELP=*help-module-name*

The name of a help module containing the beginning of the extended help for the panel.

KEYL=*key-list-name*

The name of a key list for the panel.

Optional Attributes

PANELID=*dialog-variable-name*

The name of a dialog variable containing the text for the panel identifier when the panel is displayed. The dialog variable must be defined on a class definition (CLASS) tag with `BASETYPE='CHAR 10'`, `'NAME 10'`, or `'OBJNAME 10'`. The UIM displays the contents of the variable in the upper left corner of the panel. If this attribute is omitted, no panel identifier appears on the display.

To specify a panel identifier for a menu created by using the Create Menu (CRTMNU) command, the dialog variable for ZMENU should be declared with `PANELID=ZMENU` on the PANEL tag. The value of the `ZMENU` dialog variable is displayed as the panel identifier.

TITLE=*dialog-variable-name*

The name of a dialog variable containing the text for the panel title. The dialog variable must be defined with a display width of 55 or the width of the panel minus 2, whichever is less. A translation list may be used to provide the panel title.

The UIM trims trailing blanks from the string and centers the resulting text in the panel title area of the display. If this attribute is used, no *panel-title-text* can be specified.

For a pop-up panel, the declared length of the dialog variable must be equal to the width of the pop-up panel minus 2 bytes, and less if `PANELID` or `TOPSEP=DATETIME` is specified on this tag for the panel.

WIDTH=80 | *panel-width*

The width of the panel. If the width is not specified, the panel width defaults to 80 bytes. The specified width must contain 2 bytes of space for the left and right margins. A panel with `WIDTH=80` results in 78 bytes of space for panel data.

The maximum width supported for a panel displayed as a full screen is 132 bytes. The

maximum width supported for a pop-up window depends on what size screen the device supports. On a device that supports 24 rows by 80 bytes, 74 bytes is the maximum width of a pop-up window. On a device that supports 27 rows by 132 bytes, 126 bytes is the maximum width of a pop-up window. The minimum width for a pop-up window is 20 bytes.

DEPTH=FIT | *panel-depth*

The depth of the panel. If the depth is not specified, the panel depth defaults to FIT. If `DEPTH=FIT`, the UIM uses the depth of the device at display time to determine the depth of the panel. When `DEPTH=FIT`, the compiler verifies that all panel elements fit within 24 lines.

The specified depth includes:

- One line for a panel title
- One line of area data
- One or two lines for function key descriptions
- One line for the message line

The maximum supported depth is 27 lines for a panel displayed in a full display. The maximum supported depth for a pop-up panel depends on what the display device can support. On a device that can only support 24 rows by 80 bytes, the maximum depth of a pop-up window is 21 lines. On a device that can support 27 rows by 132 bytes, the maximum depth of a pop-up window is 24 lines.

The minimum allowed depth is five lines.

MBAR=*menu-bar-name*

The name of the menu bar used on the panel. This attribute is not allowed on confirmation panels or panels that will be used as pop-up windows.

Menu bars are only allowed on panels defined with one of the following sizes:

- `WIDTH=80` or 132 bytes, and `DEPTH=FIT`
- `WIDTH=80` bytes, `DEPTH=24` lines
- `WIDTH=132` bytes, `DEPTH=27` lines

MSGL=1 | **2** | **3** | **4**

The number of message lines that should appear on this panel. One message line is the default.

TOPSEP=SYSNAM | SPACE | RULE | DATETIME | NONE

Defines the top separator for the panel. If SYSNAM is specified, the separator line contains only the system name.

If SPACE is specified, a line of spaces is used.

If RULE is specified, a line of underscored spaces is used. RULE cannot be specified if the MBAR attribute is specified on this tag.

If DATETIME is specified, the separator line contains the date and time from the dialog variables identified on the DATE and TIME attributes of this tag. DATETIME also causes the system name to be on the right side of the title line. When date and time is used as the top separator for the panel, it should **not** be used to provide a current time clock. This function should be used to show the date and time in which the important data on the panel is collected or generated.

NONE indicates that no separator line exists.

Values other than TOPSEP=SPACE or NONE may cause undesirable results when the panel width is less than 80.

DATE=dialog-variable-name

The name of a dialog variable containing a date displayed on the top separator for the panel. This attribute is required when TOPSEP=DATETIME is specified on this tag. The dialog variable must be defined with BASETYPE='DATE' on the CLASS tag.

TIME=dialog-variable-name

The name of a dialog variable containing a time displayed on the top separator for the panel. This attribute is required when TOPSEP=DATETIME is specified. The dialog variable must be defined with BASETYPE='TIME' on the CLASS tag.

ENTER='action-text'

The default enter action for the panel, occurring when the Enter key is pressed and no UIM-defined action, such as menu or action list processing, is necessary. If this attribute is omitted, the panel is redisplayed to the user with no message or error indication. The valid forms of action text are:

- 'CALL program-reference'

For a description of the interface between the UIM and the program for a function key CALL, see the *System Programmer's Interface Reference*, SC41-8223.

- 'CMD command-string'
Any dialog variable name in the command string must be preceded by an ampersand to denote variable substitution.
- 'MSG message-identifier [qualified-message-file-name]'
- 'RETURN positive-integer'

For a description of each of these dialog commands, see Appendix B, "UIM Dialog Commands" on page B-1.

SELECT='action-text'

The default selection action for the panel, occurring when items are selected in a selection list or an action list and no action is selected from the menu bar. If this attribute is not specified, the panel is displayed to the user with no message or error indication. The valid forms of action text are:

- 'ACTIONS'
- 'MSG message-identifier [qualified-message-file-name]'
- 'PULLDOWN'
- 'RETURN positive-integer'

The PULLDOWN and ACTIONS dialog commands cannot be specified if the MBAR attribute is not specified on this tag.

USREXIT='CALL program-reference'

A general exit program called each time the user presses a function key or the Enter key after dialog variables and list entries are updated and before any action specified on the key list item (KEYI), list action (LISTACT), pull-down field choice (PDFLDC), or menu item (MENU) tag is performed.

The program is passed parameters that include what function is requested by the user. The exit program may do application-defined validity checks, change the display position attribute of lists that appear on the screen, or both. If the exit program sends a CPF6A02 status message to the UIM, the UIM redisplay the panel without performing the normal action processing.

The panel is redisplayed without calling this exit program if validity check errors associated with the CLASS, validity checking (CHECK),

or translation list (TL) tags are detected, or if the user presses an inactive function key. If the user presses a function key defined with VARUPD=NO on the KEYI tag, the values entered on the panel by the user are not available to this program. They are only stored internally in the UIM.

For a description of the CALL dialog command, see Appendix B, "UIM Dialog Commands" on page B-1.

For a description of the interface between the UIM and the general exit program, see the *System Programmer's Interface Reference*, SC41-8223.

TT=truth-table-name

The name of a truth table defined by the truth table (TT) tag, specifying what combinations of truth values may occur for conditions defined by condition definition (COND) tags while the application is running.

The table specified may contain any subset or superset of the conditions referred to by tags in the panel definition. Only the truth value combinations specified in the table, augmented by worst-case assumptions for any truth values not specified in the table, are considered in evaluating whether or not the panel definition is usable. The table should not exclude any truth value combination that could occur when the panel is displayed. If a valid truth value combination is omitted, a panel group object may create without error and have undesirable results when panels are displayed. For example, the UIM may fail to show panel elements that are conditioned-on for display. For more information about truth tables, see "TT (Truth Table)" on page A-155.

If this attribute is omitted, all combinations of truth values are considered possible. This causes the tag language compiler to make worst-case assumptions for all conditions in evaluating whether or not the panel definition is valid.

CSRVAR=dialog-variable-name

This attribute must name a CHAR 10 dialog variable which is used by the UIM to contain either the name of the dialog variable or the name of the command line where the cursor is or will be positioned.

The UIM updates this variable after the panel is displayed and before the general exit program or any action routines are called. It contains the name of the dialog variable associated with the field, or the name of the command line (if named) where the cursor is positioned on exit from the panel. If the cursor is not in a field or on a named command line, the CSRVAR dialog variable is set to blanks.

The Display Panel (QUIDSPP) API supports an option that allows the application program to control the initial cursor position by setting the dialog variables associated with the CSRVAR, CSRPOS, CSRLST, and CSREID panel attributes before the panel is displayed. If the CSRVAR dialog variable does not contain the name of a dialog variable or command line displayed on the panel, the UIM default cursor positioning is used and no error is reported.

If a data item is defined using data item extenders, the CSRVAR attribute contains the name of the extender dialog variable if the cursor is positioned within the extender field. If the cursor is positioned between fields, CSRVAR is set to the name of the dialog variable specified on the VAR attribute of the data presentation area (DATA) tag, and the CSRPOS dialog variable is set to zero.

CSRPOS=dialog-variable-name

This attribute must name a BIN 15 dialog variable used by the UIM to contain the character position within the field identified by the CSRVAR attribute on this tag where the cursor is or will be positioned.

The UIM updates this variable after the panel is displayed, before the panel exit program or any action routines are called. It contains the position within a field where the cursor is positioned on exit from the panel. If the cursor is not in a field, the dialog variable is set to zero. If the cursor is positioned in a text area associated with the field, such as a prompt label or column heading for a list area, the CSRVAR attribute contains the name of the dialog variable for the corresponding data item or list column, and the CSRPOS dialog variable is set to zero.

The QUIDSPP API supports an option which allows the using program to control the initial cursor position by setting the dialog variables

PANEL Tag

associated with the CSRVAR, CSRPOS, CSRLST, and CSREID attributes on this tag before the panel is displayed. If the CSRPOS attribute identifies a position that is not valid for the display field, the UIM default cursor positioning is used and no error is reported.

CSRLST=*dialog-variable-name*

This attribute must name a CHAR 10 dialog variable used by the UIM to contain the name of the list where the cursor is or will be positioned.

The UIM updates this variable after the panel is displayed, before the panel exit program or any action routines are called. It contains the name of the list associated with the list area where the cursor is positioned on exit from the panel. If the cursor is not in a list area, the dialog variable is set to blanks.

The QUIDSPP API supports an option that allows the using program to control initial cursor position by setting the dialog variables associated with the CSRVAR, CSRPOS, CSRLST, and CSREID attributes of this tag before the panel is displayed. If the CSRLST attribute is not blank and does not contain the name of a list displayed on the panel, the UIM default cursor positioning is used and no error is reported.

CSREID=*dialog-variable-name*

This attribute must name a CHAR 4 dialog variable used by the UIM to contain the list entry handle within the list identified by the CSRLST attribute where the cursor is or will be positioned.

The UIM updates this variable after the panel is displayed, before the panel exit program or any action routines are called. It contains the list entry identifier where the cursor was positioned on exit from the panel. If the cursor was not in any list entry, the *CSREID* dialog variable is set to X'00'. If the cursor was positioned in a text area associated with a list column, such as a column heading, the CSRLST attribute contains the name of the corresponding list and the *CSREID* dialog variable is set to X'00'.

The QUIDSPP API supports an option that allows the using program to control the initial cursor position by setting the dialog variables associated with the CSRVAR, CSRPOS, CSRLST,

and CSREID attributes of this tag before the panel is displayed. If the CSREID attribute identifies an unusable position that does not specify a list entry displayed on the panel, the UIM default cursor positioning is used and no error is reported.

CSRNAME=*dialog-variable-name*

This attribute must name a CHAR 10 dialog variable used by the UIM to contain the name of the item where the cursor is positioned.

The UIM updates this variable after the panel is displayed, before the panel exit program or any action routines are called. It contains the name of the item where the cursor is positioned on exit from the panel. If the cursor was not on any item, the *CSRNAME* dialog variable is set to blanks.

The value of this variable may be used to position pop-up windows adjacent to a field using the Add Pop-Up Window (QUIADDPW) API.

Optional Text

panel-title-text

The title used on this panel. The text must appear on the same or next line as the tag. The text cannot contain other tags, and is limited in length based on the width of the panel. The *panel-title-text* may be no more than 55 bytes long and is required unless the TITLE attribute is specified on this tag.

Example: Panel Definition

This example defines a panel and sets up the elements used within the panel.

UIM Source

```
:panel name=main
      help=hmain
      panelid=zmenu
      keyl=small
      .My Main Menu
:menu depth='*'.
:topinst.Select one of the following:
:menui help=MNUSER option=1
      action='CMD MENU X'
      .Display menu X
:menui help=MNSYS
      option=2
      action='CMD MENU SYSOPR'
```




```
.System operations
:menui help=MNOFF
      option=90
      action='CMD SIGNOFF'
      .Sign off
:emenu.
:cmdline size=long.Selection or command
:epanel.
```

Results

MAIN	My Main Menu	System: SYSTEM01
Select one of the following:		
1. Display menu X		
2. System operations		
90. Sign off		
Selection or command		
====>		
F3=Exit F4=Prompt F9=Retrieve F12=Cancel		

PARML (Parameter List)



The parameter list (PARML) tag identifies parameter terms and descriptions. These tags are only allowed in information areas and help areas. This tag requires a matching end tag. The terms defined and their definitions are identified by the parameter term (PT) tag and the parameter definition (PD) tag, respectively.

Note: Care should be taken when using unformatted lines (LINES), figure (FIG), and example (XMP) tags within parameter lists because text that does not fit on one line wraps to column one of the next line. Lines and figures start at the current left margin, and examples are indented four spaces from the current left margin. The current left margin changes when nested lists are formatted. If there is online help information containing lines, figures, or examples imbedded at various locations, including within lists, it may not look the same each time.

Parameter lists can occur anywhere in text; they can be nested within other lists, and other lists can be nested within parameter lists. Two PT or two PD tags cannot be used consecutively.

Nested PARML tags increase the current left margin by four.

Other tags can be nested within the PARML tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-22. Tags Allowed Between the PARML and EPARML Tags

Tag Name	Order	Use	Page
FIG (Figure)	1	B	A-57
LINES (Unformatted lines)	1	B	A-75
XMP (Example)	1	B	A-164
NT (Note)	1	B	A-115
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128
LP (List part)	1	B	A-105
OL (Ordered list)	1	B	A-116
SL (Simple list)	1	B	A-149
UL (Unordered list)	1	B	A-157
PARML (Parameter list)	1	B	A-126
DL (Definition list)	1	B	A-55

Required Tags

PT.parameter-term
The parameter term. The term formats in highlight phrase 2 (HP2) and can contain the programming keyword (PK) or programming variable (PV) tags.

The term appears on a line by itself, starting at position four relative to the current left margin.

PD.parameter-description
The description of the parameter. It can also contain the PK and PV tags.

The definition is printed on the following line, with the paragraph indented eight spaces from the current left margin. It is an implied paragraph and can contain any text items. Additional paragraphs can be inserted following the description paragraph by using the paragraph tag.

Example: Parameter List

This example uses a parameter list to define terms or parameters.

UIM Source

```
:PARML.
:PT.TERM
:PD.This is a description of
the term. :PK.TERM:EPK. is
a programming keyword.
:PT.:PK def.DEFAULT:EPK.
:PD.This is a sample default
parameter.
:PT.:PV.variable:EPV.
:PD.This is a parameter variable.
:EPARML.
```

Results

TERM

This is a description of the term. **Term** is a programming keyword.


DEFAULT

This is a sample default parameter.

variable

This is a parameter variable.

PC (Paragraph Continuation)



The paragraph continuation (PC) tag identifies the continuation of a paragraph that has been interrupted by another document element. This tag is allowed only in information areas and help areas.

A paragraph continuation usually occurs after a figure, example, or a list. It indicates that the following text is a continuation of the paragraph interrupted by a figure, example, or list.

A matching end tag is not allowed. A paragraph continuation is implicitly ended by another paragraph or by a higher-level element.

Example: Paragraph Continuation

The paragraph continuation tag continues the paragraph after the interruption of an example.

UIM Source

```
:p.If you enter the following
command
:xmp.
WRKSPLF
:exmp.
:pc.a listing of all my spool files
appears on the
terminal.
```

Results

```
If you enter the following command
WRKSPLF
a listing of all my spool files appears on
the terminal.
```

PDACCEL (Pull-Down Accelerator)

▶▶:PDACCEL—.—*accelerator-text*————▶▶

The pull-down choice accelerator (PDACCEL) tag defines text to be displayed as the accelerator key for a pull-down choice.

This tag defines only the text displayed. It does not automatically define the function key. It is your responsibility to define the function key with the key list item (KEYI) tag to perform the action defined for the pull-down choice accelerator.


Required Text

accelerator-text

The displayable description for the accelerator key. The text must appear on the same or next line as the tag. The text cannot contain any other tags, and cannot exceed 4 bytes in length.

The accelerator text is displayed to the right of its pull-down choice. The first character of each accelerator in the pull-down field is left-aligned two spaces after the longest text for any pull-down choice.

PDFLD (Pull-Down Field)



The pull-down field (PDFLD) tag defines a selection field within the menu bar pull-down. A pull-down field consists of one or more pull-down choices. The pull-down fields are formatted according to the IBM Systems Application Architecture (SAA) basic interface.

A single pull-down field can be defined for one menu bar choice between the menu bar choice (MBARC) and the EMBARC tags. The largest option number allowed for a pull-down choice is 99. The number of pull-down choices allowed to be specified between the PDFLD tag and the EPDFLD tag is determined by how many choices fit on the screen, based on conditioning. The maximum number of pull-down choices active at one time is determined by what fits on a screen.

Other tags can be nested within the PDFLD tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.


Table A-23. Tags Allowed Between the PDFLD and EPDFLD Tags

Tag Name	Order	Use	Page
PDACCEL (Pull-down choice accelerator)	1	D	A-129
PDFLDC (Pull-down field choice)	1	D	A-131

Optional Attribute

NAME=pull-down-field-name
The name associated with the pull-down field. For more information on the rules for naming, see "Name Syntax" on page A-4.

PDFLDC (Pull-Down Field Choice)



The pull-down field choice (PDFLDC) tag defines one choice within a pull-down field. A pull-down field consists of one or more pull-down choices.

Required Attributes

OPTION=*option-number*

The number assigned to this option. Option numbers are integers in the range of 1 through 99.

The pull-down choices are displayed in the order defined in the pull-down field. If the numbering of two choices is not consecutive, a blank line is automatically placed between the two choices.

HELP=*help-module-name*

Identifies help information explaining the purpose of the pull-down field choice. The name of the help module may be a name imported from another panel group, but must follow the rules for names outlined earlier in this chapter. For more information on the rules for names, see “Name Syntax” on page A-4.

The online information identified by this attribute is displayed when help is requested while the cursor is positioned on text for this tag. This online information is also included as part of the contextual help displayed when the cursor is positioned on the text for the menu bar choice for this pull-down menu, or when the cursor is positioned within the pull-down menu but not on the text for one of the

choices. If the cursor is in the entry field and a valid choice has been entered when help is requested, the help for that choice is displayed.

ACTION=*'action-text'*

The action occurring when the pull-down choice is selected.

Table A-24. Valid Action Text for ACTION Values

Dialog Command	ACTFOR= PANEL	ACTFOR= LIST
CALL	X	X
CHGVIEW	X	
CMD	X	X
CMDLINE	X	
DSPHELP	X	
EXIT	X	
EXTHelp	X	
HELPHELP	X	
HELPIIDX	X	
KEYSHELP	X	
MENU	X	
RETRIEVE	X	
RETURN	X	X

For a description of each of these actions, see Appendix B, “UIM Dialog Commands” on page B-1.

Optional Attributes

ACTFOR=PANEL | LIST

If PANEL is specified, the pull-down choice performs actions against the whole panel.

If LIST is specified, the pull-down choice performs actions against items in a selection list or in an action list.

When LIST is specified on a pull-down choice and if the user has not selected a list to be processed, the pull-down choice is displayed with an asterisk (*) overlaying the option number to indicate that the pull-down choice is not available.

CONFIRM=*internal-panel-name*

The name of the confirmation panel displayed before the action is performed. This attribute is allowed only when ACTFOR=LIST and ACTION=CALL or ACTION=CMD is specified on this tag. The confirmation panel must give the user the option to confirm or not confirm the action. If the action is confirmed, the appropriate actions from this tag are performed. If the action is not confirmed, none of those actions are performed.

The confirmation panel must be another panel defined within this panel group.

For a list of the recommended and required conventions for this attribute, see "Confirmation Panel Requirements" on page A-133 and "Confirmation Panel Conventions" on page A-133.

USREXIT='CALL *program-reference*'

Specifies the exit program for the action list program called to update the list entries after the action defined in the ACTION attribute is performed. This attribute is allowed only when ACTFOR=LIST and ACTION=CALL or ACTION=CMD is specified on this tag. The program is passed information that includes the name of the list and an indication of whether the option succeeded or failed.

For a description of the CALL dialog command, see Appendix B, "UIM Dialog Commands" on page B-1.

For a description of the interface between the UIM and the exit program for action lists, see the *System Programmer's Interface Reference*, SC41-8223.

VARUPD=YES | NO

This attribute is allowed only when PANEL is specified on the ACTFOR attribute for this tag. When ACTFOR=LIST is specified, variable pool updating is performed. If YES is specified,

validity checking occurs and the variable pool is updated before the action takes place.

If NO is specified, the action is performed immediately and no variable pool updating occurs.

Dialog Command	VARUPD Values
CALL	YES NO
CHGVIEW	YES
CMD	YES NO
CMDLINE	NO
DSPHELP	NO
EXIT	NO YES
EXTHelp	NO
HELPHELP	NO
KEYSHELP	NO
HELPIDX	NO
MENU	YES
RETRIEVE	NO
RETURN	YES NO

Note: The default value is based on the ACTION attribute. The first value is the default value.

COND=*condition-name*

The pull-down choice is in effect on the panel only if the condition specified evaluates to true. The condition must be defined in the panel group prolog with the condition definition (COND) tag. When the choice is conditioned-off, it does not appear in the pull-down and the help for the choice is not included in requests to display help.

AVAIL=*condition-name*

The name of a condition used by the UIM to determine whether or not the pull-down choice is available. The condition must be defined in the panel group prolog with the COND tag.

When the condition is true, the pull-down choice is available. When the condition is false, the pull-down choice is not available. Any condition specified on the COND attribute of this tag takes precedence over this attribute.

Unavailable choices are displayed with a color change on color devices and an asterisk (*) overlaying the first part of the choice option number.

AVLMSGID=*message-identifier*

The message identifier of the message displayed when the pull-down choice is selected when it is not available as specified by the

AVAIL attribute. This attribute is allowed only when the AVAIL attribute is specified on this tag. If this attribute is not specified, the UIM displays a default message stating that the choice is currently not available.

AVLMSGF=*'qualified-message-file-name'*

The message file name containing the message identifier. This attribute is allowed only when the AVLMSGID attribute is specified on this tag. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, and if the AVLMSGID attribute on this tag is specified, this attribute must be specified.

CHOICE=*dialog-variable-name*

The name of a dialog variable containing the pull-down choice text to be displayed. The dialog variable must be defined with a width less than or equal to 32 bytes. If this attribute is used, no *pull-down-choice-text* can be specified.

Dialog variables must be defined with a BASETYPE of CHAR, IGC, or BIN on the class definition (CLASS) tag.

The error state of the dialog variable is not used for determining the highlighting of the text.

Special formatting for IGC. (The abbreviation IGC is used in commands and keywords to represent double-byte character set functions.) When a dialog variable with a BASETYPE of IGC is specified on the CLASS tag, the UIM does special formatting. If the variable value begins with a shift-out character (X'OE'), the UIM shifts the value 1 byte to the left to preserve vertical alignment with choices on other lines.

Optional Text

pull-down-choice-text

The descriptive text shown in the pull-down field. The text may appear on a single line in the source. The text can contain only the reverse text (RT) tag, and cannot exceed 32 bytes in length. The *pull-down-choice-text* is required unless the CHOICE attribute is specified on this tag.

For a pull-down choice, the option number, a period, and one blank appears immediately before the choice description text. The NBRSHAPE attribute of the PNLGRP tag

explains how option numbers are presented when BIDI=LTR or when BIDI=RTL is specified on the PNLGRP tag.

Confirmation Panel Requirements

The panel named on the CONFIRM attribute of this tag must follow these conventions:

- The ENTER attribute on the display panel (PANEL) tag of the confirmation panel should have 'RETURN 100' coded. This indicates to the UIM that the action is confirmed by the user.
- No ACTION attribute on a key list item (KEYI) tag can be assigned to the RETURN action, because the UIM is handling the display of the panel and is unable to interpret the returned value.
- The confirmation panel must have a list area.
- The list used as the confirmation list must not also be used on the action list panel.
- The confirmation panel must not have an action list, a command line, a menu area, or a menu bar.

Confirmation Panel Conventions

The panel named on the CONFIRM attribute of this tag should follow these conventions:

- It should have title text and top instructions as appropriate to describe the panel.
- It should have a single list area with a list definition that contains the same (or a subset of) columns defined in the original action or selection list.
- The list should be scrollable.
- If the action list has multiple views, the confirmation list should also have multiple views and the same dialog variable should be used for the view variable on both lists. The confirmation panel should also have a function key defined for the CHGVIEW dialog command. This allows a change view operation on the confirmation panel to change the view of the action or selection list panel when it is redisplayed.
- The confirmation panel should have function key definitions for the ENTER, CANCEL,

PAGEUP, PAGEDOWN, HELP, and PRINT dialog commands.

- If a general exit program is defined, it should avoid making changes to the list or condition values that affect the redisplay of the original panel.
- The list used on the confirmation panel should not be used on anything but a confirmation

panel, because the UIM deletes and changes the contents of that list. If multiple confirmation panels are used within a UIM application, they can share the same list.

- Most of the online help information for the action list panel can be used for the confirmation panel, but separate help information should be provided for the action column and for the extended panel help.

PK (Programming Keyword)

►►:PK—DEF—.*programming-keyword-text*:EPK.—◄◄

The programming keyword (PK) tag identifies a programming keyword. This tag is only allowed in information areas and help areas. It requires a matching end tag.

A programming keyword can occur anywhere in text. It helps explain the elements of programming syntax and is frequently used within parameter lists. For more information on parameter lists, see “PARML (Parameter List)” on page A-126,

The PK and EPK tag phrase must be specified on word boundaries. If the two characters immediately following the EPK tag are a punctuation mark and a blank, the UIM automatically extends the emphasis attribute to include the punctuation mark. This allows the punctuation mark and the

text associated with it to be displayed with the same emphasis.

Optional Attribute

DEF


Specifies that the programming keyword is a default value. The programming keyword formats in highlight phrase 2 (HP2) unless the DEF attribute is specified. If the DEF attribute is specified, the programming keyword formats as highlight phrase 3 (HP3).

Required Text

programming-keyword-text

Specifies the programming keyword.

PNLGRP (Panel Group)



The panel group (PNLGRP) tag begins the definition of a panel group. Only one PNLGRP tag is allowed and a matching EPNLGRP tag is required.

Other tags can be nested within the PNLGRP tag. These tags are listed in the following table. This table defines the order in which the tags must appear and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-25. Tags Allowed Between the PNLGRP and EPNLGRP Tags

Tag Name	Order	Page
COPYR (Copyright)	1	A-28
ISCHSYN (Index search synonym)	any	A-70
IMPORT (Import)	2	A-65
CLASS (Class definition)	3	A-14
VAR (Variable definition)	4	A-159
VARRCD (Variable record definition)	5	A-162

Table A-25. Tags Allowed Between the PNLGRP and EPNLGRP Tags

Tag Name	Order	Page
LISTDEF (List definition)	6	A-98
COND (Condition definition)	7	A-25
TT (Truth table)	8	A-155
MBAR (Menu bar)	9	A-106
KEYL (Key list)	10	A-74
PANEL (Display panel)	11	A-120
PRTHEAD (Print head panel)	11	A-139
PRTPNL (Print panel)	11	A-143
HELP (Help module)	11	A-58

Optional Attributes

SCHIDX=qualified-object-name

The index search object used when the index search function is requested from the help modules for panels defined in this panel group. If SCHIDX is not specified, the index search function is not accessible when help modules are displayed for panels in this panel group. This attribute has no effect on help modules defined in the panel group unless panels in the panel group use the help modules.

TXTMODE=SBCS | DBCS

Specifies whether a single-byte character set (SBCS) or double-byte character set (DBCS) is used in the tag text. If DBCS is specified, the tag text must have the shift-in or shift-out characters to indicate the start and end of DBCS text.

A panel group object for which TXTMODE=DBCS is specified can only be used on a display station and system capable of handling DBCS information. An attempt to display a DBCS menu, open a DBCS panel group object, or present DBCS help information on a device that does not support DBCS results in an exception.

TXTCHRID='character-set code-page'

Specifies the character set and code page for SBCS text data in the panel group source. This information is used for synonyms defined using the index search synonym (ISCHSYN) tag. For more information on this tag, see "ISCHSYN (Index Search Synonym)" on page A-70. If this attribute is omitted, all text must be on the index search (ISCH) and ISCHSYN tags to be in the character set and code page specified by the QCHRID system value at the time the panel group is created.

The TXTCHRID attribute specifies the code page and character set of the text information in the panel group source. It must not be confused with the CHRID parameter on the CRTPNLGRP command, which controls the way dialog variables with CHRID=PNLGRP specified on the class definition (CLASS) tag are handled when the dialog variable value is sent to or from the display station.

BIDI=NONE | LTR | RTL

Indicates the orientation of the panels in the panel group. NONE indicates that the panels in the panel group should be displayed in a single direction with a left-to-right orientation. NONE is the default and is required when TXTMODE=DBCS is specified on this tag.

When BIDI=NONE is coded, the following items are ignored:

- The NBRSHAPE attribute on this tag
- The BIDI, NBRSHAPE, CONXTREV, and SYMSWAP attributes on the CLASS tag
- All reverse text (RT) tags

LTR indicates that the panels in the panel group are bidirectional and should be displayed with a left-to-right orientation.

RTL indicates that the panels in the panel group are bidirectional and should be displayed with a right-to-left orientation.

When either LTR or RTL is specified for a panel group, the work station controller enables the hot key to flip the panel so that the user can flip the panel if necessary. When RTL is specified, the controller automatically flips all panels of the panel group as they are displayed.

The normal use of LTR is for panels written in a left-to-right language with a small amount of right-to-left language text in it. The normal use of RTL is for panels written in a right-to-left language with a small amount of text in a left-to-right language.

The UIM does not allow a LTR or RTL panel to be used on a display device that does not have the correct code page for bidirectional languages. Hebrew uses code page 424 and Arabic uses code page 420.

The value of this attribute of all possible panel groups that can be reached through hypertext links should be the same. If they are not the same when a reference phrase is selected, the resulting screen or pop-up window may be displayed with the opposite orientation.

NBRSHAPE=ARABIC | HINDI

This attribute is ignored when BIDI=NONE is specified on this. The NBRSHAPE attribute controls the display shape of UIM-generated numbers. This attribute is ignored except when code page 420 (Arabic) is being used.

When ARABIC is specified, the normal digits, X'F0' through X'F9', are used for numbers. ARABIC is the default.

When HINDI is specified, the translation of digits is performed with a translation table defined for each national language.

Digits that come from the panel group source or from messages are not affected by the NBRSHAPE attribute because they are expected to already be translated to the correct character. The numbers that are affected by the NBRSHAPE attribute are:

- Numbers generated by the UIM for menu items
- Numbers generated by the UIM for ordered list numbers
- Numbers generated by the UIM for pull-down field choices
- Page number information on a print panel and printed help information

Numbers that are not affected by the NBRSHAPE attribute are:

- The digits used in the system name
- Messages displayed on the message line
- Copyright dates on the message line
- Product number information on a print panel and in printed help information

Because the Hindi zero looks like a period, the format of the number in front of a menu item or pull-down choice is 'n)' instead of

'n.', where 'n' is the menu item or choice option number.

DFTMSGF= *qualified-message-file-name*

The default message file used when a message file is not specified for a message identifier on any of the following tags:


CHECK	Validity checking
LISTDEF	List definition
TL	Translation list
DATASLTC	Data selection field
PDFLDC	Pull-down field choice
LISTACT	List action
MENUI	Menu item

If the corresponding message file attribute is not specified on any of these tags when the MSGID attribute is specified for this tag, this attribute is required.

SUBMSGF= *qualified-message-file-name*

The default message file used when a message file is not specified on the &msg symbol.

PRTHEAD (Print Head Panel)



A print head panel (PRTHEAD) tag contains tags defining heading information and data used with a UIM print application. A print heading panel establishes the prolog section printed after the title line on the first page and the header data printed at the top of every page. The prolog and header sections can be made up of data and information areas. A PRTHEAD panel causes an automatic page eject.

Other tags can be nested within the PRTHEAD tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-26. Tags Allowed Between the PRTHEAD and EPRthead Tags

Tag Name	Order	Use	Page
DATA (Data presentation area)	1	P	A-29
INFO (Information area)	1	P	A-66
PRTRAIL (Print trail)	2	P	A-145

Required Attribute

NAME=panel-name

The name of the print head panel. For more information on the rules for naming, see “Name Syntax” on page A-4.

Optional Attributes

PRODINFO=dialog-variable-name

The name of a dialog variable containing the product information printed on the second title line of the print output.

The dialog variable must be defined with a BASETYPE of CHAR or IGC on the class definition (CLASS) tag, and the maximum width is 22 bytes.

PRTDATE=dialog-variable-name

The name of a dialog variable containing the date printed on the page title. If this attribute is specified, the PRTTIME attribute must also be specified on this tag. If this attribute is not specified, the UIM uses the current system date when the Open Print Application (QUIOPNPA) API or the Add Print Application (QUIADDPA) API is called.

The dialog variable must be defined with a class that has a BASETYPE of DATE on the CLASS tag.

PRTTIME=dialog-variable-name

The name of a dialog variable containing the time printed on the page title. The dialog variable must be defined with a class that has a BASETYPE of TIME on the CLASS tag. If this

PRTHEAD Tag

attribute is specified, the PRTDATE attribute must also be specified on this tag. If this attribute is not specified, the UIM uses the current system time when the QUIOPNPA API or the QUIADDDPA API is called.

TITLE=*dialog-variable-name*

The name of a dialog variable containing the text for the page title line. The dialog variable must be defined on a CLASS tag with a display width of 55. A translation list may be used to provide the panel title or the width of the panel minus two, whichever is less. The dialog variable may also be defined with a BASETYPE of CHAR 55 or IGC 55 on the CLASS tag. The UIM trims trailing blanks from the string and centers the resulting text in the page title area. If this attribute is used, no *title-text* can be specified.

TT=*truth-table-name*

The name of a truth table specifying what combinations of truth values may occur at run time when the panel head is formatted.

The table specified on this tag may contain a subset of the conditions referred to by tags in the print head panel. Only the truth value combinations specified in the table, augmented by worst-case assumptions for any truth values not specified in the table, are considered in evaluating whether or not the print head panel is valid. The table should not exclude any truth value combination that could occur when the print head panel is formatted at run time. If a valid truth value combination is omitted, a panel group object may create without error and produce undesirable results when panels are printed.

If this attribute is omitted, all combinations of truth values are considered possible. This causes the tag language compiler to make worst-case assumptions for all conditions in evaluating whether or not the print head panel is valid.

WIDTH=80 | 132

Defines the width, in bytes, of the PRTHEAD panel. The default value is 80 bytes.

OBJ=*dialog-variable-name*

The name of a dialog variable containing the name of the object whose information is printed on the title line of the printout. If this attribute is not specified, an object name is not printed.

If the OBJLIB attribute on this tag is specified, the class for this dialog variable must be defined with a width of 10 characters. If the OBJLIB attribute is not specified, the class for this dialog must be defined with a width of 1 to 21 characters.

OBJLIB=*dialog-variable-name*

The name of a dialog variable containing the name of the library where the specified object from the OBJ attribute on this tag is found. This library name is printed on the title line of the printout. If this attribute is not specified, a library name is not printed.

You are responsible for the validity of the data contained in the OBJ and OBJLIB attributes. The UIM does not perform validity checking on these variables. If only the OBJ attribute is specified, only the OBJ is printed. However, if only the OBJLIB attribute is specified, a message is issued at compile time.

The class for this dialog variable must be defined with a width of 10 characters.

Optional Text

| *page-title-text*

The title used on the title line. The text must appear on the same line or next line as the tag. The text can only contain the reverse text (RT) tag, and cannot exceed 55 characters in length. The *page-title-text* is required unless the TITLE attribute is specified on this tag.

Layout of the Title Lines

The title lines for the PRTHEAD tag appear on the top two lines of each printed page. The placement of fields in the title lines depends on the width specified on this tag.

Table A-27. First Line of Heading with Print Width 132

Data	Start Column	Length
Title	See note.	Max. 55
Separator	See note.	4
"Page" (with expansion)	See note.	Max. 11
Separator	125	2
Page number	127	4
Separator	131	2

Note: The start column for this data is variable. The title is centered between the left margin and the separator following the title.

Table A-28. First Line of Heading with Print Width 80

Data	Start Column	Length
Title	See note.	Max. 55
Separator	See note.	4
"Page" (with expansion)	See note.	Max. 11
Separator	73	2
Page number	75	4
Separator	79	2

Note: The start column for this data is variable.

Table A-29. Second Line of Heading with Print Width 132

Data	Start Column	Length
Product information	1	22
Separator	23	Min. 55
Library	See note.	Max. 10
Slash	See note.	1
Object	See note.	Max. 10
Separator	99	4
System name	103	8
Separator	111	2
Date	113	8
Separator	121	2
Time	123	8
Separator	131	2

Note: The library and object are formatted as OBJLIB/OBJ with trailing blanks stripped from the OBJLIB and OBJ values. The OBJLIB/OBJ aggregate is right-justified against the separator before the system name.

Table A-30. Second Line of Heading with Print Width 80

Data	Start Column	Length
Product code	1	Max. 22
Separator	23	Min. 3
Library	See note.	Max. 10
Slash	See note.	1
Object	See note.	Max. 10
Separator	47	4
System name	51	8
Separator	59	2
Date	61	8
Separator	69	2
Time	71	8
Separator	79	2


Note: The library and object are formatted as OBJLIB/OBJ with trailing blanks stripped from the OBJLIB and OBJ values. The OBJLIB/OBJ aggregate is right-justified against the separator before the system name.

Example: Print Title Line

The following example has a title line with a width of 80 bytes. The title is from the print head panel or the first print panel. The page text and page number are provided by the UIM.

Either the UIM or the application can provide the date and time. The application must use the PRTDATE and PRTTIME attributes on the PRTHEAD tag to specify a date and time. If the PRTDATE and PRTTIME attributes are not specified, the UIM uses the system date and time when the QUIOPNPA API or the QUIADDPA API is called. The date and time are formatted using the job attributes.

PRTPNL (Print Panel)



A print panel (PRTPNL) tag contains tags to define one or more area definitions for a print panel. It requires a matching EPRTPNL tag.

Other tags can be nested within the PRTPNL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-31. Tags Allowed Between the PRTPNL and EPRTPNL Tags

Tag Name	Order	Use	Page
DATA (Data presentation area)	1	P	A-29
INFO (Information area)	1	P	A-66
LIST (List area)	1	P	A-80

Required Attribute

NAME=panel-name

The name of the print panel. For more information on the rules for naming, see “Name Syntax” on page A-4.

Optional Attributes

TITLE=dialog-variable-name

The name of a dialog variable containing the text for the panel title when the panel is printed. The dialog variable must be defined with a class that has a width of 55. The UIM trims trailing blanks from the string and centers the resulting text in the title line of the print panel. If this attribute is used, no *title-text* can be specified.

TT=truth-table-name

The name of a truth table that specifies what combinations of truth values may occur at run time when the panel is printed.

The table specified on this tag may contain a subset of the conditions referred to by tags in the print panel. Only the truth value combinations specified in the table, augmented by worst-case assumptions for any truth values not specified in the table, are considered in evaluating whether or not the print panel definition is valid. The table should not exclude any truth value combination that could occur when the print panel is printed. If a valid truth value combination is omitted, a panel group object may create without error and produce undesirable results when panels are printed.

If this attribute is omitted, all combinations of truth values are considered possible. This causes the tag language compiler to make worst-case assumptions for all conditions in evaluating whether or not the print panel is valid.

WIDTH=80 | 132

Defines the width, in bytes, of the print panel. The default value is 80 bytes.

Optional Text

title-text

The title used on this print panel. The text must appear on the same or next line as the tag. The text can only contain the reverse

PRTPNL Tag

text (RT) tag, and cannot exceed 55 characters in length. The *title-text* is not allowed if the TITLE attribute is specified on this tag.

PRTTTRAIL (Print Trailer Message)

```
▶▶:PRTTTRAIL.trailer-message-text▶▶
```

The print trailer message (PRTTTRAIL) tag is allowed only within the print head panel (PRTHEAD) tag, appearing immediately before the EPRTHEAD tag. The trailer message is printed at the end of the print listing. If no trailer is specified, no default trailer is printed.

Note: The trailer is only printed when the printer file is closed by using the option for a normal close on either the Close Application (QUICLOA) API or the Remove Application (QUIRMVPA) API. The trailer is not printed if the application is closed using the option for an abnormal close.

Required Text

trailer-message-text

The text appearing at the end of the print listing. This text can be entered without

leading or trailing asterisks (*). The UIM adds asterisks before and after the text.

The text can be a maximum of 106 bytes for WIDTH=132 and a maximum of 54 bytes for WIDTH=80, specified on a PRTHEAD tag. The text can contain only the reverse text (RT) tag.

Example: Trailer Message

This example shows what kind of text a print trailer message might have.

UIM Source

```
:prtttrail.END OF LISTING
```

PV (Programming Variable)

►►:PV.*programming-variable*:EPV.◄◄

The programming variable (PV) tag identifies a programming variable. It requires a matching end tag. These tags are only allowed in information areas and help areas. It is frequently used within parameter lists. For more information on parameter lists, see “PARML (Parameter List)” on page A-126.

A programming variable can occur anywhere in the text to help explain the elements of programming syntax.

The PV and EPV tag phrase must be specified on word boundaries. If the two characters imme-

diately following the EPV tag are a punctuation mark and a blank, the UIM automatically extends the emphasis attribute to include the punctuation mark. This allows the punctuation mark and the text associated with it to be displayed using the same emphasis.

Required Text

programming-variable

The programming variable. The text formats in highlight phrase 1 (HP1).

RT (Reverse Text)

►►:RT.reverse-direction-text:ERT.◄◄

The reverse text (RT) tag indicates that the enclosed text has an orientation opposite to the orientation of the panel group. This tag is ignored for panel groups with BIDI=NONE specified on the panel group (PNLGRP) tag. On a BIDI=RTL panel group, text in a left-to-right language is placed between the RT and ERT tags, while on a BIDI=LTR panel group, text in a right-to-left language is placed between the RT and ERT tags.

With the import (IMPORT) tag, it is possible to combine help information from panel groups that have BIDI=RTL specified with help information from panel groups that have BIDI=LTR specified. This is not recommended, but when it does occur, the user needs to use the hot key sequence for the work station controller to flip the screen to read the help information with the opposite orientation. Any text within the RT and ERT tags is formatted correctly for its panel group orientation. Therefore, when the RT tag is used for text that is imported into help information with the opposite orientation, the imported text is also readable when the screen is flipped.

Unlike the highlight phrase tags, the RT tag is allowed within the text of most tags. The following tags allow an imbedded RT tag:

BOTINST	Bottom instructions
CIT	Title citation
CMDLINE	Command line
DATA	Data area
DATASLTC	Data selection choices
DATAGRP	Data group
DATAI	Data item
DD	Definition
DDHD	Definition header
DT	Definition term
DTHD	Definition term header
FIGCAP	Figure caption text
Hn	Headings
HPn	Highlighted phrase
INFO	Information area
KEYI	Key list item
LINK	Hypertext link definition
LIST	List area
LISTACT	List action

LISTGRP	List group
LI	List item
LP	List part
MBARC	Menu bar choice
MENU	Menu area
MENUI	Menu item
NT	Note
OPTLINE	Option line
P	Paragraph
PC	Paragraph continuation
PD	Parameter description
PT	Parameter term
PRTHEAD	Print head panel
PRTPNL	Print panel
PRTRAIL	Print trailer message
PDFLDC	Pull-down field choice
TOPINST	Top instruction line

The RT tag cannot be used within a figure (FIG), unformatted lines (LINES), or an example (XMP) tag. No tag is allowed between an RT tag and its matching ERT tag.

Blanks found between an RT tag and its matching ERT tag are preserved. This includes the trailing blank at the end of each source line. Therefore, starting a source line with an ERT tag is not recommended.

Example 1: Left-to-Right Formatting on a Right-to-Left Panel

This example illustrates left-to-right source formatted and displayed on a right-to-left panel.

UIM Source

:P.For more information see the
:CIT.:RT.IBM OS/400 User Interface
Manager Reference Manual:ERT.:ECIT.
which you can find in your library.

Results

IBM OS/400 User eht ees noitamrofni erom roF
uoy hcihw Interface Manager Reference Manual
.yrrabil ruoy ni dnif nac

Example 2: Left-to-Right Formatting on a Left-to-Right Panel

This example illustrates left-to-right source formatted and displayed on a left-to-right panel.


UIM Source

```
:P.This is an example of some  
:RT.PRETEND HEBREW TEXT:ERT.  
imbedded within some real  
English text.
```

Results

This is an example of some DNETERP
TXET WERBEH imbedded within some
real English text.

SL (Simple List)



The simple list (SL) tag identifies a list of items. It requires a matching end tag. These tags are only allowed in information areas and help areas.

Simple lists can occur anywhere in text and can be nested within other lists.

Care should be taken when using the unformatted lines (LINES), figure (FIG), and example (XMP) tags within simple lists, because text that does not fit on one line wraps to column one of the next line. Lines and figures start at the current left margin, and examples are indented four spaces from the current left margin. The current left margin changes when nested lists are formatted. If there is help information containing the LINES, FIG, or XMP tags imbedded at various locations, including within lists, it may not look the same each time and can cause undesirable results.

Simple lists are formatted as hanging, indented lists, with no item identifier.

Other tags can be nested within the SL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-32. Tags Allowed Between the SL and ESL Tags

Tag Name	Order	Use	Page
FIG (Figure)	1	B	A-57

Table A-32. Tags Allowed Between the SL and ESL Tags

Tag Name	Order	Use	Page
LINES (Unformatted lines)	1	B	A-75
XMP (Example)	1	B	A-164
NT (Note)	1	B	A-115
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128
LP (List part)	1	B	A-105
OL (Ordered list)	1	B	A-116
SL (Simple list)	1	B	A-149
UL (Unordered list)	1	B	A-157
PARML (Parameter list)	1	B	A-126
DL (Definition list)	1	B	A-55

Optional Attribute

COMPACT

The list is formatted with no blank line between the items.

Required Tag

:LI.item-text

The text for the list item. The text is indented four spaces from the current margin.

Example: Simple Lists

This example uses two simple lists, one imbedded within the other. The second simple list uses the COMPACT attribute.

UIM Source

Some normal text...

```
:sl.  
:li.First item  
:sl compact.  
:li.First item  
:li.Second item  
:esl.  
:li.Second item  
:esl.
```

Results

Some normal text...

First item

First item

Second item

Second item

TI (Translation List Item)

```

▶▶:TI[VALUE='internal-value']·[displayed-value]▶▶

```

The translation list item (TI) tag specifies a list item in a translation list. This tag must occur between translation list (TL) and ETL tags. The item is translated on output to the panel and on input to the variable pool.

Optional Attribute

VALUE='internal-value'.

The internal value for the dialog variable in the variable pool. This internal value is not subject to validity checks defined by the validity checking (CHECK) tag for this class. If the same internal value is specified more than once in the list, the first item in the list is chosen for translation on output.

If the BASETYPE of this class is BIN, as specified on the class definition (CLASS) tag, the value may be specified in either integer or hexadecimal notation. If the BASETYPE specified on the CLASS tag is CHAR, IGC, DATE, TIME, NAME, or OBJNAME, the value may be specified in either string or hexadecimal string notation. Strings are implicitly padded on the right with blanks, but no implicit padding is done for hexadecimal notation.

If the internal value is specified in string or hexadecimal notation, the value must be enclosed in quotation marks in addition to apostrophes. For example, an internal value of ***YES** must be specified as VALUE="*YES".


Omitting the VALUE attribute leaves the internal dialog variable value unchanged when the user enters the *displayed-value* specified as tag content after the period. A TI tag of this type has no effect on the way internal values are presented to the user for display.

Optional Text

displayed-value

The value appearing on the panel or entered by the user. The comparisons done by the UIM to determine what internal value to use for an external value specified by the user may be changed by the CASE and BLANKS attributes of the CLASS tag. If the same external value appears more than once in the list, the first item is used for translation on entry. If no value is specified, a display value of blanks is used.

TL (Translation List)



The translation list (TL) tag allows the specification of a translation list for a class, shielding the variable pool from the values actually entered on the display. Values with a BASETYPE of CHAR, IGC, DATE, TIME, NAME, OBJNAME, or that are numeric on the class definition (CLASS) tag can have a translation list. Only one translation list is allowed for each class. Translation occurs before any validity checks are performed.

Other tags can be nested within the TL and ETL tags. These tags are listed in the following table. This table defines the order in which the tags must appear and specifies on which page more information can be found for each tag.

Table A-33. Tag Allowed Between the TL and ETL Tags

Tag Name	Order	Page
TI (Translation list item)	1	A-151

Optional Attributes

CASE=UPPER | MIXED

UPPER indicates that lowercase characters (a through z) in an input field value are converted to uppercase characters (A through Z) before comparison to the external value for each translation list item. This conversion to uppercase occurs after any conversion for the CASE attribute on the CLASS tag, but has no effect on the value assigned to the dialog variable or list entry if no matching translation list item is found. It also does not change the external display value specified on each translation list item (TI) tag; the text on the TI tag must be specified in uppercase to get a match.

MIXED indicates that an input value is compared as it is entered with the external value specified on each TI tag.

MSGID=message-identifier

The message identifier of the message sent if the translation fails because the user entered a value not specified in the list. If this attribute is not specified, the UIM assumes that the entered value is valid as it is entered and passes the value on to validity checking for the class.

MSGF='qualified-message-file-name'

The message file containing the message sent for this error if the translation fails. If the DFTMSGF attribute is not specified on the panel group (PNLGRP) tag, this attribute must be specified if the MSGID attribute is specified on this tag.

Examples: Translation List

This example shows how a translation list is defined.

UIM Source

```
:tl msgid=MMM0001 msgf='*LIBL/QCPFMSG'.
:ti value=1.Blue
:ti value=1.BLUE
:ti value=2.Red
:ti value=2.RED
:ti value=3.Green
:ti value=3.GREEN
:ti value=4.Turquoise
:ti value=4.TURQUOISE
:etl.
```


On entry, *Blue*, due to the default CASE=UPPER and the uppercase version of the translation item, is mapped to the value 1. On output, 1 is mapped to the value *Blue*, which is mixed case, because the first matching translation list item is always used. Notice that because the integer notation is used for the value, the BASETYPE on the CLASS tag that this translation list applies to must be numeric.

| This is an example of a class definition and a
| translation list for a dialogue variable that allows a
| valid OS/400 library name (*LIBL, *CURLIB, or
| blanks).

| **UIM Source**

```
| :class name=objlibc  
|         basetype='objname 10'.  
| :tl.  
| :ti value='*LIBL'.*LIBL  
| :ti value='*CURLIB'.*CURLIB  
| :ti value=' ' ' '.  
| :etl.  
| :eclass.
```

TOPINST (Top Instruction)



The top instruction (TOPINST) tag of an area specifies the top instruction lines. This tag is valid for all areas, but is allowed only for display panels. It appears immediately after the introducing tag for the area.

Multiple top instruction tags may be used to present multiple lines of instructions if the TOPINST tag contains *instruction-text*. If multiple TOPINST tags are coded, no blank lines appear between the text on different tags. Only one top instruction tag is allowed per area if an INST attribute variable is used for this tag.

For menus, a blank line is always left between the body and the instruction lines area. For more information about how instruction lines are formatted with respect to the body of certain areas, see the BODYSEP attribute in “DATA (Data Presentation Area)” on page A-29.

If no TOPINST tag is specified for an area, no text is used for the instruction line and the line is not allocated in the area.

Optional Attribute

INST=dialog-variable-name

The name of a dialog variable containing the top instruction text displayed. The dialog variable must be defined with a width less than or equal to the width specified on the panel tag

minus two. If this attribute is used, no *instruction-text* can be specified for this tag.

Dialog variables must be defined with a BASETYPE of CHAR, IGC, or BIN on the class definition (CLASS) tag.

The error state of the dialog variable is not used for determining the highlighting of the text.

Special formatting for IGC. The abbreviation IGC is used in commands and keywords to represent double-byte character set (DBCS) functions. When a dialog variable with a BASETYPE of IGC is specified on the CLASS tag, the UIM does special formatting. If the variable value begins with a shift-out character (X'0E'), the UIM shifts the value 1 byte to the left to preserve vertical alignment with other lines.

Optional Text

instruction-text

The text appearing as top instructions for the area. The text is an implied paragraph. When the display is formatted, any text that does not fit onto one display line is formatted onto additional lines as necessary and indented two positions. The text can be a maximum of 255 characters, and can only contain the reverse text (RT) tag. The *instruction text* is required unless the INST attribute is specified on this tag.

TT (Truth Table)

```
►►:TT—NAME=truth-table-name—CONDS='condition-name-list'—.:ETT.◄◄
```

The truth table (TT) tag begins the definition of a truth table used by the compiler when processing panel definitions. The TT tag must occur in the prolog section of the panel group after the condition definition (COND) tags and before any menu bar (MBAR) tags. You should use a truth table to assert to the UIM which conditions are mutually exclusive.

During compilation of a panel group, a panel is formatted once for each row of a truth table. Using the truth value for each condition, the compiler checks if the panel definition is valid. If a panel element is conditioned using the COND attribute on this tag, and if that condition is not mentioned in the truth table, it is assumed to have a true value by the compiler.

The name of a truth table must be specified on the TT attribute of the display panel (PANEL), print panel (PRTPNL), or print head panel (PRTHEAD) tag for the compiler to use the truth table for panel verification.

After the compile, if the truth table is wrong and the conditioning causes more panel elements to be active in an area than can be displayed, only the elements that fit are displayed, and no exception is reported.

Other tags can be nested within the TT tag. These tags are listed in the following table. This table defines the order in which the tags must appear and specifies on which page more information can be found for each tag.

Table A-34. Tag Allowed Between the TT and ETT Tags

Tag Name	Order	Page
TTROW (Truth table row)	1	A-156

Required Attributes

NAME='*truth-table-name*'

The name of the truth table. For more information on the rules for naming, see "Name Syntax" on page A-4. This name is referred to by all panels which use this truth table for compile-time checking. This name must be unique within the panel group.

CONDS='*condition-name-list*'.

A list of condition names separated by blanks. Each condition in the list must have been previously defined with the COND tag. The rows of the truth table are defined with the truth table row (TTROW) tag. Each item in the VALUES attribute of the TTROW tag corresponds positionally with the condition specified in this attribute. A maximum of 50 condition names can be specified.

Example: Truth Table

If conditions A, B, and C are known to be mutually exclusive on panel X, this example would illustrate how to assert this to the compiler.

UIM Source

```
:tt name=tt1 conds='A B C'.
:ttrow      values='1 0 0'.
:ttrow      values='0 1 0'.
:ttrow      values='0 0 1'.
:ett.
```

TTROW (Truth Table Row)

►►:TTROW—VALUES='condition-value-list'—◄◄

The truth table row (TTROW) tag defines a row in a truth table used by the compiler when processing panel definitions. The TTROW tag must occur between the truth table (TT) and ETT tags in the prolog section of the panel group.

During compilation of a panel group, a panel is formatted once for each row of a truth table, and the truth value for each condition is used to check if the panel definition is valid. A truth table can describe which of the conditions that control the formatting of a panel are mutually exclusive. If a condition is used within the panel definition and is not mentioned in the truth table, it is assumed to be true for the purposes of compile time checking; this is the same as specifying an asterisk (*) in the VALUES attribute on this tag.

VALUES='condition-value-list'.


The value of each condition used by the compiler to check the panel definition. Each item in the VALUES attribute of the TTROW tag corresponds positionally with the condition specified in this attribute. The following values can be used for the condition:

- 0** The condition is false.
- 1** The condition is true
- *** No truth value is specified. The compiler assumes the value is true for a worst case.

The items in the list of condition values are separated by blanks. The number of items in the list must equal the number of items in the CONDS attribute of the TT tag.

Required Attribute

UL (Unordered List)



The unordered list (UL) tag identifies an unordered list of items. The UL tag requires a matching end tag. These tags are only allowed in information areas and help areas.

Unordered lists can occur anywhere in text and can be nested within other lists.

Note: Care should be taken when using the unformatted lines (LINES), figure (FIG), and example (XMP) tags within unordered lists, because text that does not fit on one line wraps to column one of the next line. Lines and figures start at the current left margin and examples are indented four spaces from the current left margin. The current left margin changes when nested lists are formatted. If there is help information containing the LINES, FIG, or XMP tag imbedded at various locations, including within lists, it may not look the same each time and can cause undesirable results.

Unordered lists are formatted as hanging, indented lists, with the item identifier at the current left margin. There are three levels of item identifiers for nested, unordered lists:

- Bullets (lowercase letter o)
- Hyphens (-)
- Dashes (--).

These levels are repeated for more than three levels of nested, unordered lists.

Other tags can be nested within the UL tag. These tags are listed in the following table. The table defines the order in which the tags must appear, indicates which tags can be used in display panels only, print panels only, or both (specified by a D, P, or B, respectively), and specifies on which page more information can be found for each tag.

When more than one tag is listed with the same order number, all tags of that number can be mixed in any order. However, a tag with a higher order number cannot precede a tag with a lower

order number. For example, a tag with an order number of three cannot precede a tag with an order number of one or two.

Table A-35. Tags Allowed Between the UL and EUL Tags

Tag Name	Order	Use	Page
FIG (Figure)	1	B	A-57
LINES (Unformatted lines)	1	B	A-75
XMP (Example)	1	B	A-164
NT (Note)	1	B	A-115
P (Paragraph)	1	B	A-119
PC (Paragraph continuation)	1	B	A-128
LP (List part)	1	B	A-105
OL (Ordered list)	1	B	A-116
SL (Simple list)	1	B	A-149
UL (Unordered list)	1	B	A-157
PARML (Parameter list)	1	B	A-126
DL (Definition list)	1	B	A-55

Optional Attribute

COMPACT

The list is formatted without a blank line between the items.

Required Tag

UL, LI Tags

:LI.*item-text*

The text for the list item. This text is preceded by the item identifier; the text is indented four spaces from the current margin.

Example: Unordered Lists

This example uses two unordered lists, one imbedded within the other. The second unordered list uses the COMPACT attribute.

UIM Source

Some normal text...


```
:ul.  
:li.First item (bullet)  
:ul compact.  
:li.First item (hyphen)  
:li.Second item (hyphen)  
:eul.  
:li.Second item (bullet)  
:eul.
```

Results

Some normal text...

- First item (bullet)
 - First item (hyphen)
 - Second item (hyphen)
- Second item (bullet)

VAR (Variable Definition)



The variable definition (VAR) tag declares a dialog variable in the panel group. The VAR tag does not allow nested tags and must be placed after the last class definition (CLASS) tag and before the first variable record definition (VARRCD) tag.

A value for each dialog variable exists in the variable pool for an application opened using this panel group. The dialog variables communicate values to and from panels when the panels are presented to the user. Dialog variable values are set and retrieved using the UIM application programming interfaces (APIs).

The VAR tag defines all Z-variables, as well as other dialog variables used by an application. Only variables defined by a VAR tag in the panel group source are available in an open application.

Required Attribute

NAME=*variable-name*

The name of a dialog variable. This name must be unique within the panel group. For more information on the rules for naming, see “Name Syntax” on page A-4.

Optional Attributes

CLASS=*class-name*

The name of the class to which this variable belongs. The class must have been previously defined in the panel group.

The class definition for all Z-variables is determined by the UIM, so this attribute cannot be specified on the VAR tag for a Z-variable. A class must be specified for other variables declared in the panel group.

ERRVAR=*error-status-variable-name*

The name of a dialog variable, automatically defined by the UIM with a BASETYPE of CHAR 1 on the CLASS tag. The error status variable must not be defined by another VAR

tag. This name must also be unique within the panel group.

This dialog variable contains the error status of the variable defined by this tag. This attribute is used with the Put Dialog Variable (QUIPUTV) API and the Get Dialog Variable (QUIGETV) API.

During the QUIPUTV API, the current value of the error variable determines the error status. A value of 1 indicates that the dialog variable specified on the NAME attribute on this tag is in error. A value other than 1 indicates that the dialog variable is not in error. If the error status variable is updated during the same QUIPUTV API request as its associated dialog variable, the new value of the error status variable is used.

During the QUIGETV API for either the NAME dialog variable or the ERRVAR dialog variable, the value of the error status variable is set to 1 if the dialog variable specified on the NAME attribute of this tag is in error. Otherwise, the value of the error status variable is set to zero.

Note: Simply updating the ERRVAR dialog variable does not set the error state of the dialog variable specified in the VAR attribute of this tag. The VAR dialog variable must be updated using the QUIPUTV API to change its error state.

The error dialog variable cannot be referred to any place in the panel group source where dialog variables can normally be specified.

Dialog Variables Defined by UIM

The UIM defines a set of dialog variables that can be automatically available in the variable pool for every open application. The variables must be defined using the variable definition (VAR) tag in order to be available in the variable pool. These variables can be referenced by user programs

(see the QUIGETV API) and in panel definitions, and some can be modified by user programs (see the QUIPUTV API) to control UIM processing functions. Dialog variables are not allowed for input fields on any panel.

All dialog variables defined by the UIM have names that begin with the letter Z. If you define a dialog variable for your application with the same name as a UIM dialog variable, you receive a warning message. The message states that you do not have access to the UIM dialog variable with the same name. However, you are allowed to use the dialog variable that you defined. The following is a description of all UIM-defined dialog variables:

ZCANCEL Indicates whether the CANCEL function is requested and is set as follows:

- 0 The CANCEL function was not requested.
- 1 The CANCEL function is requested.

This Z-variable can be changed by the calling (application) program using the QUIPUTV API. Changing this dialog variable results in changing the job's cancel flag. For more information on the cancel flag, see "Folding Up a List Panel" on page 17-23.

ZDBCS Indicates whether the job is currently in DBCS mode, and is set as follows:

- 0 The job is not in DBCS mode.
- 1 The job is in DBCS mode.

ZDSPSIZ Indicates the maximum size of the display that the device is capable of displaying and is set as follows:

- ***DS3** The largest size panel the device can display is 24 x 80.
- ***DS4** The largest size panel the device can display is 27 x 132. This device can also display panels of size 24 x 80.

ZEXIT Indicates whether the EXIT function was requested and is set as follows:

- 0 The EXIT function is not requested.
- 1 The EXIT function is requested.

This Z-variable can be changed by the calling (application) program using the Put Dialog Variable API service. Changing this dialog variable results in changing the job's exit flag. For more information on the job's exit flag, see "Folding Up Multiple Panels When EXIT Is Requested" on page 17-21.

ZJOB Simple name of the current job (the first qualifier of the job name).

ZJOBNBR Job number of the current job (the last qualifier of the job name).

ZLMTCBP Indicates the limits to which the user controls the initial program, initial menu, current library, and Attention key handling program values and is set as follows:

- ***NO**
- ***PARTIAL**
- ***YES**

ZMENU Name of the menu object currently displayed by the UIM. This dialog variable can be used only in definitions of *MENU objects.

ZMNULIB The name of the library that contains the menu object currently displayed by the UIM. This dialog variable can be used only in definitions of *MENU objects.

ZSYSNAM Current system name retrieved from the SYSNAM network attribute.

ZUSER User profile name for the current job (which is also the middle qualifier of the job name).

Z36ENV Indicates whether the job is currently running in the System/36 environment and is set as follows:

- 0 The job is not running in the System/36 environment.
- 1 The job is running in the System/36 environment.

For a description of the characteristics (including external display form) for the base type of each Z-variable, see "CLASS (Class Definition)" on page A-14.

Table A-36. Attributes of UIM-Defined Variables (Z-Variables)

Name	Base Type	Length	Program Modifiable	Description
ZCANCEL	CHAR	1	Yes	Indicates whether the CANCEL function is required
ZDBCS	CHAR	1	No	Indicates whether the job is in DBCS mode
ZDPSIZ	CHAR	4	No	Indicates the maximum size of display
ZEXIT	CHAR	1	Yes	Indicates whether the EXIT function is requested
ZJOB	OBJNAME	10	No	Job name of the current job (first qualifier)
ZJOBNBR	CHAR	6	No	Job number of the current job
ZLMTCPB	CHAR	10	No	Limits the capabilities the user has
ZMENU	OBJNAME	10	No	Name of the menu object
ZMNULIB	OBJNAME	10	No	Name of the library containing the menu object
ZSYSNAM	CHAR	8	No	Current system name
ZUSER	OBJNAME	10	No	User profile name
Z36ENV	CHAR	1	No	Indicates if running in the System/36 environment

VARRCD (Variable Record Definition)

```

▶▶:VARRCD—NAME=variable-record-name—VARS='variable-list'————▶▶
▶▶└─NOPUT='variable-list'└─NOGET='variable-list'└─.————▶▶

```

The variable record definition (VARRCD) tag does not allow nested tags, and must be placed after the last variable definition (VAR) tag and before the first list definition (LISTDEF) tag.

When data is passed between a calling program and the variable pool, a variable buffer is used. The variable buffer contains values for one or more dialog variables. A VARRCD tag defines which dialog variables are in the variable buffer as well as the sequence the variables appear in the variable buffer.

The VARRCD tag must be used to define a variable record definition for use with the Get Dialog Variable (QUIGETV) API and the Put Dialog Variable (QUIPUTV) API requests. Only variables defined by a VAR tag in the panel group source may appear in the variable record definition.

Required Attributes

NAME=*variable-record-name*

The name of a variable record definition. This name must be unique within the panel group. For more information on the rules for naming, see “Name Syntax” on page A-4.

VARS=*'variable-list'*

A list of up to 256 dialog variables which make up the variable record. All dialog variables in this variable list must be previously defined using the VAR tag. The dialog variable names in the list are separated by one or more blanks.

The order in which the variable names appear in the variable list is the order the variable values must appear in the variable buffer of the calling program when the QUIPUTV and QUIGETV APIs are called.

The variables must appear contiguously in the variable buffer for the calling program. The

UIM makes no boundary alignment adjustments when calculating the offsets to variables within the buffer.

If any read-only Z-variables are listed in the VARS attribute of this tag, they must also appear in the NOPUT attribute of this tag.

Optional Attributes

NOPUT=*'variable-list'*

A list of up to 256 variables which should not be processed when the QUIPUTV API is requested. All variables in this variable list must appear in the variable list specified on the VARS attribute of this tag. The variable names in the list are separated by blanks.

Using this attribute, you can specify that only a subset of the variables in the variable buffer should be copied to the variable pool during the QUIPUTV API.

If this attribute is not specified, all variables specified on the VARS attribute of this tag are copied from the variable buffer to the variable pool during the QUIPUTV API.


NOGET=*'variable-list'*

A list of up to 256 variables which should not be processed when the QUIGETV API is requested. All variables in this variable list must appear in the variable list specified on the VARS attribute of this tag. The variable names in the list are separated by blanks.

Using this attribute, you can specify that only a subset of the variables in the variable buffer should be copied from the variable pool during the QUIGETV API.

If this attribute is not specified, all variables specified on the VARS attribute of this tag are copied from the variable pool to the variable buffer during the QUIGETV API.

XH1 through XH4 (Extended Help Headings)



The extended help heading (XH1-XH4) tag identifies the heading used over contextual help when it is displayed as part of an extended panel help, including help for index search topics. This tag must appear within a help module (HELP) tag and EHELP boundary and is not allowed on the information (INFO) tag. The text associated with this tag is used as the heading text.

This tag allows headings to appear with help information, based on whether the text is displayed for extended panel help or for contextual help. The text from XHn tags always appears in extended panel help. The text also appears in contextual help if any tag containing help information precedes the XHn tag, or the contextual help is displayed in a full screen and no help panel title is specified on the HELP tag.

In all cases of contextual help, with the exception of the two previously mentioned, the text from the XHn tag does not appear when the XHn tag is the first tag used for contextual help.

Required Text

extended-help-heading-text

The text associated with this tag is used as a heading when the help item is used in extended panel help. The text must be on the same or next line as the period ending the tag.

Formatting Rules

Headings have one blank line formatted before and after them. The heading tag generates a blank line before the heading, and the tag following the heading generates the space after the heading.

Specific formatting rules follow:

XH1 Centers, underscores and highlights text (HP3). This tag causes a page eject when it appears in a printed help module.

XH2 Left-justifies, underscores, and highlights text (HP3).

XH3 Left-justifies and highlights text (HP2).

XH4 Left-justifies and underscores text (HP1).

Example: Sample Headings

This example shows how extended help headings are highlighted and justified.

UIM Source

```
:XH1.Main Subject
:p.Here's a paragraph.
:XH2.Topic
:p.Another paragraph.
:XH3.Subtopic
:p.Still another paragraph.
:XH4.A Four Heading
:p.Still another paragraph.
```

Results:

Main Subject

Here's a paragraph.

Topic

Another paragraph.

Subtopic

Still another paragraph.

A Four Heading

Still another paragraph.

XMP (Example)

►►:XMP.—:EXMP.◄◄

The example (XMP) tag identifies an example of computer input or output. The XMP tag requires a matching end tag. These tags are only allowed in information areas and help areas.

Examples can occur anywhere in text, except in other examples. The body of an example is composed of the text between the XMP tag and the EXMP tags.

The normal formatting of text is suspended within an example; that is, the lines are not concatenated.

Note: Care should be taken when using examples within lists, because example text that does not fit on a line wraps to column one of the next line. The current left margin changes when nested lists are formatted. If there is help information containing examples imbedded at various locations, including within lists, it may not look the same each time and can cause undesirable results. An example is indented 4 spaces from the current margin. Help modules displayed in full-screen format or in an extended help window

are indented by 4 bytes. Therefore, the formatting width initially is 10 bytes less than the width specified on the help module. When the XMP tag appears in an information area, the formatting width initially is 6 bytes less than the width specified on the panel tag.

Example: Formatting an Example

This example illustrates how to use an example.

UIM Source

```
Some normal text...
:xmp.
This is an example
right here
:exp.
```

Results:

```
Some normal text...
This is an example
right here
```

Appendix B. UIM Dialog Commands

Dialog commands are special functions, recognized only by the UIM, that equate actions entered by a user with screen management functions. Dialog commands differ from CL commands in that they cannot be entered on a command line nor are they valid outside the scope of the UIM.

Exactly what function the UIM performs for each dialog command depends largely on the type of screen being presented and other attributes defined by the function key, key list item (KEYI), menu item (MENU), list action (LISTACT), or pull-down field choice (PDFLDC) language tags. For more information on the language tags, see Appendix A, "UIM Panel Group Definition Language" on page A-1.

Some dialog commands are defined in terms of the content of the current command line, the position of the cursor, and the type of screen. Dialog commands also affect messages specified by the application, by the condition evaluation, and by calling the general exit. For example, some dialog commands cause condition evaluation to be

bypassed, while others cause the calling of the general exit to be bypassed.

Dialog commands can be assigned to the following:

- Menu items
- Function keys
- Options on action lists
- Hypertext links
- Pull-down field choices
- ENTER and SELECT attributes of the PANEL tag

Not all dialog commands are allowed in all of these situations. For example, the dialog commands PAGEUP and PAGEDOWN cannot be assigned to options of an action list because they apply to the entire screen, and not to an individual list entry.

For a summary of the valid uses of the dialog commands, see Table B-1 on page B-2. For a summary of the effect of the different dialog commands, see Table B-2 on page B-3. Later in this appendix, there is a detailed description of each dialog command.

Dialog Commands

Table B-1. Summary of the Valid Uses of Dialog Commands

Dialog Command Name	Valid Uses						
	Function Key	Pull-down Menu Choices	Menu Item	List Action	ENTER on PANEL Tag	SELECT on PANEL Tag	Hypertext Link Action
ACTIONS	X					X ³	
CALL	X	X	X	X	X		
CANCEL	X		X				
CHGVIEW	X	X ²					
CMD	X	X	X	X	X		
CMDLINE	X	X ²					
DSPHELP		X ²					X
ENTER	X						
EXIT	X	X ²	X				
EXTHelp		X ²					
HELP	X						
HELPHELP		X ²					
HELPIDX		X ²					
HOME	X						
KEYSHelp		X ²					
MENU	X	X ²	X				
MOREKEYS	X						
MOVETOP	X						
MSG					X	X	
PAGEDOWN	X						
PAGEUP	X						
PRINT	X						
PROMPT ¹	X						
PULLDOWN						X ³	
RETRIEVE	X	X ²					
RETURN	X	X	X		X	X	

Notes:

- ¹ PROMPT becomes CALL or RETURN when processing a cursor-sensitive prompt defined by the PROMPT attribute of a DATAI, DATAIX, or LISTCOL language tag.
- ² Valid only when ACTFOR=PANEL is specified on the PDFLDC tag.
- ³ Valid only when MBAR attribute is specified on the PANEL tag.

Table B-2. Summary of the Effects of Dialog Commands

Dialog Command Name	Effects			
	VARUPD on KEY1 or PDFLDC Tag ¹	Stop Displaying User Messages ²	Evaluate Conditions	Call General Exit
ACTIONS	No	No	No	No
CALL	Yes or No	Yes	Yes	Yes
CANCEL	Yes or No	Yes	N/A	Yes
CHGVIEW	Yes	Yes	Yes	Yes
CMD	Yes or No	Yes	Yes	Yes
CMDLINE	No	No	No	No
DSPHELP	No	No	No	No
ENTER	Yes	N/A ³	N/A ³	N/A ³
EXIT	Yes or No	Yes	N/A	Yes
EXTHelp	No	No	No	No
HELP	No	No	No	No
HELPHELP	No	No	No	No
HELPIIDX	No	No	No	No
HOME	Yes	Yes	Yes	Yes
KEYSHELP	No	No	No	No
MENU	Yes	Yes	Yes	Yes
MOREKEYS	No	No	No	No
MOVETOP	Yes	No	No	No
MSG	N/A	Yes	Yes	Yes
PAGEDOWN	Yes ⁶	No	No	Yes ⁶
PAGEUP	Yes ⁶	No	No	Yes ⁶
PRINT	No	No	No	No
PROMPT ⁵	Yes or No	Yes	Yes	Yes
PULLDOWN	No	No	No	No
RETRIEVE	No	No	No	No
RETURN	Yes or No	Yes	N/A	Yes
Default ⁴	N/A	Yes	Yes	Yes

Notes:

¹ VARUPD attribute applies only when the action is assigned to a function key or pull-down choice. When ACTFOR=LIST is specified on the PDFLDC tag, VARUPD is YES.

² The UIM stops displaying messages generated by an application when another function is about to start. HELP can become a function if the help is for a command and the user directly starts the prompt and processing of the command from the help screen.

³ These ENTER values are not applicable (N/A) because ENTER always equates with another function by the time these actions are performed.

⁴ The UIM displays the panel again for the default ENTER or SELECT action.

⁵ PROMPT becomes CALL or RETURN when processing a cursor-sensitive prompt defined by the PROMPT attribute of a DATAI, DATAIX, or LISTCOL language tag.

⁶ When PAGEUP and PAGEDOWN apply to the message area, an information area, or a menu area, these values are not applicable.


The VARUPD Attribute

One of the main qualifiers of a function is the VARUPD attribute of the KEYI (key list item) and PDFLDC (pull-down field choice) language tag. This attribute defines whether or not dialog variables and list entries should be updated with

values entered by the user. It also defines whether the function associated with the key should be processed if errors are detected while validity checking the values of input fields on the display. Most dialog commands assume a particular value for VARUPD that cannot be overridden by the panel definition. The following is a summary of the effect of VARUPD:

Type of Action	Effect of VARUPD Attribute	
	VARUPD=YES	VARUPD=NO
Returning control to the application that called the QUIDSPP API.	All validity checking is performed, and dialog variables and list entries are updated when correct. When one or more variables fail the validity checking, the panel is displayed again with error messages.	No validity checking is performed and no updates are made to the dialog variables and list entries. Changes made to the input field by the user since the last operation are lost. The values entered by the user can sometimes be recovered by calling QUIDSPP and specifying yes on the redisplay parameter. For more information, see the <i>System Programmer's Interface Reference</i> .
An action performed under the control of the UIM <i>without</i> returning to the application	All validity checking is performed, and dialog variables and list entries are updated when correct. When one or more variables fail the validity checking, the panel is displayed again with error messages.	No validity checking is performed and no updates are made to the dialog variables and list entries. Contents of the input fields are saved by the UIM and are used when displaying the panel again, providing updates have not been made that make the saved values obsolete. For example, changing a dialog variable that was displayed on the saved panel causes the saved value to be discarded and the new value shown when the panel is displayed again.

ACTIONS (Menu Bar Cursor Action)




Alternates the cursor position between the panel and the menu bar. The Common User Access (CUA) guidelines recommend this function be assigned to F10.

When the ACTIONS function key is pressed, the UIM saves the information where the cursor was located and moves the cursor to the first choice on the menu bar. If the ACTIONS function key is pressed again, the cursor returns to its previous location before it was moved to the menu bar. If the user moves the cursor to the menu bar area using the cursor movement keys (arrow keys) and

then presses the ACTIONS function key, the UIM determines the best position for the cursor.

Messages: No messages are issued by the UIM during processing.

CALL (Call Program)



Calls an application program and allows applications to link programs and screens together.

The call function calls by address, by name, or by an extended program model (EPM) call.

For best performance, use call by address. If call by address is not feasible, use the call by name or an EPM call with a library qualified program name (do not use *LIBL).

For a description of the interface between the UIM and the program being called, see the section called "User Interface Management EXIT Program" in the *System Programmer's Interface Reference*. The CALL dialog command can be used with the following:

- Menu item action
- Function key action
- Action list option
- Action list exit
- General panel exit
- Default enter action
- Application format exit
- Contextual prompt exit
- Pull-down choice action

The CALL dialog command cannot be used on menu objects created using the Create Menu (CRTMNU) command, but can be used within a panel group object created using the Create Panel Group (CRTPNLGRP) command. If calling a program is the desired result of a menu option in an external menu, use the CMD dialog command to submit the CALL CL command. The user must have the proper authority to the CALL CL command and the program being called.

Required Parameter

dialog-variable-name

Specifies a dialog variable containing the call information as described below for each of the three types of call.

Call by address

This type of call is used within OS/400 system programs to allow calls of other system modules. Define the specified dialog variable with BASETYPE='PTR'. When the call function is requested, the dialog variable must contain a system pointer to the program. Ensure the proper authority is contained in the pointer.

Call by name

Allows calling an application program using a qualified name of a program object. Define the specified dialog variable with BASETYPE='CHAR 20'. When the call function is requested, the first 10 characters of the dialog variable must contain the name of the program object. The second 10 characters must contain the name of the

library where the program resides. The program and library names should be left justified and put in uppercase unless a quoted object name is used.

Call by extended program model (EPM)

This type of call allows calling an entry point in an EPM language program. The UIM uses the QPXXCALL interface to make the call. Define the specified dialog variable with BASETYPE='CHAR 130'. When the call function is requested, the dialog variable must contain the following:

Characters Contents

1-20	The name of the EPM program object and the name of the library that the object resides in
21-120	The name of the external entry point to be called
121-130	The name of the environment to which the entry point belongs

Because UIM is simply passing this information to the QPXXCALL language interface program, ensure that the contents of the dialog variable adhere to the requirements defined by QPXXCALL. When UIM calls the QPXXCALL program, the EPM environment is implicitly started and remains active until explicitly deleted. For more information, see the *Extended Program Model User's Guide and Reference*.

Note: There is a high performance overhead for calling an EPM program. If possible, call by address or call by name instead. The support for calling an EPM program is provided for cases where, due to application design, an EPM program is used as the target of the CALL dialog command.

VARUPD Value: The CALL dialog command does not have a predefined VARUPD value. When CALL is assigned to a function key, the VARUPD value of the function key dictates whether or not to perform validity checking and then updates the dialog variables.

CHGVIEW Command


Messages: The following errors may be encountered during processing:

- Program not found.
- Not authorized to specified program.
- Number of parameters for specified program is not valid.
- Program saved with STG(*FREE).
- Any exception signalled by the QPXXCALL language interface program.

The UIM does not stop processing if these errors occurred on a call for the general panel exit, on a call for the list action exit, and on application formatted area calls.

For all other types of calls, the UIM ends the action it was performing. In most cases, this involves displaying the panel again with an error message indicating that the program call was not successful.

CANCEL



Backs up one screen and is used with a menu item action or a function key action.

If the current screen was called by the QUIDSPP API, the function parameter contains an indication that CANCEL was requested.

If the current screen is a menu called from the previous screen via the menu fast-path function (for example, entering GO on the command line), the UIM displays the previous screen.

Optional Parameter

NOSET|SET

Indicates whether the cancel flag is set.


NOSET means that the cancel flag is not set; this is the default value. SET means that the cancel flag is set. For more information on the cancel flag, see "Folding Up a List Panel" on page 17-23.

VARUPD Value: CANCEL does not have a pre-defined VARUPD value. When CANCEL is assigned to a function key, the VARUPD value of the function

key determines whether or not to perform validity checking and then updates the dialog variables.

Messages: No messages are issued during processing.

CHGVIEW (Change View)



Changes the displayed view of a list and can only be assigned to a function key or a pull-down field choice action.

If there are several columns of information that a user needs to see, and all the columns do not fit on the display, you can change the view so the user sees one set of columns and then another set of columns. This continues until all the columns of information are viewed.

You can specify several different ways to present a list area on the LISTVIEW language tag and which columns belong to each view. List views are numbered sequentially starting with 0. For example, if a list area has five presentation views, the views are numbered from 0 to 4. The first LISTVIEW tag in the panel source for the list area defines view 0, the second LISTVIEW tag in the panel source for the list area defines view 1, and so on for all LISTVIEW tags in the list area.

With the CHGVIEW dialog command, you can switch views. The function operates in a circular fashion. For example, if the current view is 3, CHGVIEW presents view 4 (if there is a view 4), or back to view 0 if there is not a view 4. Applications can specifically select a view by changing the dialog variable coded on the VIEW attribute of the LIST tag. The UIM also modifies this dialog variable whenever the CHGVIEW dialog command is performed.

Which list the request applies to depends on the cursor position. The rules are very similar to those for the PAGEDOWN and PAGEUP dialog commands.

- If the cursor is in a list area defined as having multiple views, the request applies to that area.

- If the cursor is not in a list area defined as having multiple views, the request applies to the first list area on the screen that does have multiple views.


Parameters: None

VARUPD Value: The CHGVIEW dialog command always operates with VARUPD=YES and the following occurs:

- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking prevent changing the view and the screen is displayed again with the appropriate error messages.

Messages: No messages are issued during processing unless there are errors from a validity check.

CMD (System Command)



Submits a CL or OCL command to the system command.

Parameter

command-text

All text following the CMD dialog command is treated as a command and is submitted to the system for processing. Whether the command is native or System/36 environment is determined by the system, not by the UIM.

The command string may contain the names of dialog variables to be substituted into the command string before the UIM submits the command to the system. Each dialog variable name must be preceded by an ampersand (&) and followed by a period (.). Although the ending period is not required, its use is recommended to avoid ambiguity.

Before submitting the command, the UIM performs substitution for dialog variables. Each dialog variable specified as part of the command string is replaced by its displayable value. This value is always calculated from the current value of the dialog variable.


VARUPD Value: The CMD dialog command does not have a predefined VARUPD value. When CMD is assigned to a function key or pull-down field choice, the VARUPD attribute on the KEY1 or PDFLDC language tag dictates whether or not to perform validity checking and then updates the dialog variables. Because substituting commands depends on the values of dialog variables, care should be taken when using VARUPD=NO.

Messages: No messages are issued during processing unless there are errors from a validity check.

Hint: Because these commands are not logged to the job log, it is sometimes difficult to discover and correct command syntax errors. One way to see the command after all dialog variables have been substituted is to make the command the value of the message on a SNDMSG command as follows:

SNDMSG MSG (command here) TOUSR (*REQUESTER)

CMDLINE (Command Line)




Displays a pop-up window containing a command line on the bottom of the display.

Parameters: None

Messages: No messages are issued during processing.

DSPHELP (Display Help)



Displays a specified UIM help module.

Required Parameter

help-module-name

Specifies the name of the help module to be displayed.

Optional Parameter

qualified-panel-group-name


Specifies the name of the panel group containing the help module. If it is not specified, then 1) the help module must be from the same panel group that contains the DSPHELP dialog command, or 2) the help module must be imported from another panel group by using an IMPORT tag.

product-library

Specifies the name of a library which becomes the product library when the help module is displayed. This parameter is only used when the DSPHELP dialog command is used for a hypertext link action.

Messages: No messages are issued during processing.

ENTER



Allows processing of an action and is only allowed on the Enter key.

For more information, see “Considerations for Using the ENTER, HELP, and PROMPT Dialog Commands.”

Parameters: None

VARUPD Value: The ENTER dialog command always operates with VARUPD=YES and the following occurs:

- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking stop the operation. The display is shown again with the appropriate error messages.

Messages: Any messages resulting from submitting or canceling the commands are displayed on the message line. Additional messages can be sent if validity-checking errors are encountered.

Considerations for Using the ENTER, HELP, and PROMPT Dialog


Commands: The actions performed for ENTER, HELP, and PROMPT depend heavily on the type of display and contents of the command line. These dialog commands can be assigned only to function keys, and they have different characteristics than other dialog commands. These dialog commands are more like action qualifiers; things used to determine or modify a more concrete action like a system command string.

For example, an action list panel describes several actions that are performed, based on the contents of various fields. The ENTER and PROMPT dialog commands, and to a lesser extent HELP dialog commands, are initially requested, but serve only to describe how the rest of the panel is interpreted. They are not sufficient by themselves to describe what should be done.

Some important aspects to remember when reading descriptions of these dialog commands are:

- A menu with a command line can contain a selection from a menu item or a command. If the first nonblank character string is unquoted and contains only numeric values, it is interpreted as a menu item. Otherwise, it is assumed to be a command.
- An action list with a command line can contain parameter strings or commands. If any entry on an action list is selected, any string in the command line is treated as a parameter list. Otherwise, it is treated as a command.

EXIT (Exit Display)



- Allows the user to back out of groups of displays.
- If the current display was displayed using QUIDSPP API, the UIM sets the function requested parameter indicating that the EXIT dialog command was requested. It is up to the application to determine what must be done next.

- | If the current display is a menu called from a series of displays, the UIM presents the display where the MENU command was initially requested. The EXIT dialog command backs completely out of a series of menus.

Optional Parameter


NOSET|SET

Indicates whether the job's exit flag is set. NOSET means that the exit flag is not set; this is the default. SET means that the exit flag is set. For more information on the exit flag, see "Folding Up Multiple Panels When EXIT Is Requested" on page 17-21.

VARUPD Value: The EXIT dialog command does not have a predefined VARUPD value although the user interface style implies VARUPD=NO should normally be used. When EXIT is assigned to a function key or pull-down choice, the VARUPD value of the function key dictates whether or not to perform validity checking and then updates the dialog variables.

Messages: No messages are issued during processing.


EXTHELP (Extended Help)



Displays the extended help for the panel.

Parameters: None

HELP



Displays help information. The Common User Access (CUA) guidelines recommend assigning this to the Help and F1 keys.

The specific action taken (and help text displayed) depends on the screen type, cursor position, and so on. For the UIM rules, see "Defining Contextual Help" on page 17-14, and for more information on the specific attributes, see "Considerations

for Using the ENTER, HELP, and PROMPT Dialog Commands" on page B-8.


Parameters: None

VARUPD Value: It is always VARUPD=NO. No validity checking is performed on the current contents of the current panel and no updates to dialog variables are made.

Messages: The message Help information is not available can be issued during processing and can occur if the user chooses to delete or not install help text supplied by the system.

Additional messages are also possible when help is requested for a specific command on a command line. Possible messages might be that the command does not exist, or the user might not have authority to it. If these messages are issued, they appear as the first message in the message area. Messages describing other conditions on the screen can still be viewed by scrolling forward.

HELPHELP




Displays information about how to use the help facilities for contextual help, extended help, help on function keys, and the help index from help panels. The HELPHELP dialog command can be coded only on pull-down choices for menu bars.

Parameters: None

Messages: No messages are issued during processing.

HELPIDX




- | Begins the InfoSeeker function for the SCHIDX attribute specified on the panel group tag. Users may select a topic in the index to be displayed or printed. The printed HELPIDX dialog command can be coded only on pull-down choices for menu bars.

MOREKEYS Command

Parameters: None

Messages: No messages are issued during processing.

HOME (Display Home Menu)



Displays the job's home menu. This menu is added to the stack of menus. It does not imply returning to the beginning of the stack of menus. The HOME dialog command can be used with a menu item and function keys.


Parameters: None

VARUPD Value: The HOME dialog command always operates with VARUPD=YES and the following occurs:

- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking prevent the operation and the screen is displayed again with the appropriate error messages.

Messages: No messages are issued during processing.


KEYSHELP



Displays the help for the function keys on the displayed panel. The Common User Access (CUA) guidelines recommend assigning this to the F1 key.

Messages: No messages are issued during processing.

MENU



Displays a subsequent menu as a result of selecting a menu item or pressing a function key.

Required Parameter

qualified-menu-name

Specifies the qualified name of the menu to be displayed.

Optional Parameter


RTNPNTINORTNPNT

This parameter indicates whether the current menu is considered a return point when the dialog command is requested. This parameter functions the same as the return point (RTNPNT) parameter of the GO CL command. RTNPNT indicates that the current menu is returned when the Exit key is pressed; this is the default. No return point (NORTNPNT) indicates to not return to the current menu when the Exit key is pressed.

This parameter has no effect when it is coded in a panel group object using the Create Panel Group (CRTPNLGRP) command. It is meaningful only when it is used in a menu object created using the Create Menu (CRTMNU) command.

Messages: No messages are issued during processing.

MOREKEYS (Display More Function Keys)



Displays an additional list of active function keys when they cannot all fit on the panel. The action of the MOREKEYS dialog command can be assigned only to Function Key F24. When it is, it cannot be conditioned using the COND attribute of the key item (KEYI) language tag.

If an application codes ACTION=MOREKEYS on the KEYI tag, the UIM manages the situation if all of the function key descriptions do not fit on the panel at once.

When a panel is displayed with a KEYL (Key List) language tag using the MOREKEYS dialog command, the UIM gathers a list of all currently active function keys. This is based on the priority assigned to each key item on the PRIORITY attribute of the KEYL language tag. The UIM attempts to fit as many of the function keys as possible in the function key area of the panel.

If not all of the function key descriptions fit in the area, the UIM enables the function key assigned to the MOREKEYS dialog command and places the descriptions of the function keys on the panel. If all of the descriptions of the function keys fit, the function key assigned to the MOREKEYS dialog command is not enabled.


If a user presses the function key assigned to the MOREKEYS dialog command, the UIM starts where it left off in the key list and gathers as many active descriptions of function keys that fit in the function key area in order of priority. The function key assigned to the MOREKEYS dialog command is enabled.

This process continues until the end of the key list is reached. If the MOREKEYS dialog command is selected again, the UIM starts back at the beginning of the key list and begins processing the MOREKEYS dialog command again.

Parameters: None

Messages: No messages are issued during processing.

MOVETOP (Move to Top)



Moves a cursor-selected line to the top of the scrollable information area.

When a function key assigned to this dialog command is pressed, the UIM moves the line containing the cursor to the top of the scrollable area. If the cursor is on a blank line inserted by the UIM (paragraph separators, and so on), the next line is moved to the top of the scrollable area.

The MOVETOP dialog command applies only to information areas, and is intended primarily to

allow users of online text to position the information in the most readable manner. For example, an entire chart positioned on one display is easier to read than a chart that appears on two displays.


Parameters: None

VARUPD Value: The MOVETOP dialog command operates with VARUPD=YES (except when scrolling the message line) and the following occurs:

- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking prevent the operation and the panel is displayed again with the appropriate error messages.

Messages: The UIM can issue Cursor not positioned on valid line.

MSG (Display Message)



Displays a message on the message line. It can only be assigned as the default enter action or the default selection action to perform when the Enter key is pressed, and the UIM cannot find any other specific function to perform.

One intended use of this dialog command is to inform the user that they must select an option or press a function key.

Required Parameter

message-id

Specifies the message identifier of the message to be displayed.

Optional Parameter


qualified-message-file-name

Specifies the qualified name of the message file containing the message. It defaults to the message file specified on the DFTMSGF attribute of the PNLGRP tag.

PROMPT Command

VARUPD Value: Because the MSG dialog command can only be specified on the ENTER attribute of the PANEL tag, VARUPD has no meaning. The VARUPD value is defined by the function key assigned to the ENTER action.

PAGEDOWN



Scrolls forward by one screen or panel and can be assigned to only a function key.


When processing incomplete lists, selecting scroll areas, and specifying VARUPD=YES, the process is the same for the PAGEDOWN dialog command as it is for the PAGEUP dialog command.

Parameters: None

Messages: UIM can issue Already at bottom of area.

Additional messages can be sent if validity checking encounters errors.

PAGEUP



Scrolls backward by one screen or panel and can be assigned to only a function key.

If a full scrollable area of data is available to the UIM, or the scrollable area is complete, scrolling is performed without intervention of the application. If the scrollable area is an action list with selected actions, none are performed at this time.

A special case exists where an incomplete list is displayed and the PAGEUP scroll results in an incomplete panel. In this case, the UIM calls the program specified to add additional list entries or mark the list complete.

For screens and panels with multiple scrollable areas, the position of the cursor determines what is scrolled. The rules are as follows:

- If the cursor is in a scrollable area, that area is selected. The message line is considered a scrollable area.

The boundaries of a scrollable area are defined by the top and bottom line of a menu, information, list, or data area, although not all information in that area (such as instruction lines) is actually scrolled.

- If the cursor is outside a scrollable area, the first scrollable area on the panel (top to bottom) is selected for scrolling.

Parameters: None

VARUPD Value: PAGEUP operates with VARUPD=YES except when scrolling the message line, and the following occurs:


- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking prevent scrolling and the panel is displayed again with the appropriate error messages.

When scrolling the message line, the PAGEUP dialog command operates as if VARUPD=NO is in effect. Fields need not be correct and dialog variables are not updated.

Messages: UIM can issue Already at top of area.

Additional messages can be sent if validity checking encounters errors.

PRINT (Print Display)




- | Prints the current display and can be assigned only to the 5250 PRINT key.

Parameters: None

VARUPD Value: Does not apply.

Messages: No messages are issued during processing unless errors are found during validity checking.

PROMPT



Prompts for commands, action list options, and entry fields and can be assigned only to function keys. Its specific function depends on the following:

- Type of screen being managed
- Location of the cursor
- Contents of the command or parameter line

Parameters: None

VARUPD Value: For more information, see “Prompting an Entry Field” and “Prompting an Action List Option or Command.”

Messages: Any messages resulting from submitting or canceling the commands are displayed on the message line. In addition, the UIM can issue the following messages:

- The prompt attempt for the menu item was not valid.
- Cursor is in a location where the prompt function is not allowed.

Additional messages can be sent if errors from validity checking are encountered.

Prompting an Entry Field: The prompt function becomes a CALL or RETURN function based on the prompt definition specified on the PROMPT attribute of the associated panel definition tag. Prompting an entry field should be assigned to the F4 key.

When prompting an entry field, VARUPD processing is done if it is specified on the definition of the function key.

If VARUPD=YES is specified for the function key, the following occurs:

- Validity checking is always performed
- Valid values are processed and the dialog variables are updated
- Any failures from validity checking prevent prompting and the panel is displayed again with the appropriate error messages.

If VARUPD=NO is specified for the function key, the application program can get access to the keyed data that is not verified by using the

DSPVALUE attribute of the tag where the prompt was defined.

For more information about entry field prompting, see the description of the PROMPT attribute for the following tags found in Appendix A, “UIM Panel Group Definition Language” on page A-1.

- Data item (DATAI)
- Data item Extender (DATAIX)
- List column (LISTCOL)

Prompting an Action List Option or Command:

When prompting an option on an action list or command line, the PROMPT dialog command always operates with VARUPD=YES and the following occurs:

- Validity checking is always performed.
- Valid values are processed and the dialog variables are updated.
- Any failures from validity checking prevent prompting and the panel is displayed again with the appropriate error messages.

The prompt function results in either submitting a command string to the system or calling an application program. This occurs according to the following rules:

- If the command line contains a menu item, an error is sent. The UIM does not support prompting for menu items.
- If the cursor is on the command line or in the option column and if the panel has an action list panel with options specified, the UIM selects the PROMPT action associated with each selected option. The PROMPT action can either be to submit a command to the system or to call an application program.

If an option is selected that does not have a defined prompt action, action list processing stops, and the panel is displayed again with an error message. The error message indicates that the user cannot prompt for the selected option. In this case, the selected option number is displayed with error emphasis.

The contents of the command line are parameters for the list action. These parameters can be accessed by defining a dialog variable for the UIM to update. The update is with the contents of the command line when the action list is processed. For more information see

RETURN Command

the LIST tag in Appendix A, "UIM Panel Group Definition Language" on page A-1

Each individual option receives a separate prompt. The UIM does not apply information added during prompting from one command to another.


When the prompt action is to call an application program, the option is processed without prompting by the UIM. When the UIM calls the application program, an indication is given that the user requested the prompt function. It is the responsibility of the application program to provide its own version of prompting.

- If the command line contains a command, the command is submitted for prompting and processing. The command can then be run or canceled through normal prompter functions. Depending on the environment the job is running in, the system can pass the command to the System/36 environment or REXX.

If the command line was blank (a subclass of assuming it contains a command), the Major Command Groups menu is displayed.

For additional information about the PROMPT dialog command, see "Considerations for Using the ENTER, HELP, and PROMPT Dialog Commands" on page B-8.


PULLDOWN (Display Pull-Down Menu)



Displays the first pull-down menu of the menu bar.

Parameters: None

RETRIEVE (Retrieve Command String)



Displays the previously entered command.

The UIM keeps a series of commands entered on command lines. When the RETRIEVE dialog command is issued, the previous command is dis-

played on the command line. If the RETRIEVE dialog command is issued again before any other function is performed, the next most recent command is displayed.


Menu item selections and parameter strings cannot be retrieved. Also, commands submitted via the CMD dialog command cannot be retrieved.

Parameters: None

VARUPD Value: The RETRIEVE dialog command always operates with VARUPD=NO. No validity checking is performed on the contents of the current panel and no updates are made to the dialog variables.

Messages: No messages are issued during processing.

RETURN (Return Control to Application)



Provides the application with a method of handling function keys, menu items, and pull-down choices by having the UIM return control to the application with the appropriate indication.

- | **Note:** To provide the Refresh/Redisplay function for an application, use the RETURN dialog command.

The effect of the RETURN dialog command can be obtained for action lists by using the ACTOR attribute of the LIST tag. This attribute determines whether or not the UIM should handle the action list.

Required Parameter

- n* This parameter specifies a numeric value from 1 through 32767. This value is returned to the application, on the function requested parameter of QUIDSPP API, when the RETURN function is encountered.

VARUPD Value: The RETURN dialog command does not have a predefined VARUPD value. When RETURN is assigned to a function key, the VARUPD value of the function key determines

whether or not to perform validity checking and then updates the dialog variables.

Messages: No messages are issued during processing unless errors are found during validity checking.

Appendix C. Feedback Area Layouts for Display Files

This appendix contains Product-Sensitive Programming Interface and Associated Guidance Information.

Tables in this section describe the open and I/O feedback areas associated with any opened display file. The following information is presented for each item in these feedback areas:

- Offset, which is the number of bytes from the start of the feedback area to the location of each item.
- Data Type.
- Length, which is given in number of bytes.
- Contents, which is the description of the item and the valid values for it.

For information about feedback area layouts for files other than display files, see the *Data Management Guide*.

The support provided by the high-level language you are using determines how to access this information and how the data types are represented. See your high-level language manual for more information.

Open Feedback Area

The open feedback area is the part of the open data path (ODP) that contains general information about the file after it has been opened. It also contains file-specific information for display files, plus information about each device defined for the file. This information is set during open processing and may be updated as other operations are performed.

Table C-1 (Page 1 of 3). Open Feedback Area

Offset	Data Type	Length	Contents
0	Character	2	Open data path (ODP) type: DS Display, tape, ICF, save, printer file not being spooled, or diskette file not being spooled. DB Database member. SP Printer or diskette file being spooled or inline data file.
2	Character	10	Name of the file being opened. If the ODP type is DS (for display files), this is the name of the display file.
12	Character	10	Name of the library containing the file. For an inline data file, the value is *N.
22	Character	10	Not applicable to displays.
32	Character	10	Not applicable to displays.
42	Binary	2	Not applicable to displays.
44	Binary	2	Maximum record length.
46	Character	2	Not applicable to displays.
48	Character	10	Not applicable to displays.
58	Binary	4	Reserved.
62	Binary	4	Reserved.

Table C-1 (Page 2 of 3). Open Feedback Area

Offset	Data Type	Length	Contents
66	Binary	2	File type: 1 Display 2 Printer 4 Diskette 5 Tape 9 Save 10 DDM 11 ICF 20 Inline data 21 Database
68	Character	3	Reserved.
71	Binary	2	Number of lines on a display screen.
73	Binary	2	Number of positions on a display screen.
75	Binary	4	Not applicable to displays.
79	Character	2	Not applicable to displays.
81	Character	1	Not applicable to displays.
82	Character	1	Not applicable to displays.
83	Character	10	Reserved.
93	Character	10	Reserved.
103	Binary	2	Not applicable to displays.
105	Binary	2	Maximum number of records that can be read or written in a block when using blocked record I/O.
107	Binary	2	Not applicable to displays.
109	Binary	2	Blocked record I/O record increase. Number of bytes that must be added to the start of each record in a block to address the next record in the block.
111	Binary	4	Reserved.
115	Character	1	Miscellaneous flags. Bit 1: Reserved. Bit 2: File with sharing 0 File was not opened with sharing. 1 File was opened with sharing (SHARE(*YES)). Bits 3-5: Not applicable to displays. Bit 6: Field-level descriptions 0 File does not contain field-level descriptions. 1 File contains field-level descriptions. Bit 7: DBCS-capable file 0 File is not DBCS-capable. 1 File is DBCS-capable. Bit 8: Not applicable to displays.

Table C-1 (Page 3 of 3). Open Feedback Area

Offset	Data Type	Length	Contents
116	Character	10	For display files, this is the name of the display device description that is the requesting program device. This field is supplied only when a device name of *REQUESTER is being attached to the display file by an open or acquire operation. Otherwise, this field contains *N.
126	Binary	2	File open count. If the file has not been opened with sharing, this field contains a 1. If the file has been opened with sharing, this field contains the number of programs currently attached to this file.
128	Binary	2	Reserved.
130	Binary	2	Not applicable to displays.
132	Character	1	Miscellaneous flags. Bits 1-4: Not applicable to displays. Bit 5: Separate indicator area 0 Indicators are in the I/O buffer of the program. 1 Indicators are not in the I/O buffer of the program. The DDS keyword, INDARA, was used when the file was created. Bit 6: User buffers 0 System creates I/O buffers for the program. 1 User program supplies I/O buffers. Bit 7: Reserved. Bit 8: Not applicable to displays.
133	Character	2	Open identifier. The value is unique for a full (not shared) open operation of a file. It allows you to match this file to an entry on the associated data queue.
135	Binary	2	The field value is the maximum record format length, including both data and file-specific information such as: option indicators, response indicators, source sequence numbers, and program-to-system data. If the value is zero, then use the field at offset 44.
137	Binary	2	Not applicable to displays.
139	Character	1	Miscellaneous flags. Bits 1-3: Not applicable to displays. Bit 4: CCSID character substitution 0 No substitution characters will be used during CCSID data conversion. 1 Substitution characters may be used during CCSID data conversion. Bits 5-8: Reserved.
140	Character	6	Reserved.
146	Binary	2	Number of devices defined for this ODP. For displays, this is determined by the number of devices defined on the DEV parameter of the Create Display File (CRTDSPF) command.
148	Character		Device name definition list. See "Device Definition List" on page C-4 for a description of this array.

Device Definition List

The device definition list part of the open feedback area is an array structure. Each entry in the array contains information about each device attached to the file. The number of entries in this array is determined by the number at offset 146 of the

open feedback area. The device definition list begins at offset 148 of the open feedback area. The offsets shown for it are from the start of the device definition list rather than the start of the open feedback area.

Table C-2 (Page 1 of 2). Device Definition List

Offset	Data Type	Length	Contents
0	Character	10	Program device name. For display files, the value is the name of the device description.
10	Character	50	Reserved.
60	Character	10	Device description name. For display files, the value is the name of the device description.
70	Character	1	Device class. For displays, the device class is hex 01.
71	Character	1	Device type.
	hex 07		5251 Display Station
	hex 0B		5291 Display Station
	hex 0D		5292 Display Station
	hex 12		5555-B01 Display Station
	hex 13		3270 Display Station
	hex 15		Graphic-capable device
	hex 16		Financial terminal
	hex 17		3180 Display Station
	hex 19		3277 DHCF Device
	hex 26		3179-2 Display Station
	hex 27		3196-A Display Station
	hex 28		3196-B Display Station
	hex 33		3197-C1 Display Station
	hex 34		3197-C2 Display Station
	hex 35		3197-D1 Display Station
	hex 36		3197-D2 Display Station
	hex 37		3197-W1 Display Station
	hex 38		3197-W2 Display Station
	hex 39		5555-E01 Display Station
	hex 3E		3476-EA Display Station
	hex 3F		3477-FG Display Station
	hex 40		3278 DHCF device
	hex 41		3279 DHCF device
	hex 42		ICF finance device
	hex 43		Retail communications device
	hex 44		3477-FA Display Station
	hex 45		3477-FC Display Station
	hex 46		3477-FD Display Station
	hex 47		3477-FW Display Station
	hex 48		3477-FE Display Station
	hex 4D		Network Virtual Terminal display station
	hex 51		5555-C01 Display Station
	hex 52		5555-F01 Display Station
	hex 56		3476-EC Display Station
	hex 58		5555-G01 Display Station

Table C-2 (Page 2 of 2). Device Definition List

Offset	Data Type	Length	Contents
			hex 59 5555-G02 Display Station
			hex 5D 3486-BA Display Station
			hex 5F 3487-HA Display Station
			hex 60 3487-HG Display Station
			hex 61 3487-HW Display Station
			hex 62 3487-HC Display Station
72	Binary	2	Number of lines on the display screen.
74	Binary	2	Number of positions in each line of the display screen.
76	Character	2	Bit flags.
			Bit 1: Blinking capability.
			0 Display is not capable of blinking.
			1 Display is capable of blinking.
			Bit 2: Device location.
			0 Local device.
			1 Remote device.
			Bit 3: Acquire status. This bit is set even if the device is implicitly acquired at open time.
			0 Device is not acquired.
			1 Device is acquired.
			Bit 4: Invite status.
			0 Device is not invited.
			1 Device is invited.
			Bit 5: Data available status (only if device is invited).
			0 Data is not available.
			1 Data is available.
			Bit 6: Not applicable to displays.
			Bit 7: Requesting program device.
			0 Not a requesting program device.
			1 A requesting program device.
			Bit 8: DBCS device.
			0 Device is not capable of processing double-byte data.
			1 Device is capable of processing double-byte data.
			Bits 9-10: Reserved.
			Bit 11: DBCS keyboard.
			0 Keyboard is not capable of entering double-byte data.
			1 Keyboard is capable of entering double-byte data.
			Bits 12-16: Reserved.
78	Character	1	Not applicable to displays.
79	Character	1	Not applicable to displays.
80	Character	50	Reserved.

I/O Feedback Area

The results of I/O operations are communicated to the program using OS/400 messages and I/O feedback information. The I/O feedback area is updated for every I/O operation unless your program is using blocked record I/O. In that case, the feedback area is updated only when a block of records is read or written. Some of the information reflects the last record in the block. Other

information, such as the count of I/O operations, reflects the number of operations on blocks of records and not the number of records. See your high-level language manual to determine if your program uses blocked record I/O.

The I/O feedback area consists of two parts: a common area and a file-dependent area.

Common I/O Feedback Area

Table C-3 (Page 1 of 3). Common I/O Feedback Area

Offset	Data Type	Length	Contents
0	Binary	2	Offset to file-dependent feedback area.
2	Binary	4	Write operation count. Updated only when a write operation completes successfully. For blocked record I/O operations, this count is the number of blocks, not the number of records.
6	Binary	4	Read operation count. Updated only when a read operation completes successfully. For blocked record I/O operations, this count is the number of blocks, not the number of records.
10	Binary	4	Write-read operation count. Updated only when a write-read operation completes successfully.
14	Binary	4	Other operation count. Number of successful operations other than write, read, or write-read. Updated only when the operation completes successfully. This count includes update, delete, force-end-of-data, force-end-of-volume, change-end-of-data, release record lock, and acquire/release device operations.
18	Character	1	Reserved.
19	Character	1	Current operation. hex 01 Read or read block or read from invited devices hex 02 Read direct hex 03 Read by key hex 05 Write or write block hex 06 Write-read hex 07 Update hex 08 Delete hex 09 Force-end-of-data hex 0A Force-end-of-volume hex 0D Release record lock hex 0E Change end-of-data hex 11 Release device hex 12 Acquire device
20	Character	10	Name of the record format just processed, which is either: <ul style="list-style-type: none">Specified on the I/O request, orDetermined by default or format selection processing For display files, the default name is either the name of the only record format in the file or the previous record format name for the record written to the display that contains input-capable fields. Because a display file may have multiple formats on the display at the same time, this format may not represent the format where the last cursor position was typed.

Table C-3 (Page 2 of 3). Common I/O Feedback Area

Offset	Data Type	Length	Contents
30	Character	2	<p>Device class:</p> <p>Byte 1:</p> <p>hex 00 Database</p> <p>hex 01 Display</p> <p>hex 02 Printer</p> <p>hex 04 Diskette</p> <p>hex 05 Tape</p> <p>hex 09 Save</p> <p>hex 0B ICF</p> <p>Byte 2 (if byte 1 contains hex 01 for displays):</p> <p>hex 07 5251 Display Station</p> <p>hex 0B 5291 Display Station</p> <p>hex 0D 5292 Display Station</p> <p>hex 12 5555-B01 Display Station</p> <p>hex 13 3270 Display Station</p> <p>hex 15 Graphic-capable device</p> <p>hex 16 Financial terminal</p> <p>hex 17 3180 Display Station</p> <p>hex 19 3277 DHCF device</p> <p>hex 26 3179-2 Display Station</p> <p>hex 27 3196-A Display Station</p> <p>hex 28 3196-B Display Station</p> <p>hex 33 3197-C1 Display Station</p> <p>hex 34 3197-C2 Display Station</p> <p>hex 35 3197-D1 Display Station</p> <p>hex 36 3197-D2 Display Station</p> <p>hex 37 3197-W1 Display Station</p> <p>hex 38 3197-W2 Display Station</p> <p>hex 39 5555-E01 Display Station</p> <p>hex 3E 3476-EA Display Station</p> <p>hex 3F 3477-FG Display Station</p> <p>hex 40 3278 DHCF device</p> <p>hex 41 3279 DHCF device</p> <p>hex 42 ICF finance device</p> <p>hex 43 Retail communications device</p> <p>hex 44 3477-FA Display Station</p> <p>hex 45 3477-FC Display Station</p> <p>hex 46 3477-FD Display Station</p> <p>hex 47 3477-FW Display Station</p> <p>hex 48 3477-FE Display Station</p> <p>hex 4D Network Virtual Terminal display station</p> <p>hex 51 5555-C01 Display Station</p> <p>hex 52 5555-F01 Display Station</p> <p>hex 56 3476-EC Display Station</p> <p>hex 58 5555-G01 Display Station</p> <p>hex 59 5555-G02 Display Station</p> <p>hex 5D 3486-BA Display Station</p> <p>hex 5E 3486-BG Display Station</p> <p>hex 5F 3487-HE Display Station</p> <p>hex 60 3487-HD Display Station</p> <p>hex 61 3487-HW Display Station</p> <p>hex 62 3487-HC Display Station</p>

Table C-3 (Page 3 of 3). Common I/O Feedback Area

Offset	Data Type	Length	Contents
32	Character	10	Device name. For displays, the name of the device for which the operation just completed.
42	Binary	4	Length of the record processed by the last I/O operation.
46	Character	80	Reserved.
126	Binary	2	Number of records retrieved on a read request for blocked records or sent on a write or force-end-of-data or force-end-of-volume request for blocked records.
128	Binary	2	For output, the field value is the record format length, including first-character forms control, option indicators, source sequence numbers, and program-to-system data. If the value is zero, use the field at offset 42. For input, the field value is the record format length, including response indicators and source sequence numbers. If the value is zero, use the field at offset 42.
130	Character	2	Reserved.
132	Binary	4	Not applicable to displays.
136	Character	8	Reserved.

I/O Feedback Area for Display Files

Table C-4 (Page 1 of 3). I/O Feedback Area for Display Files

Offset	Data Type	Length	Contents																																																				
0	Character	2	<p>Flag bits.</p> <p>Bit 1: Cancel-read indicator.</p> <p>0 The cancel-read operation did not cancel the read request.</p> <p>1 The cancel-read operation canceled the read request.</p> <p>Bit 2: Data-returned indicator.</p> <p>0 The cancel-read operation did not change the contents of the input buffer.</p> <p>1 The cancel-read operation placed the data from the read-with-no-wait operation into the input buffer.</p> <p>Bit 3: Command key indicator.</p> <p>0 Conditions for setting this indicator did not occur.</p> <p>1 The Print, Help, Home, Roll Up, Roll Down, or Clear key was pressed. The key is enabled with a DDS keyword, but without a response indicator specified.</p> <p>Bits 4-16: Reserved.</p>																																																				
2	Character	1	<p>Attention indicator byte (AID). This field identifies which function key was pressed. This field will always contain the value hex F1 to imitate the Enter key being pressed on a display device. For display files, this field will contain the 1-byte hexadecimal value returned from the device.</p> <table><tr><th>Hex Codes</th><th>Function Keys</th></tr><tr><td>hex 31</td><td>1</td></tr><tr><td>hex 32</td><td>2</td></tr><tr><td>hex 33</td><td>3</td></tr><tr><td>hex 34</td><td>4</td></tr><tr><td>hex 35</td><td>5</td></tr><tr><td>hex 36</td><td>6</td></tr><tr><td>hex 37</td><td>7</td></tr><tr><td>hex 38</td><td>8</td></tr><tr><td>hex 39</td><td>9</td></tr><tr><td>hex 3A</td><td>10</td></tr><tr><td>hex 3B</td><td>11</td></tr><tr><td>hex 3C</td><td>12</td></tr><tr><td>hex B1</td><td>13</td></tr><tr><td>hex B2</td><td>14</td></tr><tr><td>hex B3</td><td>15</td></tr><tr><td>hex B4</td><td>16</td></tr><tr><td>hex B5</td><td>17</td></tr><tr><td>hex B6</td><td>18</td></tr><tr><td>hex B7</td><td>19</td></tr><tr><td>hex B8</td><td>20</td></tr><tr><td>hex B9</td><td>21</td></tr><tr><td>hex BA</td><td>22</td></tr><tr><td>hex BB</td><td>23</td></tr><tr><td>hex BC</td><td>24</td></tr><tr><td>hex BD</td><td>Clear</td></tr></table>	Hex Codes	Function Keys	hex 31	1	hex 32	2	hex 33	3	hex 34	4	hex 35	5	hex 36	6	hex 37	7	hex 38	8	hex 39	9	hex 3A	10	hex 3B	11	hex 3C	12	hex B1	13	hex B2	14	hex B3	15	hex B4	16	hex B5	17	hex B6	18	hex B7	19	hex B8	20	hex B9	21	hex BA	22	hex BB	23	hex BC	24	hex BD	Clear
Hex Codes	Function Keys																																																						
hex 31	1																																																						
hex 32	2																																																						
hex 33	3																																																						
hex 34	4																																																						
hex 35	5																																																						
hex 36	6																																																						
hex 37	7																																																						
hex 38	8																																																						
hex 39	9																																																						
hex 3A	10																																																						
hex 3B	11																																																						
hex 3C	12																																																						
hex B1	13																																																						
hex B2	14																																																						
hex B3	15																																																						
hex B4	16																																																						
hex B5	17																																																						
hex B6	18																																																						
hex B7	19																																																						
hex B8	20																																																						
hex B9	21																																																						
hex BA	22																																																						
hex BB	23																																																						
hex BC	24																																																						
hex BD	Clear																																																						

Table C-4 (Page 2 of 3). I/O Feedback Area for Display Files

Offset	Data Type	Length	Contents
			hex F1 Enter/Rec Adv hex F3 Help (not in operator-error mode) hex F4 Roll Down hex F5 Roll Up hex F6 Print hex F8 Record Backspace hex 3F Automatic Enter (for Selector Light Pen)
3	Character	2	Cursor location (line and position). Updated on input operations that are not subfile operations that return data to the program. For example, hex 0102 means line 1, position 2. Line 10, position 33 would be hex 0A21.
5	Binary	4	Actual data length. The length of the record format processed by the I/O operation.
9	Binary	2	Relative record number of a subfile record. Updated for a subfile record operation. For input operations, updated only if data is returned to the program. If multiple subfiles are on the display, this offset will contain the relative record number for the last subfile updated.
11	Binary	2	Indicates the lowest subfile relative record number currently displayed in the uppermost subfile display area if the last write operation was done to the subfile control record with SFLDSP specified. Updated for roll up and roll down operations. Reset to 0 on a write operation to another record. Not set for message subfiles.
13	Binary	2	Total number of records in a subfile. Updated on a put-relative operation to any subfile record. The number is set to zero on a write or write-read operation to any subfile control record with the SFLINZ keyword optioned on. If records are put to multiple subfiles on the display, this offset will contain the total number of records for all subfiles assuming that no write or write-read operations were performed to any subfile control record with the SFLINZ keyword optioned on.
15	Character	2	Cursor location relative to active DDS WINDOW keyword (line and position). Updated on input operations that are not subfile operations that return data to the program. The cursor location is based off the usable positions within the window. For example, hex 0C13 means line 12, position 19.
17	Character	17	Reserved.
34	Character	2	Major return code. 00 Operation completed successfully. 02 Input operation completed successfully, but job is being canceled (controlled). 03 Input operation completed successfully, but no data received. 04 Output exception. 08 Device already acquired. 11 Read from invited devices was not successful. 34 Input exception. 80 Permanent system or file error. 81 Permanent session or device error. 82 Acquire or open operation failed. 83 Recoverable session or device error.
36	Character	2	Minor return code. For the values for a display file, see Appendix E, "Display File Return Codes" on page E-1.
38	Character	8	Not applicable to displays.
46	Character	1	Not applicable to displays.

Table C-4 (Page 3 of 3). I/O Feedback Area for Display Files

Offset	Data Type	Length	Contents
47	Character	1	Reserved.
48	Character	1	Not applicable to displays.
49	Character	10	Not applicable to displays.
59	Character	4	Reserved.
63	Character	8	Not applicable to displays.
71	Character	9	Reserved.

Get Attributes

Performing the get attributes operation allows you to obtain certain information about a specific display device.

Table C-5 (Page 1 of 3). Get Attributes

Offset	Data Type	Length	Contents
0	Character	10	Program device name.
10	Character	10	Device description name. Name of the device description associated with this entry.
20	Character	10	User ID.
30	Character	1	Device class. For displays, the device class is D.
31	Character	6	Device type:
		3179	3179 Display Station
		317902	3179-2 Display Station
		3180	3180 Display Station
		3196A	3196-A1/A2 Display Station
		3196B	3196-B1/B2 Display Station
		3197C1	3197-C1 Display Station
		3197C2	3197-C2 Display Station
		3197D1	3197-D1 Display Station
		3197D2	3197-D2 Display Station
		3197W1	3197-W1 Display Station
		3197W2	3197-W2 Display Station
		3270	3270 Display Station
		3476EA	3476-EA Display Station
		3476-EC	3476-EC Display Station
		3477FA	3477-FA Display Station
		3477FC	3477-FC Display Station
		3477FD	3477-FD Display Station
		3477FE	3477-FE Display Station
		3477FG	3477-FG Display Station
		3477FW	3477-FW Display Station
		525111	5251 Display Station
		5291	5291 Display Station
		5292	5292 Display Station
		529202	5292-2 Display Station
		5555B1	5555-B01 Display Station
		5555C1	5555-C1 Display Station
		5555E1	5555-E01 Display Station
		5555F1	5555-F1 Display Station
		5555-G1	5555-G01 Display Station
		5555-G2	5555-G02 Display Station
		3486BA	3486-BA Display Station
		3486BG	3486-BG Display Station
		3487HC	3487-HC Display Station
		3487HD	3487-HD Display Station
		3487HE	3487-HE Display Station
		3487HW	3487-HW Display Station
		DHCF77	3277 DHCF device
		DHCF78	3278 DHCF device
		DHCF79	3279 DHCF device

Table C-5 (Page 2 of 3). Get Attributes

Offset	Data Type	Length	Contents
37	Character	1	Requesting program device. This flag indicates whether this entry is defining a *REQUESTER device. N Not a *REQUESTER device (communications source device). Y A *REQUESTER device (communications target device).
38	Character	1	Acquire status. Set even if device is implicitly acquired at open time. N Device is not acquired. Y Device is acquired.
39	Character	1	Invite status. Y Device is invited. N Device is not invited.
40	Character	1	Data available. Y Invited data is available. N Invited data is not available.
41	Binary	2	Number of rows on display.
43	Binary	2	Number of columns on display.
45	Character	1	Display allow blink. Y Display is capable of blinking. N Display is not capable of blinking.
46	Character	1	Online/offline status. O Display is online. F Display is offline.
47	Character	1	Display location. L Local display. R Remote display.
48	Character	1	Display type. A Alphanumeric or Katakana. I DBCS.
49	Character	1	Keyboard type of display. A Alphanumeric or Katakana keyboard. I DBCS keyboard.
50	Character	1	Not applicable to displays.
51	Character	1	Not applicable to displays.
52	Character	1	Not applicable to displays.
53	Character	8	Not applicable to displays.
61	Character	8	Not applicable to displays.
69	Character	8	Not applicable to displays.
77	Character	8	Not applicable to displays.
85	Character	8	Not applicable to displays.
93	Character	8	Not applicable to displays.

Table C-5 (Page 3 of 3). Get Attributes

Offset	Data Type	Length	Contents
101	Character	1	Controller information.
			Y Display is attached to a controller that supports an enhanced inter-
			face for nonprogrammable work stations.
			N Display is not attached to a controller that supports an enhanced
			interface for nonprogrammable work stations.
102	Character	42	Reserved.

Appendix D. Double-Byte Character Set Support for Displays

This appendix contains information that you need if you use double-byte characters. This includes the following topics:

- Double-byte character set (DBCS) fundamentals
- Processing double-byte characters
- Device file support
- Display support
- Writing application programs that process double-byte characters
- DBCS font tables
- DBCS sort tables
- DBCS conversion dictionaries
- Using DBCS conversion

DBCS printer and spooling support information can be found in the *Guide to Programming for Printing*.

1-Byte Code (SBCS)	2-Byte Code (DBCS)
A ——— X'C1'	A ——— X'42C1'
B ——— X'C2'	B ——— X'42C2'
1 ——— X'F1'	1 ——— X'42F1'
2 ——— X'F2'	2 ——— X'42F2'
	あ ——— X'4481'
	美 ——— X'45D7' (Japanese)
	が ——— X'8877' (Japanese)
	橋 ——— X'524F' (Korean)
	進 ——— X'4F99' (Simplified Chinese)
	進 ——— X'5B70' (Traditional Chinese)

X'hhhh' indicates that the code has the hexadecimal value, "hhhh".

1-Byte Codes: 256 characters

2-Byte Codes: 256 X 256 characters

HRSL3338-0

You can use double-byte characters as well as single-byte characters in one application. For instance, you may want to store double-byte data and single-byte data in your database, create your displays with double-byte text and fields, or print reports with double-byte characters.

Double-Byte Character Set Fundamentals

Some languages, such as Chinese, Japanese, and Korean, have a writing scheme that uses many different characters that cannot be represented with single-byte codes. To create coded character sets for such languages, the system uses two bytes to represent each character. Characters that are encoded in two-byte code are called double-byte characters.

The following example shows alphanumeric characters coded in a single-byte code scheme and double-byte characters coded in a double-byte code scheme.


DBCS Code Scheme

IBM supports two DBCS code schemes: one for the host system, the other for personal computers. The IBM host-system code scheme has the following code-range characteristics:

First byte	hex 41 to hex FE
Second byte	hex 41 to hex FE
Double-byte blank	hex 4040

In the following figure, using the first byte as the vertical axis and the second byte as the horizontal

axis, 256 x 256 intersections (code points) are expressed. The lower-right code area is designated as the valid double-byte code area and x is assigned to the double-byte blank.



D: double-byte code area
x double-byte blank

RSLH712-3

Figure D-1. IBM Host-System Code Scheme

By assigning the values hex 41 to hex FE in the first and second bytes as the DBCS character codes, the codes can be grouped in wards with 192 code points in each ward. For example, the code group with the first byte starting with hex 42 is called *ward 42*. Ward 42 has the same alphanumeric characters as those in a corresponding single-byte EBCDIC code page, but with double-byte codes. For example, the character *A* is represented in single-byte EBCDIC code as hex C1 and in IBM-host code as hex 42C1.

The AS/400 system supports the following double-byte character sets:

- IBM Japanese
- IBM Korean
- IBM Simplified Chinese
- IBM Traditional Chinese

The following tables show the code ranges for each character set and the number of characters supported in each character set.

Table D-1. IBM Japanese Character Set

Wards	Content	Number of Characters
40	Space in 4040	1

Table D-1. IBM Japanese Character Set

Wards	Content	Number of Characters
41 to 44	Non-Kanji characters <ul style="list-style-type: none"> • Greek, Russian, Roman numeric (ward 41) • Alphanumeric and related symbols (ward 42) • Katakana, Hiragana, and special symbols (ward 43-44) 	549
45 to 55	Basic Kanji characters	3226
56 to 68	Extended Kanji characters	3487
69 to 7F	User-defined characters	Up to 4370
80 to FE	Reserved	
Total number of IBM-defined characters:		7263

Table D-2. IBM Korean Character Set

Wards	Content	Number of Characters
40	Space in 4040	1
41 to 46	Non-Hangeul/Hanja characters (Latin alphabet, Greek, Roman, Japanese Kana, numeric, special symbols)	939
47 to 4F	Reserved	
50 to 6C	Hanja characters	5265
6D to 83	Reserved	
84 to D3	Hangeul characters (Jamo included)	2672
D4 to DD	User-defined characters	Up to 1880
DE to FE	Reserved	
Total number of IBM-defined characters:		8877

Table D-3. IBM Simplified Chinese Character Set

Wards	Content	Number of Characters
40	Space in 4040	1
41 to 47	Non-Chinese characters (Latin alphabet, Greek, Russian, Japanese Kana, numeric, special symbols)	712
48 to 6F	Chinese characters: Level 1 and Level 2	3755 and 3008
70 to 75	Reserved	
76 to 7F	User-defined characters	Up to 1880
80 to FE	Reserved	
Total number of IBM-defined characters:		7476

Table D-4. IBM Traditional Chinese Character Set


Wards	Content	Number of Characters
40	Space in 4040	1
41 to 46	Non-Chinese characters (Latin alphabet, Greek, Roman, Japanese Kana, numeric, special symbols)	674
47 to 4B	Reserved	
4C to 68	Primary Chinese characters	5401
69 to 91	Secondary Chinese characters	7652
92 to CF	Reserved	
D0 to DD	User-defined characters	Up to 2632
DE to FE	Reserved	
Total number of IBM-defined characters: 13728		

This code scheme applies to the AS/400 system, System/36, System/38, as well as the System/370* system. A different DBCS code scheme, called the IBM personal computer DBCS code scheme, is used on the Personal System/55. For details of the IBM personal computer DBCS code scheme, refer to IBM PS/55 publications.

Double-byte code that is not valid has a double-byte code value that is not in the valid double-byte code range. Double-byte code that is not valid is not the same as undefined double-byte code, which has valid double-byte code value but no graphic symbol currently defined for the code.

Shift-Control Characters

When the IBM host-system code scheme is used, the system uses shift-control characters to identify the beginning and end of a string of double-byte characters. The shift-out (SO) character, hex 0E, indicates the beginning of a double-byte character string. The shift-in (SI) character, hex 0F, indicates the end of a double-byte character string.



RSLH713-1

Each shift-control character occupies the same amount of space as one alphanumeric character. By contrast, double-byte characters occupy the same amount of space as two alphanumeric characters.

Using Double-Byte Data

This section tells you how you can use double-byte data and discusses the limitations to its use.

How You Can Use: You can use double-byte data in the following ways:

- As data in files:
 - Data entered in input-capable fields and data displayed in output-capable fields of display files.
 - Data used as literals in display files.
- As the text of messages.
- As the text of object descriptions.
- As literals and constants, and as data to be processed by high-level language programs.
- As search words when using the information search function. For more information on DBCS and the search information function, see “National Language Considerations” on page 20-11.

Double-byte data can be displayed only at DBCS display stations. Double-byte data can be written onto diskettes and tape, as well as onto disk storage.

How You Cannot Use: You cannot use double-byte data in the following ways:

- As AS/400 object names.
- As command names or variable names in control language (CL) and other high-level languages.
- As displayed output on alphanumeric display stations.

Double-Byte Character Size

When displayed, double-byte characters are twice as wide as alphanumeric characters.

Consider the width of double-byte characters when you calculate the length of a double-byte data field because field lengths are usually identified as the number of alphanumeric character positions used. For more information on calculating the length of fields containing double-byte data, refer to the *DDS Reference*.

Processing Double-Byte Characters

Due to the large number of double-byte characters, the system needs more information to identify each double-byte character than is needed to identify each alphanumeric character.

There are two types of double-byte characters: basic and extended. These characters are usually processed by the display station on which the characters are displayed.

Basic Characters

A DBCS display station can process basic characters without any assistance from the system. The display station knows about the graphic characters because they are stored in the display station. The number of double-byte characters that are stored in the display station varies with the language supported and the storage size of the display station. A DBCS display station can display basic characters without using the extended character processing function of the operating system.

Extended Characters

When processing extended characters, the display station requires the assistance of the system. The system must tell the display station what the character looks like before the display station can display the character. Extended characters are stored in a DBCS font table, not in the DBCS display station. When displaying extended characters, the display station receives them from the DBCS font table under control of the operating system.

Extended character processing is a function of the operating system that is required to make characters stored in a DBCS font table available to a DBCS display station.

To request extended character processing, specify the double-byte extended character parameter, `IGCEXNCHR(*YES)`, on the file creation command when you create a display (`CRTDSPF` command) file that processes double-byte data. Because `IGCEXNCHR(*YES)` is the default value, the system automatically processes extended characters unless you instruct it otherwise. You can change this file attribute by using a change file (`CHGDSPF`) or override file (`OVRDSPF`) command. For example, to override the display file `DBCSDSPF` so that extended characters are processed, enter:

```
OVRDSPF DSPF(DBCSDSPF) IGCEXNCHR(*YES)
```

Note: The system ignores the `IGCEXNCHR` parameter when processing alphanumeric files.

What Happens When Extended Characters Are Not Processed

When extended characters are not processed, the following happens:

- Basic characters are displayed.
- The system displays the undefined character where it would otherwise display extended characters.
- The extended characters, though not displayed, are stored correctly in the system.

Device File Support

The following sections describe DBCS device files and special considerations for working with DBCS device files. Data description specifications (DDS) can be used with DBCS device files. For information about using DDS, refer to the *DDS Reference* manual.

What a DBCS File Is

A *DBCS file* is a file that contains double-byte data or is used to process double-byte data. Other files are called *alphanumeric files*.

Display files can be DBCS files.

When to Indicate a DBCS File

You should indicate that a file is DBCS in one or more of the following situations:

- The file receives input, or displays output, which has double-byte characters.
- The file contains double-byte literals.
- The file has double-byte literals in the DDS that are used in the file at processing time (such as constant fields and error messages).
- The DDS of the file includes DBCS keywords. See the *DDS Reference* for information on these keywords.
- The file stores double-byte data (database files).

How to Indicate a DBCS File

You must indicate that a device file is a DBCS file in order for the system to process double-byte data properly. You can do this in one of the following ways:

- By specifying IGCDTA(*YES) on the Create Display File (CRTDSPF) command
- Through DDS

DDS provides fields of the following data types:

DBCS-Only Field

DBCS-only fields display and accept only double-byte characters. Double-byte characters are always enclosed in shift-out and shift-in characters that have to be paired.

DBCS-Open Field

DBCS-open fields display and accept both single-byte and double-byte characters. Double-byte characters are enclosed in shift-out and shift-in characters that have to be paired.

DBCS-Either Field

DBCS-either fields display and accept *either* single-byte or double-byte characters, but not *both*. Double-byte characters are enclosed in shift-out and shift-in character pairs.

DBCS-Graphic Field

DBCS-graphic fields do not contain shift-out and shift-in characters.

In display files, you can define fields with DBCS-only data type (type J), either data type (type E), open data type (type O), or DBCS-graphic data type (type G).

You can also use a double-byte literal that is used with the file at processing time, such as literals specified with the Default (DFT) and Error Message (ERRMSG) DDS keywords.

Note: You may also use double-byte literals as text and comments in a file, such as with the DDS keyword TEXT. However, the system does not consider a file, whose only DBCS attribute is that it has double-byte comments, to be a DBCS file.

You may also specify the Alternative Data Type (IGCALTTYP) DDS keyword in display files. This keyword lets you use display files with both alphanumeric and double-byte applications. When you put the IGCALTTYP keyword into effect, you can use double-byte data with the file.

Put the IGCALTTYP keyword into effect by creating, changing, or overriding display files with the IGCDTA(*YES) value. You can put the IGCALTTYP keyword into effect for display files by specifying IGCDTA(*YES) on the following device file commands:

- Create Display File (CRTDSPF)
- Change Display File (CHGDSPF)
- Override with Display File (OVRDSPF)

When you specify IGCDTA(*NO), the IGCALTTYP keyword is not in effect and you can use only alphanumeric data with the file. Changing or overriding the file to put the IGCALTTYP keyword into effect does not change the DDS of the file.

Except when using the IGCALTYP function, you do not need to specify IGCDTA(*YES) on the file creation command if you have already specified DBCS functions in the DDS. Instead, specify IGCDTA(*YES) when the file has DBCS functions that are not indicated in the DDS. For example, specify IGCDTA(*YES) on the file creation command if the file is intended to contain double-byte data.

Improperly Indicated DBCS Files

If you do not properly indicate that a display file is a DBCS file, one of the following happens:

- Display data management assumes that the output data to the display does not contain double-byte data. The end result depends on whether the display is an alphanumeric or DBCS display.

If the display is an alphanumeric display, the double-byte data is interpreted as alphanumeric data. The shift-control characters appear as blanks. The displayed double-byte data does not make sense.

If the display is a DBCS display, the double-byte data is displayed with the exception of extended characters. The system does not perform extended character processing on the data. Therefore, extended characters are displayed with the symbol for undefined double-byte characters.

- The system does not recognize literals with DBCS text as double-byte literals if the source file is not specified as a DBCS file.

Display Support

The following sections describe information on displaying double-byte characters.

Inserting Shift-Control Characters

The system inserts shift-control characters into DBCS-only fields automatically.

To insert shift-control characters into DBCS-open fields or DBCS-either fields, do the following:

1. Position the cursor in the field in which you want to insert double-byte data.
2. Press the Insert Shift Control Character key (according to your DBCS display station user's guide).

The system inserts a pair of shift-control characters at the same time, as follows (where 0_E represents the shift-out character and 0_F represents the shift-in character):

$0_E 0_F$

The system leaves the cursor under the shift-in character and puts the keyboard in insert mode. Insert double-byte characters between the shift-control characters. To insert double-byte characters, start typing in double-byte characters at the cursor position. For example, enter the double-byte character string D1D2D3, as follows (where 0_E represents the shift-out character, 0_F represents the shift-in character, and D1, D2, and D3 represent three double-byte characters):

$0_E D1D2D3 0_F$

To find out if a field already has the shift-control characters, press the Display Shift Control Character key.

Number of Displayed Extended Characters

The system can display up to 512 different extended characters on a Japanese display at one time. Additional extended characters are displayed as undefined characters. However, the additional extended characters are stored correctly in the system.

Number of Input Fields on a Display

The use of DBCS input fields affects the total number of input fields allowed on a display. For a 5250 display station, you can specify as many as 256 input fields. However, each three instances of a DBCS field reduces the maximum number of fields by one. For example, if there are 9 DBCS fields on a display, then the maximum is $256 - (9/3) = 253$ input fields.

Effects of Displaying Double-Byte Data at Alphanumeric Work Stations

Alphanumeric display stations cannot display double-byte data correctly. If you try to display double-byte data at an alphanumeric display station, the following happens:

- The system sends an inquiry message to that display station, asking whether you want to continue using the program with double-byte data or to cancel it.
- If you continue using the program, the system ignores the shift-control characters and interprets the double-byte characters as though they were alphanumeric. Displayed double-byte data does not make sense.

Effects of Displaying DBCS-Graphic Fields on Double-Byte Displays

The following occurs when displaying DBCS-graphic fields on a DBCS-graphic display without graphic capabilities.

- If a DBCS-graphic field is sent to a DBCS device without graphic capabilities, shift control characters are added to the field and one DBCS character is truncated from the end of the field. For example, assume an output buffer contained the graphic characters 'ABCD', and also assume the characters are displayed on a device without graphic capabilities. When the characters are displayed, they appear as 'ABC' with shift control characters at the beginning and end of the field.
- If the program is displaying an output DBCS-graphic field one character long, the field is displayed with 2 null characters. This is because a DBCS field needs to be defined at least 4 bytes long to allow room for the shift control characters and a DBCS character.
- If the program is displaying an input DBCS-graphic field 1 character long, message CPF501F will be sent to the calling program. The message explains that an incorrect field length caused the output operation to fail. Ensure that DBCS input capable fields sent to the DBCS device are at least 4 bytes long.

Application Program Considerations

The following sections describe considerations for writing applications that process double-byte data.

Designing Application Programs That Process Double-Byte Data

Design your application programs for processing double-byte data in the same way you design application programs for processing alphanumeric data, with the following additional considerations:

- Design display formats that can be used with double-byte data.
- If needed, provide DBCS conversion as a means of entering double-byte data for interactive applications. Use the DDS keyword for DBCS conversion (IGCCNV) to specify DBCS conversion in display files. Because DBCS display stations provide a variety of double-byte data entry methods, you are not required to use the AS/400 DBCS conversion function to enter double-byte data.
- Create double-byte messages to be used by the program.
- Specify extended character processing so that the system displays all double-byte data. See "Extended Characters" on page D-4 for instructions.
- Determine whether additional double-byte characters need to be defined. User-defined characters can be defined and maintained using the character generator utility (CGU). Information on CGU can be found in the *CGU User's Guide*.
- Make sure that the double-byte data is always processed in a double-byte unit and do not split a double-byte character.

Changing Alphanumeric Application Programs to DBCS Application Programs

If an alphanumeric application program uses externally described files, you can change that application program to a DBCS application program by changing the externally described

files. To convert an application program, do the following:

1. Create a duplicate copy of the source statements for the alphanumeric file that you want to change.
2. Change alphanumeric constants and literals to double-byte constants and literals.
3. Change fields in the file to the open (O) data type or specify the Alternative Data Type (IGCALTTYP) DDS keyword so that you can enter both double-byte and alphanumeric data in these fields. You may want to change the length of the fields as the double-byte data takes more space.
4. Store the converted file in a separate library. Give the file the same name as its alphanumeric version.
5. When you want to use the changed file in a job, change the library list, using the Change Library List (CHGLIBL) command, for the job in which the file will be used. The library in which the DBCS display file is stored is then checked before the library in which the alphanumeric version of the file is stored.

DBCS Font Tables

DBCS font tables contain the images of the double-byte extended characters used on the system. The system uses these images to display and print extended characters.

The following DBCS font tables are objects that you can save or restore. These font tables are distributed with the DBCS national language versions of the OS/400 licensed program:

- QIGC2424** A Japanese DBCS font table used to display and print extended characters in a 24-by-24 dot matrix image. The system uses the table with Japanese display stations, printers attached to display stations, 5227 Model 1 Printer, and the 5327 Model 1 Printer.
- QIGC2424K** A Traditional Chinese DBCS font table used to print extended characters in a 24-by-24 dot matrix image.

The system uses the table with the 5227 Model 3 Printer and the 5327 Model 3 Printer.

- QIGC2424K** A Korean DBCS font table used to print extended characters in a 24-by-24 dot matrix image. The system uses the table with the 5227 Model 2 Printer and the 5327 Model 2 Printer.

- QIGC2424S** A Simplified Chinese DBCS font table used to print extended characters in a 24-by-24 dot matrix image. The system uses the table with the 5227 Model 5 Printer.

- QIGC3232** A Japanese DBCS font table used to print characters in a 32-by-32 dot matrix image. The system uses the table with the 5583 Printer and the 5337 Model 1 Printer.

- QIGC3232S** A Simplified Chinese DBCS font table used to print characters in a 32-by-32 dot matrix image. The system uses the table with the 5337 Model R05 Printer.

All DBCS font tables have an object type of *IGCTBL. You can find instructions for adding user-defined characters to DBCS font tables in the *CGU User's Guide*.

Finding Out if a DBCS Font Table Exists

Use the Check DBCS Font Table (CHKIGCTBL) command to find out if a DBCS font table exists in your system.

For example, to find out if the table QIGC2424 exists, enter:

```
CHKIGCTBL IGCTBL(QIGC2424)
```

If the table does not exist, the system responds with a message. If the table does exist, the system simply returns without a message.

Check for the existence of a table when adding a new type of DBCS display station to make sure that the table used by the device exists in the system.

Copying a DBCS Font Table onto Tape or Diskette

Use the Copy DBCS Font Table (CPYIGCTBL) command to copy a DBCS font table onto tape or diskette.

Copy a DBCS font table onto tape or diskette in the following instances:

- Before deleting that table.
- After new user-defined characters are added to the tables.
- When planning to use the tables on another system.

The DBCS font tables are saved when you use the Save System (SAVSYS) command so you do not have to use the CPYIGCTBL command when performing normal system backup.

How to Copy a Table onto Tape or

Diskette: To copy a DBCS font table onto a tape or diskettes, do the following:

1. Make sure that you have a tape or diskettes initialized to the *DATA format. If necessary, specify the FMT(*DATA) parameter on the Initialize Diskette (INZDKT) command to let the system prepare the tape or diskettes.
2. Load the initialized tape or diskette onto the system.
3. Enter the CPYIGCTBL command as follows:
 - a. Choose the value OPTION(*OUT).
 - b. Use the DEV parameter to select the device to which you want to copy the table.
 - c. Use the SELECT and RANGE parameters to specify which portion of the table you want copied from the system. See the description of the CPYIGCTBL command in the *CL Reference* for instructions on choosing SELECT and RANGE parameter values.

The following are two examples of the CPYIGCTBL command used to copy a DBCS font table to removable media.

- To copy the DBCS font table QIGC2424 onto diskettes, enter:

```
CPYIGCTBL IGCTBL(QIGC2424) OPTION(*OUT) DEV(QDKT)
```

- To copy just the user-defined characters from DBCS font table QIGC2424 onto tape, enter:

```
CPYIGCTBL IGCTBL(QIGC2424) OPTION(*OUT) +  
DEV(QTAP01) SELECT(*USER)
```

4. Press the Enter key. The system copies the DBCS font table onto the specified media.
5. Remove the tape or diskette after the system finishes copying the table.

Copying a DBCS Font Table from Tape or Diskette

Use the Copy DBCS Font Table (CPYIGCTBL) command to copy a DBCS font table from a tape or a diskette onto the system. The system automatically creates the DBCS font table again when copying its contents if the following are true:

- The specified table does not already exist in the system.
- The media from which you are copying the table contains all of the IBM-defined double-byte characters.
- SELECT(*ALL) or SELECT(*SYS) is specified on the CPYIGCTBL command.

How to Copy a Table from a Tape or

Diskette: To copy a DBCS font table from tape or diskette onto the system:

1. Load the removable media from which the table will be copied onto the system.
2. Enter the CPYIGCTBL command as follows:
 - a. Choose the OPTION(*IN) value.
 - b. Use the DEV parameter to select the device from which to copy the DBCS font table.
 - c. Use the SELECT and RANGE parameters to specify which portion of the table will be copied from the tape or diskette. See the *CL Reference* for a description of the CPYIGCTBL command and for instructions on choosing SELECT and RANGE parameter values.

The following are two examples of commands used to copy a DBCS font table to the system.

- To copy the DBCS font table QIGC2424 from diskette, enter:

```
CPYIGCTBL IGCTBL(QIGC2424) OPTION(*IN) +  
DEV(QDKT)
```

- To copy just the user-defined characters from DBCS font table QIGC2424 from tape and to replace the user-defined characters in the table with the ones from the tape, enter:

```
CPYIGCTBL IGCTBL(QIGC2424) OPTION(*IN) +
DEV(QTAP01) SELECT(*USER) RPLIMG(*YES)
```

3. Press the Enter key. The system copies the DBCS font table from the tape or diskette onto the system.
4. Remove the tape or diskette after the system finishes copying the table.

Deleting a DBCS Font Table

Use the Delete DBCS Font Table (DLTIGCTBL) command to delete a DBCS font table from the system.

Delete an unused DBCS font table to make more storage space available. For example, if you do not plan to use Japanese printer 5583 or 5337 with your system, DBCS font table QIGC3232 is not needed and can be deleted.

How to Delete a DBCS Font Table: To delete a table, do the following:

1. If desired, copy the table onto tape or diskettes. See “Copying a DBCS Font Table onto Tape or Diskette” on page D-9 for instructions. If you do not copy the table to removable media before deleting it, you will not have a copy of the table for future use.
2. Vary off all devices using that table.
3. Enter the DLTIGCTBL command.

For example, to delete the DBCS font table QIGC3232, enter:

```
DLTIGCTBL IGCTBL(QIGC3232)
```

4. Press the Enter key. The system sends inquiry message CPA8424 to the system operator message queue for you to confirm your intention to delete a DBCS font table.
5. Respond to the inquiry message. The system sends you a message when it has deleted the table.

Warning: Do not delete a DBCS font table if any device using that table is currently varied on. Also, make sure that the affected controller is not varied on. If you try to delete the table while the device and controller are varied on, the system reports any devices attached to the same controller(s) as those devices, and the controller(s) as damaged the next time you try to print or display extended characters on an affected device. If such damage is reported, do the following:

1. Vary off the affected devices, using the Vary Configuration (VRYCFG) command.
2. Vary off the affected controller.
3. Vary on the affected controller.
4. Vary on the affected devices.
5. Continue normal work.

Starting the Character Generator Utility

You must use the character generator utility (CGU) to regenerate the font tables. Use the STRCGU command to start the character generator utility. You may call the CGU main menu or specify a specific CGU function, depending on the parameter used. Refer to the *CGU User's Guide* for more information.

Copying User-Defined Double-Byte Characters

Use the STRFMA command to copy user-defined double-byte characters between an AS/400 DBCS font table and a user font file at a Personal System/55, a 5295 Display Station, or an InfoWindow 3477 Display Station.

DBCS Font Files

In addition to the system-supplied DBCS font tables, the system also provides DBCS font files. These DBCS font files are physical files which contain frequently used double-byte characters. When using the character generator utility, you can use the characters in these files as the base for a new user-defined character. These files are supplied with read-only authority as they are not to be changed. If you do not use the character generator utility or the Advanced DBCS Printer Support/400 licensed program, you may delete

these files to save space. They all exist in the QSYS library.

The following DBCS font files are distributed with the DBCS national language versions of the OS/400 licensed program. They are used as a reference for the CGU and the Advanced DBCS Printer Support/400 licensed program.

- QCGF2424** A Japanese DBCS font file used to store a copy of the Japanese DBCS basic character images.
- QCGF2424K** A Korean DBCS font file used to store a copy of the Korean DBCS basic character images.
- QCGF2424C** A Traditional Chinese DBCS font file used to store a copy of the Traditional Chinese DBCS basic character images.
- QCGF2424S** A Simplified Chinese DBCS font file used to store a copy of the Simplified Chinese DBCS basic character images.

DBCS Sort Tables

DBCS sort tables contain the sort information and collating sequences of all the double-byte characters used on the system. The system uses these tables to sort double-byte characters using the sort utility.

DBCS sort tables are objects that you can save, restore, and delete. Using the character generator utility you can also add, delete, and change entries in these tables corresponding to the image entries in the DBCS font tables. For Japanese use only, you can also copy the DBCS master sort table to and from a data file.

The following DBCS sort tables are distributed with the DBCS national language versions of the OS/400 licensed program:

- QCGMSTR** A Japanese DBCS master sort table used to store the sort information for the Japanese double-byte character set.
- QCGACTV** A Japanese DBCS active sort table used to store the sort collating sequences for the Japanese double-byte character set.

QCGMSTRC A Traditional Chinese DBCS master sort table used to store the sort information for the Traditional Chinese double-byte character set.

QCGACTVC A Traditional Chinese DBCS active sort table used to store the sort collating sequences for the Traditional Chinese double-byte character set.

QCGACTVK A Korean DBCS active sort table used to map Hanja characters to Hangeul characters with equivalent pronunciation.

QCGMSTRS A Simplified Chinese DBCS master sort table used to store the sort information for the Simplified Chinese double-byte character set.

QCGACTVS A Simplified Chinese DBCS active sort table used to store the sort collating sequences for the Simplified Chinese double-byte character set.

You may sort Japanese, Korean, Simplified Chinese, and Traditional Chinese double-byte characters. Each of these languages has two DBCS sort tables, a DBCS master sort table and a DBCS active sort table, except for Korean which has only a DBCS active sort table. The DBCS master sort table contains sort information for all defined DBCS characters. The DBCS active sort table for Japanese, Simplified Chinese, and Traditional Chinese is created from the master sort table information and contains the collating sequences for the double-byte characters of that given language. These collating sequences have a purpose similar to the EBCDIC and ASCII collating sequences for the single-byte alphanumeric character set. For Korean characters, the Hangeul characters are assigned both their collating sequence as well as their DBCS codes according to their pronunciation. Hence, a separate collating sequence is not required, and each of the Hanja characters is mapped to a Hangeul character of the same pronunciation using the DBCS active sort table QCGACTVK. Refer to the *Sort User's Guide and Reference* for more information.

All DBCS sort tables have an object type of *IGCSRT.

Using DBCS Sort Tables on the System

You can save the tables to tape or diskette, delete them from the system, and restore them to the system. The Japanese DBCS master sort table can also be copied to a data file and copied from a data file so that it can be shared with a System/36 or Application System/Entry* (AS/Entry) system. You can also add sort information for each user-defined character, and add that character to the DBCS collating sequence, as you create it using the character generator utility.

Finding Out if a DBCS Sort Table Exists

Use the Check Object (CHKOBJ) command to find out if a DBCS sort table exists in your system.

For example, to find out if the table QCGMSTR exists, enter:

```
CHKOBJ OBJ(QSYS/QCGMSTR) OBJTYPE(*IGCSRT)
```

If the table does not exist, the system responds with a message. If the table does exist, the system simply returns without a message.

Check for the existence of a DBCS active sort table when you want to sort double-byte characters for the first time. The DBCS active table for the DBCS language must exist to sort the characters.

Saving a DBCS Sort Table onto Tape or Diskette

Use the Save Object (SAVOBJ) command to save a DBCS sort table onto tape or diskette. Specify *IGCSRT for the object type.

The DBCS sort tables are saved when you use the SAVSYS command so you do not have to use the SAVOBJ command when performing normal system backup.

When to Save a DBCS Sort Table onto Tape or Diskette: Save a DBCS sort table onto tape or diskette in the following instances:

- Before deleting that table
- After information is added, updated, or changed in the tables using the character generator utility
- When planning to use the tables on another AS/400 system

Restoring a DBCS Sort Table from Tape or Diskette

Use the RSTOBJ command to restore a DBCS sort table from a tape or a diskette onto the system. The tables on the tape or diskette must previously have been saved using the SAVOBJ command. Specify *IGCSRT for the object type. The system automatically re-creates the DBCS sort table when the specified table does not already exist in the system.

These tables must be restored to the QSYS library for the system to know they exist. For that reason, RSTOBJ restores *IGCSRT objects only to the QSYS library and only if the objects do not already exist there.

Copying a Japanese DBCS Master Sort Table to a Data File

Through the character generator utility, use the CPYIGCSRT command to copy the Japanese DBCS master sort table (QCGMSTR) to a data file. This data file can then be moved to a System/36 system or AS/Entry system to replace the Japanese master sort table there.

When to Copy the Japanese DBCS Master Sort Table to a Data File: Copy the Japanese DBCS master sort table to a data file in the following instances:

- When planning to move the table to a System/36 or AS/Entry system for use there. You should always transport the Japanese DBCS master sort table together with the Japanese DBCS font tables.
- Before deleting that table, as an alternative to the SAVOBJ command. You can then keep the file or save it on diskette or tape.

How to Copy the Japanese DBCS Master Sort Table to a Data File

Note: In this section, the AS/Entry system also applies to every instance of System/36.: To copy the Japanese DBCS master sort table to a data file, do the following:

1. Decide what data file you want to copy it to. The file need not exist, it will be automatically created.
2. Enter the CPYIGCSRT command as follows:
 - a. Choose the value OPTION(*OUT).
 - b. Use the FILE parameter to specify the name of the data file to which you want to copy the master table. If you are transporting the master table to the System/36 for use there, you should specify a file name of #KAMAST, or you will have to rename the file when you get it to the System/36. Use the AS/400 CPYF command for copying the file onto diskette, and the System/36 TRANSFER command for copying the file from diskette to the System/36.
 - c. Use the MBR parameter to specify the name of the data file member to which you want to copy the master table. If you are transporting the master table to the System/36 for use there, you should specify *FILE for the MBR parameter.
3. Press the Enter key. The system creates the file and member if they do not exist, and writes over the existing member if it does exist.
4. If you now transport this file to your System/36 to replace the #KAMAST file there, you should also use the SRTXBLD procedure to update the active table to reflect the new master table.

Copying a Japanese DBCS Master Sort Table from a Data File

Use the CPYIGCSRT command to copy the Japanese DBCS master sort table (QCGMSTR) from a data file.

When to Copy the Japanese DBCS Master Sort Table from a Data File:

You may use the System/36 Migration Aid to migrate the System/36 or AS/Entry system master sort file (#KAMAST) to the AS/400 system. When you migrate the #KAMAST file using the System/36 Migration Aid, you do not have to use the CPYIGCSRT command.

Copy the Japanese DBCS master sort table from a data file in the following instances:

- When you do not use the System/36 Migration Aid, you may copy the #KAMAST file from the System/36 or AS/Entry system to the AS/400 system. Then use the CPYIGCSRT command to copy sort information from the #KAMAST file to the AS/400 master sort table (QCGMSTR). Delete the #KAMAST file from the AS/400 system after you complete the copy operation.
- When you have copied a version of the master table to a data file and you now want to restore that version.

You should always migrate or copy the Japanese DBCS master sort table together with the Japanese DBCS font tables.

How to Copy the Japanese DBCS Master Sort Table from a Data File:

To copy the Japanese DBCS master sort table from a data file, do the following:

1. Enter the CPYIGCSRT command as follows:
 - a. Choose the value OPTION(*IN).
 - b. Use the FILE parameter to specify the name of the data file that contains a migrated System/36 or AS/Entry system master file or an AS/400 master table previously copied to the file using OPTION(*OUT) with the CPYIGCSRT command. To migrate your System/36 or AS/Entry system master file without using the System/36 Migration Aid, use the TRANSFER command with the IFORMAT parameter on the System/36 or AS/Entry system to save the #KAMAST master file on diskette. Use the AS/400 Copy File (CPYF) command to copy the master file #KAMAST from diskette. Use the CPYIGCSRT command as described here

to copy data from the file to the AS/400 Japanese DBCS master sort table.

- c. Use the MBR parameter to specify the name of the data file member from which you want to copy the master table data.
2. Press the Enter key. Even though the information in the existing Japanese DBCS master sort table is overridden, that table must exist before you can use this command.
3. To update the Japanese DBCS active table to reflect the new copied information, use the SRTXBLD procedure in the System/36 or AS/Entry system environment, or the STRCGU command specifying OPTION(5). This must be done before you can use the sort utility to sort Japanese double-byte characters.

Deleting a DBCS Sort Table

Use the DLTIGCSRT command to delete a DBCS sort table from the system.

When to Delete a DBCS Sort Table:

Delete an unused DBCS sort table to free disk space, but you should always first save a copy of the table using the SAVOBJ command. You should delete the DBCS master sort table for a DBCS language if any of the following are true:

1. You will not be creating any new characters for that language using the character generator utility.
2. You will not be using the sort utility to sort characters for that language.

You should delete the DBCS active sort table for a DBCS language if you will not be using the sort utility to sort characters for that language. The DBCS active sort table must be on the system to use the sort utility for this language.

How to Delete a DBCS Sort Table To delete a table, do the following:

1. If desired, save the table onto tape or diskettes. See "Saving a DBCS Sort Table onto Tape or Diskette" on page D-12 for instructions. If you do not save the table onto removable media before deleting it, you will not have a copy of the table for future use.
2. Enter the DLTIGCSRT command.

For example, to delete the DBCS sort table QCGACTV, enter:

```
DLTIGCSRT IGCSRT(QCGACTV)
```

3. Press the Enter key. The system sends you a message when it has deleted the table.

DBCS Conversion Dictionaries

The DBCS conversion dictionary is a collection of alphanumeric entries and their related DBCS words. The system refers to the dictionary when performing DBCS conversion. See "How DBCS Conversion Works" on page D-20 for information on how the system uses the DBCS conversion dictionary during DBCS conversion.

All DBCS conversion dictionaries have an object type of *IGCDCT. A system-supplied and a user-created dictionary are used with DBCS conversion.

System-Supplied Dictionary (for Japanese Use Only)

QSYSIGCDCT, the system-supplied dictionary that is stored in the library, QSYS, is a collection of entries with a Japanese pronunciation expressed in alphanumeric characters and the DBCS words related to those entries. The system checks this dictionary second when performing DBCS conversion.

QSYSIGCDCT contains these entries:

- Personal names
 - Family names
 - First names
- Organization names
 - Private enterprises registered in the security market
 - Public corporations
 - Typical organizations in the central and local governments
 - Most universities and colleges
- Addresses
 - Public administration units within the prefectures
 - Towns and streets in 11 major cities

- Business terms, such as department names and position titles commonly used in enterprises
- Individual double-byte characters, including basic characters, as defined by IBM

You cannot add or delete entries from this dictionary. However, you may rearrange the related DBCS words so that the words used most frequently are displayed first during DBCS conversion. See “Editing a DBCS Conversion Dictionary” on page D-16 for instructions on rearranging terms.

User-Created Dictionary

A user-created dictionary contains any alphanumeric entries and related DBCS words that you choose to include. You might create a user dictionary to contain words unique to your business or words that you use regularly but that are not included in the system-supplied dictionary.

You can create one or more DBCS conversion dictionaries with any name and store them in any library. When performing DBCS conversion, however, the system only refers to the first user dictionary named QUSRIGCDCT in the user’s library list, no matter how many dictionaries you have or what they are named. Make sure that the library list is properly specified so that the system checks the correct dictionary.

During DBCS conversion, the system checks QUSRIGCDCT before checking QSYSIGCDCT.

Commands for DBCS Conversion Dictionaries

You can use the following commands to perform object management functions with the DBCS conversion dictionary. Specify the OBJTYPE(*IGCDCT) parameter when entering these commands:

- CHGOBJOWN: Change the owner of a DBCS conversion dictionary
- CHKOBJ: Check a DBCS conversion dictionary
- CRTDUPOBJ: Create a duplicate object of the dictionary
- DMPOBJ: Dump a DBCS conversion dictionary

- DMPYSOBY: Dump the system-supplied dictionary
- DSPOBJAUT: Display a user’s authority to the dictionary
- GRTOBJAUT: Grant authority to use the dictionary
- MOVOBJ: Move the dictionary to another library
- RNMOBJ: Rename the dictionary
- RSTOBJ: Restore the dictionary
- RVKOBJAUT: Revoke authority to use the dictionary
- SAVCHGOBJ: Save a changed dictionary
- SAVOBJ: Save the dictionary

The system saves or restores DBCS conversion dictionaries when you use these commands:

- RSTLIB: Restore a library in which the dictionary is stored
- SAVLIB: Save a library in which the dictionary is stored
- SAVSYS: Save QSYSIGCDCT, the system DBCS conversion dictionary, when saving the system

Creating a DBCS Conversion Dictionary:

To create a DBCS conversion dictionary, do the following:

1. Use the Create DBCS Conversion Dictionary (CRTIGCDCT) command.
2. Name the dictionary, QUSRIGCDCT, so it can be used during DBCS conversion. The system uses the dictionary if it is the first user-created dictionary found when searching a user’s library list.

You might call the dictionary by another name while it is being created to prevent application programs from using it for conversion. Later, change the dictionary name using the Rename Object (RNMOBJ) command.

For example, to create a user DBCS conversion dictionary to be stored in the library DBCSLIB, enter:

```
CRTIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT)
```

3. Use the EDTIGCDCT command to put entries and related words into the dictionary after creating it. See “Editing a DBCS Conversion Dictionary” on page D-16 for instructions on putting entries in the dictionary.

Dictionary: Use the Edit DBCS Conversion Dictionary (EDTIGCDCT) command to edit the DBCS conversion dictionary. Use editing to add user-defined characters to the dictionary, so that users can enter characters using DBCS conversion, and rearrange terms in a DBCS conversion dictionary to suit individual needs.

- If you specified a specific string with the ENTRY parameter or if you want to display double-byte characters, you must use a DBCS display station.
- If you did not specify a specific string with the ENTRY parameter, or if you do not want to display double-byte characters, use either a DBCS display station, or a 24-row by 80-column alphanumeric display station.

- Add entries to the dictionary (including adding the first entries to the dictionary after it is

- Delete entries from the dictionary.
- Change entries in the dictionary, such as replacing the DBCS words related to an alphanumeric entry.
- Move the DBCS words related to an alphanumeric entry to rearrange the order in which they appear during DBCS conversion.

Dictionary: After you enter the EDTIGCDCT command, the system presents either the Work With DBCS Conversion Dictionary display or the Edit Related Words display, depending on the value entered for the ENTRY parameter on the command.

Work with DBCS Conversion Dictionary Display:
Use this display to work with alphanumeric entries, such as choosing an entry to edit or deleting an entry. The system displays the Work with DBCS Conversion Dictionary display if you enter *ALL or a generic string for the ENTRY parameter of the EDTIGCDCT command.

HRSLS332-1

the Work with DBCS Conversion Dictionary display.

Edit Related Words Display: Use this display to work with the DBCS words related to an alphanumeric entry. The system displays the Edit Related Words display if you enter a specific string for the ENTRY parameter. The system also displays the

Edit Related Words display if you choose an entry to edit from the Work with DBCS Conversion Dictionary display. Following is an example of the Edit Related Words display:

関連語句の編集

辞書 : QSYSIGCDCT 項目 : 71
ライブラリー . . . : QSYS

編集命令を打鍵して、実行キーを押してください。

NO	関連語句
	***** データの始め *****
0001	アイ
0002	あい
0003	阿井
0004	合
0005	相
0006	哀
0007	挨
0008	始
0009	娃
0010	愛
0011	藍

F3= 終了 F12= 取消し F18= 漢字変換の開始/終了

続く . . .

HRSL3328-2

See the discussion of the EDTIGCDCT command in the *CL Reference* for a complete description of the Edit Related Words display.

Examples of Editing Operations: The following sections give examples of the editing operations that you can perform using the EDTIGCDCT displays:

- Beginning to edit a dictionary
- Adding the first entries in a dictionary
- Deleting an entry
- Moving a related word
- Ending editing the dictionary

Beginning to Edit a Dictionary: Enter the EDTIGCDCT command to start editing the dictionary for any type of editing operation. For example, to put the first entry in the dictionary, enter:

```
EDTIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT) ENTRY(*ALL)
```

Or, to edit the entries beginning with the string ABC enter:

```
EDTIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT) ENTRY('ABC*')
```

Adding the First Entries in a Dictionary: To add the first entries into a dictionary, do the following:

1. Specify ENTRY(*ALL) when entering the EDTIGCDCT command. For example, to edit the dictionary QUSRIGCDCT stored in the library DBCSLIB, enter:

```
EDTIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT) ENTRY(*ALL)
```

The system displays the Work with DBCS Conversion Dictionary display.

2. Enter a 1 in the first option field in the list and enter an alphanumeric entry to be added to the dictionary in the entry field.

The system then displays the Edit Related Words display showing only two lines of data: BEGINNING OF DATA and END OF DATA.

3. Enter an I in the *NBR* field beside the BEGINNING OF DATA line to insert a line.
4. Press the Enter key. The system displays a blank line.
5. On the blank line, enter a DBCS word to be related to the new alphanumeric entry.

If you enter data on the inserted line and leave the cursor on that line, another new line

appears below when you press the Enter key. You can enter another DBCS word on this line, or delete it by leaving it blank, and pressing the Enter key.

- When you finish adding this first entry, press F12 to get the Exit Dictionary Entry display. Enter the Y option to save the entry and then return to the Work With DBCS Conversion

Dictionary display. Enter option 1 again and enter another alphanumeric entry in the entry field to continue adding entries to the dictionary, or press F3 to end editing the dictionary.

Deleting an Entry: Enter a 4 in the input field beside the entry to be deleted as follows:

漢字変換辞書の処理

辞書 : QSYSIGCDCT 項目 : *ALL
ライブラリー . . . : QSYS

サブセット *ALL, 総称*

オプション (および項目) を打鍵して実行キーを押してください。
1= 追加 2= 編集 4= 削除 5= 表示 6= 印刷

OPT	項目	OPT	項目	OPT	項目	OPT	項目
-	?	-	アッパ'チョウ	-	アッパ'リ	-	アイイ'チョウ
-	ア	-	アッジュク	-	アッ	-	アイイト'オリ
-	アッ	-	アッジュクキ'チョウ	-	アッイ	-	アイオ'チョウ
-	アッカ	-	アッジュクヒ	-	アイ	-	アイカ'リ
-	アッケン'ン	-	アッショウ	-	アイイトナム	-	アイカ'リ'チョウ
-	アッケン'チョウ	-	アッスル	-	アイウチ	-	アイカン
-	アッサイ	-	アッセイ	-	アイウ	-	アイガ'
-	アッサク	-	アッセン	-	アイイ	-	アイガ'ン
-	アッサツ	4	アットリ	-	アイイ'ン	-	アイキ

続く ...

F3= 終了 F5= 再表示 F12= 取消し

HRSL3331-2

Moving a Related Word: Moving the words related to an alphanumeric entry changes the order in which the words appear during DBCS conversion. To move a word, do the following:

- Display the Edit Related Words display for the entry in which you want to move DBCS words, either by entering a specific entry with the EDTIGCDCT command, or by choosing an entry to edit from the Work with DBCS Conversion Dictionary display.
- When the display appears, enter an M in the *NBR* field beside the DBCS word to be moved.
- Enter an A in the *NBR* field of the line after which the word will be moved.
- Press the Enter key. The system moves the word, on the line marked M to a position immediately following the line marked with an A.

Ending the Editing Process: To end the editing operation, press F3. The Exit Dictionary Entry display is displayed, and you can choose to save the entry or not. The system then returns you to your basic working display, such as the Command Entry display.

Suggestions for Editing the Dictionary: When editing the DBCS conversion dictionary, consider the following:

- You can use DBCS conversion with the Edit Related Words display to enter related words into a user-created dictionary. See "DBCS Conversion (for Japanese Use Only)" on page D-19 for information on this procedure.
- Place the most commonly used DBCS words at the beginning of the list of related words on the Edit Related Words display. This simplifies DBCS conversion because the system displays the related words in the same order in which those words are listed in the dictionary.

Displaying and Printing the DBCS Conversion Dictionary

Use the Display DBCS Conversion Dictionary (DSPIGCDCT) command to display and print the DBCS conversion dictionary. You can display or print the entire dictionary or just a certain part of it, depending on the value you specify for the ENTRY parameter.

For example, to print the entry ABC from the dictionary QUSRIGCDCT and its related words, enter:

```
DSPIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT) +  
ENTRY(ABC) OUTPUT(*PRINT)
```

To display all of the entries from the system-supplied dictionary QSYSIGCDCT and their related words, enter:

```
DSPIGCDCT IGCDCT(QSYS/QSYSIGCDCT)
```

Following is an example of the display produced by the DSPIGCDCT command. It shows alphanumeric entries and their related words.

漢字変換辞書の表示

辞書 : QSYSIGCDCT 項目 : ?
ライブラリー . . . : QSYS

番号	項目	番号	関連語句
1	?	1	ケ
		2	キ
		3	エ
		4	、
		5	、
		6	、
		7	全
		8	々
		9	ノ
		10	※
		11	下
		12	(株)
		13	No

続行するためには、実行キーを押してください。

F3= 終了 F12= 取消し

続く ...

HRSL3337-2

See the discussion of the DSPIGCDCT command in the *CL Reference* for a complete description of the command and the display it produces.

Deleting a DBCS Conversion Dictionary

Use the Delete DBCS Conversion Dictionary (DLTIGCDCT) command to delete a DBCS conversion dictionary from the system.

In order to delete the dictionary, you must have object existence authority to the dictionary and object operational authorities to the library in which the dictionary is stored.

When you delete a dictionary, make sure that you specify the correct library name. It is possible that many users have their own dictionaries, each

named QUSRIGCDCT, stored in their libraries. If you do not specify any library name, the system deletes the first DBCS conversion dictionary in your library list.

For example, to delete the DBCS conversion dictionary QUSRIGCDCT in the library DBCSLIB, enter:

```
DLTIGCDCT IGCDCT(DBCSLIB/QUSRIGCDCT)
```

DBCS Conversion (for Japanese Use Only)

When you use DBCS display stations to enter double-byte data, you may use the various data entry methods supported on the display station, or you may choose to use the AS/400 DBCS conversion support. DBCS conversion lets you enter an

alphanumeric entry or DBCS code and convert the entry or code to its related DBCS word. DBCS conversion is intended for Japanese character sets and its use is limited for application to other double-byte character sets.

Specifically, DBCS conversion lets you convert the following:

- A string of alphanumeric characters to a DBCS word
- English alphanumeric characters to double-byte alphanumeric characters
- Alphanumeric Katakana to double-byte Hiragana and Katakana letters
- A *DBCS code* to its corresponding double-byte character
- A *DBCS number* to its corresponding double-byte character

Where You Can Use DBCS Conversion

You can use DBCS conversion in the following instances:

- When entering data into input fields of certain SEU displays. For information about which fields you can use with DBCS conversion, refer to the *SEU User's Guide and Reference*.
- When prompting for double-byte data using QCMDXEC. For instructions on this procedure, see the *CL Reference*.
- When entering data into input fields of DBCS display files in user-written applications. Specify DBCS conversion with the DDS keyword IGCCNV. See the *DDS Reference* for information on this keyword.
- When editing the related words on the Edit Related Words display, which is displayed when editing the DBCS conversion dictionary (EDTIGCDCT command). See "Editing a DBCS Conversion Dictionary" on page D-16 for information on the Edit Related Words display.

How DBCS Conversion Works

DBCS conversion is an interactive function between you and the system in which you enter an alphanumeric entry. The system displays related DBCS words, and you choose which word to use.

The system determines which words are related to an alphanumeric entry by checking DBCS conversion dictionaries. The system checks two DBCS conversion dictionaries when performing DBCS conversion. It checks the first user-created dictionary named QUSRIGCDCT found when searching a user's library list. Then, it checks the system-supplied dictionary, QSYSIGCDCT, stored in the library QSYS. (QSYSIGCDCT contains only Japanese double-byte characters.) You can create other user dictionaries, and you can give them names other than QUSRIGCDCT, but the system only refers to the first user-created dictionary named QUSRIGCDCT found in your library list when performing DBCS conversion.

After checking the dictionaries, the system displays words related to the alphanumeric entry. You then position the cursor under the word of your choice, and press the Enter key. The system enters that word where the cursor was positioned when you began DBCS conversion.

Using DBCS Conversion

You can change the user-defined dictionary used during DBCS conversion. Before you change the user-defined dictionary, end your application program or end the command that the system is performing. Then change the dictionary that is used by changing the library list (using the CHGLIBL command).

You can create your own DBCS conversion dictionary for DBCS conversion. The system-supplied dictionary is a collection of entries with a Japanese pronunciation expressed in alphanumeric characters and Japanese DBCS words related to the entry. See "Creating a DBCS Conversion Dictionary" on page D-15 for instructions on this procedure.

If no user-created dictionary is found, the system refers only to QSYSIGCDCT. See "DBCS Conversion Dictionaries" on page D-14 for more information on creating and using DBCS conversion dictionaries.

Performing DBCS Conversion

The following procedure describes how to convert one alphanumeric entry to its related DBCS word using DBCS conversion. You must start DBCS conversion separately for each field in which you want to enter double-byte data.

Note: DBCS conversion is intended for Japanese data entry. Its use with other languages is limited.

While performing DBCS conversion, you can display information about the function by pressing the Help key. Help is available until you end DBCS conversion.

1. Position the cursor in the field in which you want to enter double-byte characters. Insert shift-control characters into the field if they have not yet been inserted. To find out how to insert shift characters, see "Inserting Shift-Control Characters" on page D-6.
2. Position the cursor under the shift-in character, in a blank area between the shift-control characters, or under a double-byte character.

3. Press the function key used to start DBCS conversion.

In SEU, as well as from the Edit Related Words display (displayed when using the EDTIGCDCT command), press F18.

4. Enter the following values:
 - a. In the first field, enter one of the following:
 - I** Inserts the converted word before the character under which you positioned the cursor in step 2.
 - R** Replaces the character under which you positioned the cursor in step 2 with the converted word.
 - b. In the second field, enter one of the following:
 - 1) A string of alphanumeric characters to be converted. The string can have as many as 12 characters.
 - 2) The 4-character DBCS code of a double-byte character.
 - 3) The 2- to 5-digit DBCS number of a double-byte character.
 - c. In the third field, enter one of the following conversion codes:

No entry	Converts the entry in field B from alphanumeric to double-byte by referring to the DBCS conversion dictionaries.
G	Converts the 2- to 5-digit DBCS number in field B to the character it represents.
H	Converts the entry in field B to double-byte Hiragana, upper-case alphabetic, numeric, or special characters.
K	Converts the entry in field B to double-byte Hiragana, lower-case alphabetic, numeric, or special characters.
X	Converts the 4-character DBCS code to the character it represents.

5. Press the Enter key. The system displays words related to the entry in the second field.

If you see a plus (+) sign following the last displayed word, the system has additional words to display. Press the Roll Up key to see these entries. Then, to return to a word displayed earlier, press the Roll Down key.

If a word is shown in a reverse image, the word contains an imbedded blank.

6. Choose the DBCS word from the last field that best suits your needs by positioning the cursor under that DBCS word.
 7. Press the Enter key. The system enters the word where the cursor was positioned in step 2, either by inserting the word or by replacing another word, depending on what you entered in the first field.
 8. Do one of the following:
 - a. Continue using DBCS conversion. Repeat steps 4 through 7 until you finish entering data into the field.
 - b. End DBCS conversion by pressing the *same* function key used to start conversion. The system automatically ends the conversion when you reach the end of the field.
- In SEU, as well as from the Edit Related Words display (displayed when using the EDTIGCDCT command), press F18.

Converting One Alphanumeric Entry to a Double-Byte Entry: The following example shows how to convert one entry and enter it into a field.

1. Position the cursor in the field in which you want to enter double-byte data.

HRSL321-0

3. Press the function key used to start DBCS conversion. For the display just shown, the function key is F18. The system displays a prompt line.

Notice that shift control characters
have been inserted into the field.

日付 : 91/05/23 人 事 情 報 保 守 プログラム名 : EMPMAINT
画面名 : EMPMAINT

社員番号 : 12002 氏名 EP 性別 ____ 年齢 ____
フリガナ _____

現住所 _____
都道府県名 _____ 市町村名 _____

本籍地 _____
都道府県名 _____ 市町村名 _____

職位コード _ 職位名称 _____

部課コード _ 部課名称 _____

給与 _____ 趣味 _____

F3 : 終了 F18: カナ漢字変換

1 _____

HRSL322-0

The prompt line.

Because the cursor was placed under a
shift-in character when conversion was
started, conversion automatically is set to I
(inserting the converted word).

4. Enter an alphanumeric entry to be converted
in the second field.

Leave the third field blank.

日付 : 91/05/23 人 事 情 報 保 守 プログラム名 : EMPMAINT
画面名 : EMPMAINT

社員番号 : 12002 氏名 _____ 性別 ____ 年齢 ____
フリガナ _____

現住所 _____
都道府県名 _____ 市町村名 _____

本籍地 _____
都道府県名 _____ 市町村名 _____

職位コード _ 職位名称 _____

部課コード _ 部課名称 _____

給与 _____ 趣味 _____

F3 : 終了 F18: カナ漢字変換

1 177 _____

HRSL323-0

Enter an alphanumeric entry here.

5. Press the Enter key. The system displays
related DBCS words.

6. Position the cursor under the DBCS word that
you want to enter, if that word is not the first

DBCS word shown. In the following example,
the first word is the one to be entered.

日付 : 91/05/23	人 事 情 報 保 守	プログラム名 : EMPMAINT
		画面名 : EMPMAINT E
社員番号 : 12002	氏名 _____ フリガナ _____	性別 ____ 年齢 ____
現住所 _____		
都道府県名 _____	市町村名 _____	
本籍地 _____		
都道府県名 _____	市町村名 _____	
職位コード _	職位名称 _____	
部課コード _	部課名称 _____	
給与 _____	趣味 _____	
	F3 : 終了	F18: カナ漢字変換
1 771 _____	新井 荒井 新居 荒居 荒 粗	

Position the cursor here.

HRSL324-0

7. Press the Enter key. The DBCS word is
entered into the field.

The system enters the word into the field.

日付 : 91/05/23	人 事 情 報 保 守	プログラム名 : EMPMAINT
		画面名 : EMPMAINT E
社員番号 : _____	氏名 新井 _____ フリガナ _____	性別 ____ 年齢 ____
現住所 _____		
都道府県名 _____	市町村名 _____	
本籍地 _____		
都道府県名 _____	市町村名 _____	
職位コード _	職位名称 _____	
部課コード _	部課名称 _____	
給与 _____	趣味 _____	
	F3 : 終了	F18: カナ漢字変換
1 7071 _____		

HRSL325-0

Converting Many Alphanumeric Entries at One Time: You do not have to continually start DBCS conversion for each alphanumeric entry. Instead, you can do the following:

1. Enter as many alphanumeric entries as will fit into field B. Separate each entry by a blank. Field B contains space for 12 alphanumeric characters:

These are the entries to be converted.

```

  |   |   |
I XXX_YYY_ZZZ_ _

```

A B C D

The system converts the entries one at a time, in the order entered. When the system converts an entry, the system displays the DBCS words related to that entry in field D.

2. Position the cursor under the DBCS word that you want to use.
3. Press the Enter key. Then, the system adjusts field B; the next entry is moved to the position farthest left of the field. The DBCS words related to that entry are displayed in field D.

At this time, you can enter additional alphanumeric entries to be converted at the end of field B.

Converting Alphanumeric Blanks to DBCS

Blanks: You can convert alphanumeric blanks (one position wide) to DBCS blanks (two positions wide, the same width as double-byte characters) using DBCS conversion.

To convert blanks, do the following:

1. Enter one or more blanks in field B.

```

- _____ -
A            B            C                    D

```

2. Press the Enter key. The system displays in field D the same number of DBCS blanks as the alphanumeric blanks that you entered in field B. The DBCS blanks are displayed in reverse image.
3. Press the Enter key again. The system enters the DBCS blanks into the field where you started DBCS conversion.

Changing Alphanumeric Entries or Conversion

Code: If none of the related words shown during conversion are suitable candidates for the alphanumeric entry, and you would like to try a conversion again (by using a different type of conversion or a different alphanumeric entry), do the following:

1. Move the cursor to field B. For example:

Move the cursor here.

```

  |
XXXXXX

```

A B C D

2. Do one of the following:
 - a. Position the cursor under the first position of the field in which you want to enter alphanumeric entries.
 - b. Enter a different alphanumeric entry.
 - c. Change the conversion code in field C, such as from H to K.
3. Press the Enter key.
4. Continue DBCS conversion.

Using DBCS Conversion to Enter Words in the

DBCS Conversion Dictionary: You can use DBCS conversion when entering DBCS words on the Edit Related Words display.

To start DBCS conversion, do the following:

1. Position the cursor at the position where the DBCS word is to be entered.
2. Press F18. The system displays the conversion prompt line at the bottom of the display.

Perform DBCS conversion according to the instructions described in "Performing DBCS Conversion" on page D-21.

Note: You must start and end DBCS conversion separately for each line of data.

Considerations for Using DBCS Con-

version: Consider the following when performing DBCS conversion:

- You can only perform DBCS conversion at a DBCS display station, using the 5556 keyboard.
- You may use DBCS conversion to insert or replace characters only if the line in which double-byte characters are to be inserted has sufficient space.
 - The space available for inserting characters is equal to the number of characters

- from the last character on the line that is not blank to the right edge of the display.
- The space available for replacing characters is equal to the number of characters from the cursor position (including the character marked by the cursor) to the end of the DBCS portion of the field.

The following happens when you do not have enough space:

- If you try to insert or replace a string of characters where there is no space available, the system sends a message.
- If you ignore the message and press the Enter key again, the system truncates the characters in excess of the limit from the right side of the string to be inserted or replaced.

Appendix E. Display File Return Codes

This section contains descriptions of all major and minor return codes for display files. These return codes are set in the I/O feedback area of the display file. The return codes report the results of each operation. The appropriate return code is available to the application program that issued the operation. The program then checks the return code and acts accordingly. Refer to your high-level language manual for information about how to access these return codes.

The return code is a four-digit value: the first two digits contain the major code, and the last two digits contain the minor code. With some return codes, a message is also sent to the job log or the operator message queue (QSYSOPR). You can refer to the message for additional information.

Major Code 00

Major Code 00—Operation completed successfully.

Description: The operation issued by your program completed successfully.

Action: Continue with the next operation.

Code	Description/Action
------	--------------------

0000	Description: For input operations performed by your program, 0000 indicates that some data was received on a successful input operation.
------	---

For output operations performed by your program, 0000 indicates that the last output operation completed successfully.

Action: Your program may continue. One of the messages listed below may have been issued to warn of an unusual

condition that may be significant to your program even though it is not an error.

Messages:

CPF4018 (Status)
CPF4019 (Diagnostic)
CPF4054 (Diagnostic)
CPF4082 (Diagnostic)
CPF4410 (Diagnostic)
CPF5003 (Status)
CPF5508 (Diagnostic)

Major Code 02

Major Code 02—Input operation completed successfully, but your job is being ended (controlled).

Description: The input operation issued by your program was completed successfully. However, your job is being ended (controlled).

Action: Your program should complete its display processing as soon as possible to allow your program to complete in an orderly manner. The system eventually changes a job ended (controlled) to a job ended (immediate) and forces all processing to stop for your job.

Code	Description/Action
------	--------------------

0200	Description: On a successful input operation, an indication was received that a job ended (controlled) request is pending. Also, 0200 indicates that some data was received.
------	---

Action: Your program may continue. However, the recommended action is to complete the display processing and end the program, because the system will eventually cancel your job and cause all processing to stop for your job.

Major Code 03

Major Code 03—Input operation completed successfully, but no data received.

Description: The input operation was completed successfully, but no data was received.

Action: Check the minor return code for additional information, and continue with the next operation.

Code Description/Action

0300 Description: No data was received on a successful input operation. Examples of conditions causing this are no data being available on a get-relative or a get-next-changed operation to a subfile record format.

Action: Continue with whatever processing is appropriate. For example, if your program issued a get-next-changed operation to a subfile record format, then a 0300 indicates that there are no more subfile records changed by the user and no more user input data to process.

Messages:

CPF5017 (Notify)
CPF5020 (Notify)
CPF5037 (Notify)

0309 Description: Your program is being ended (controlled). No data was received.

This return code is only applicable to the read-from-invited-devices operation.

Action: Your program can continue processing. However, the recommended action is to complete the display processing and end the program, because the system will eventually cancel your job and cause all processing to stop for your job.

Messages:

CPF4741 (Notify)

0310 Description: The time interval specified by the WAITRCD value for the display file has ended.

This return code is only applicable to the read-from-invited-devices operation.

Note: Because no device is associated with the completion of this operation, the device name in the I/O feedback area contains an *N.

Action: Issue the operation to perform the intended function after the specified time interval has ended. For example, if you are using the time interval to control the length of time to wait for data, you can then issue another read-from-invited-devices operation to receive the data.

Messages:

CPF4742 (Status)
CPF4743 (Status)

Major Code 04

Major Code 04—Output exception occurred.

Description: An output exception occurred because your program attempted to send output when it should have been receiving the data that had already been sent by the display. Your data, associated with this output operation, was not sent to the display. Your program can attempt to send its output later.

Action: Issue an input operation to receive the data.

Code Description/Action

0412 Description: An output exception occurred because your program attempted to send data when it should have been receiving the data that had already been sent by the display. Your program data was not sent and should be sent later, after the data from the display has been received.

Action: Issue an input operation to receive the data.

Messages:

CPF4737 (Notify)

Major Codes 08–11

Major Codes 08 and 11—Miscellaneous program errors occurred.

Description: The operation just attempted by your program was not successful. The operation may have failed because it was issued at the wrong time.

Action: Refer to the individual return code descriptions for the appropriate recovery actions.

Code	Description/Action
------	--------------------

0800	Description: The acquire operation just performed was not successful. It tried to acquire a device that had already been acquired.
------	---

Action: If the display device requested by the original acquire operation is the one needed, your program can begin using it because it is already available. If a different device is required, issue another acquire operation for a different device name.

Messages:

CPD4077 (Diagnostic)
CPF50A0 (Status)

1100	Description: The read-from-invited-devices operation was not successful because no devices were invited.
------	---

Action: Issue an invite function followed by a read-from-invited-devices operation.

Messages:

CPF4740 (Notify)

Major Code 34

Major Code 34—Input exception occurred.

Description: The input operation attempted by your program was not successful. The data received was too long for the record format specified on the input operation.

Action: Refer to the individual return code descriptions for the appropriate recovery actions.

Code	Description/Action
------	--------------------

3431	Description: The input operation issued by your program was not successful because the length of the data received from the display exceeds the receive data length specified in the user-defined data stream. The data received is truncated.
------	---

This return code is only applicable to input operations using a record format specifying a user-defined data stream (USRDFN DDS keyword).

Action: Close the device file and end your program. Then, change your program so that the input record length is at least as long as the data record to be received.

Messages:

CPF5062 (Notify)

Major Code 80

Major Code 80—Permanent system or file error (not recoverable).

Description: A file or system error that is not recoverable has occurred. Recovery is unlikely until the problem causing the error has been corrected.

Action: The following general actions can be taken by your program for each 80xx return code. Other specific actions are given in each return code description.

- Continue processing without the display.
- Close the device file and open the file again. If the operation is still unsuccessful, try it again only a limited number of times. (The number of times should be specified in your program.)
- End.

Code	Description/Action
------	--------------------

8081	Description: The operation was not successful because a system error condition was detected.
------	---

Action: Your display device may need to be varied off and then on again. Your program can either:

- Continue processing without the display device.
- Close the device file and open the file again.
- End.

Messages:

CPF4182 (Escape)	CPF5416 (Escape)
CPF4510 (Escape)	CPF5418 (Escape)
CPF5192 (Escape)	CPF5423 (Escape)
CPF5257 (Escape)	CPF5429 (Escape)
CPF5403 (Escape)	CPF5431 (Escape)
CPF5404 (Escape)	CPF5433 (Escape)
CPF5405 (Escape)	CPF5434 (Escape)
CPF5408 (Escape)	CPF5441 (Escape)
CPF5409 (Escape)	CPF5447 (Escape)
CPF5410 (Escape)	CPF5455 (Escape)
CPF5411 (Escape)	CPF5456 (Escape)
CPF5414 (Escape)	CPF5507 (Escape)
CPF5415 (Escape)	

8082 Description: The operation was not successful because the display device is unusable. This may occur because a cancel reply has been taken to an error recovery message for the device or because the display has been held by a Hold Communications Device (HLDCMNDEV) command. No operations should be issued to the device.

Action: Communications with the display cannot be resumed until the device has been reset to a varied-on state. If the device has been held, use the Release Communications Device (RLSCMNDEV) command to reset the device. If the device is in an error state, vary the device off and then on again. Once the device is reset, normal operation can be started by opening the display device file again. Your program can either:

- Continue processing without the display device.
- Close the device file and open the file again.
- End.

Messages:

CPF4354 (Escape)
CPF5269 (Escape)

80A6 Description: A Systems Network Architecture (SNA) unbind operation was not successful on a close or release opera-

tion. This may be the result of a device configuration error. The device may be unusable. No operations should be issued to the device.

Action: Refer to the device response code in the accompanying error message to determine the cause of the failure. Vary the device off and then on again to reset the error. Correct the error and try your program again.

Messages:

CPF4527 (Escape)

80B3 Description: The open operation was not successful because the display file is not available. The file cannot be opened again until the necessary resources are available.

Action: Your program can wait for the display file to become available, then issue another open operation. Otherwise, you may continue other processing or end the program.

Consider increasing the WAITFILE parameter with the Change Display File (CHGDSPF) command or Override with Display File (OVRDSPF) command to allow more time for the file to become available.

Messages:

CPF4128 (Escape)

80C0 Description: An error that is not recoverable has occurred on the display device.

Action: Your display devices may need to be varied off and then on again. Your program can either:

- Continue processing without the display station.
- Close the device file and open the file again.
- End.

Messages:

CPF5103 (Escape)	CPF5420 (Escape)
CPF5192 (Escape)	CPF5421 (Escape)
CPF5412 (Escape)	CPF5430 (Escape)
CPF5413 (Escape)	CPF5437 (Escape)
CPF5419 (Escape)	CPF5439 (Escape)

80EB Description: An open operation was not successful because an open option that is not valid or a combination of options that is not valid was specified in your program, in the display file, or in an override command.

Action: Close the display file, correct the problem, and open the file again. See the individual messages to determine what options are not valid.

Messages:

CPF4062 (Escape)	CPF4345 (Escape)
CPF4129 (Escape)	CPF5151 (Escape)
CPF4148 (Escape)	CPF5510 (Escape)
CPF4156 (Escape)	CPF5511 (Escape)
CPF4163 (Escape)	CPF5512 (Escape)
CPF4169 (Escape)	CPF5513 (Escape)
CPF4191 (Escape)	CPF5552 (Escape)
CPF4238 (Escape)	

80ED Description: The open operation was not successful because the record format descriptions in the file have changed since your program was compiled.

Action: Close the file and end the program. Determine whether the changes affect your application program. If they do, recompile the program. If the changes do not affect your program, the file should be changed or overridden to LVLCHK(*NO). When LVLCHK(*NO) is specified, the system does not compare the record format descriptions.

Messages:

CPF4131 (Escape)

80F8 Description: An operation to a file was not successful because the file is marked in error.

Action: Close the file. Refer to messages in the job log to determine what errors occurred. Take the appropriate action for those errors.

Messages:

CPF4132 (Escape)	CPF5129 (Escape)
CPF4213 (Escape)	CPF5144 (Escape)
CPF4550 (Escape)	CPF5427 (Escape)

Major Code 81

Major Code 81—Permanent device error (not recoverable).

Description: A device-related error that is not recoverable occurred during an I/O operation. Any attempt to continue using this display device will probably fail again until the cause of the problem is found and corrected, but operations directed to other display devices associated with the file should be expected to work.

Action: The following general actions can be taken for each 81xx return code. Other specific actions are given in each return code description.

- Continue processing without the display device.
- Release the device or close the file, correct the problem, and acquire the device again or open the file. If the operation is still unsuccessful, try it again only a limited number of times. (The number of times should be specified in your program.)
- End.

Several return codes indicate that an error condition must be corrected by varying the device off and on again.

Code	Description/Action
------	--------------------

8181	Description: A system error condition was detected during the I/O operation to the device.
------	---

	Action: Release the device in error or close the file. You may need to vary the device off and on again to clear the error. Determine the cause of the failure from the accompanying message. Check for any system operator messages indicating that additional corrective action must be performed. Open the file again or acquire the device to continue.
--	--

	Messages:
--	------------------

	CPF4553 (Escape)
	CPF4725 (Escape)
	CPF5105 (Escape)
	CPF5189 (Escape)

CPF5254 (Escape)

8191 Description: The operation was not successful because a permanent line error occurred, and the system operator took a recovery option in response to the line error message. (You can find out what type of line error occurred by asking the system operator.) The device has been marked unusable.

Action: Release the device in error or close the file. Vary the device off and on again to clear the error. Open the file again or acquire the device to continue.

Messages:

CPF4526 (Escape)
CPF4542 (Escape)
CPF4551 (Escape)
CPF5128 (Escape)
CPF5143 (Escape)
CPF5198 (Escape)

8197 Description: An error condition that is not recoverable was detected at the device. An example of such an error is the user turning off the display device.

Action: Release the device in error or close the file. The display device may need to be varied off and then on again to clear the error. Refer to the accompanying error message for additional information regarding the source of the specific error detected. Open the file or acquire the device again to continue.

Messages:

CPF4149 (Escape)	CPF5106 (Escape)
CPF4197 (Escape)	CPF5140 (Escape)
CPF4524 (Escape)	CPF5143 (Escape)
CPF4533 (Escape)	CPF5199 (Escape)
CPF4538 (Escape)	CPF5265 (Escape)
CPF5047 (Escape)	

81C2 Description: The operation issued by your program was not successful because the Systems Network Architecture (SNA) session with the display is not active.

Action: Release the device or close the file. Vary the device off and on again to clear the error. Open the file or acquire the device again to continue.

Messages:

CPF5170 (Escape)
CPF5422 (Escape)

Major Code 82

Major Code 82—Open or acquire operation failed.

Description: An attempt to open the display file or acquire the display device was not successful. The error may be recoverable or permanent, but is limited to the specific display device. Recovery is unlikely until the problem causing the error has been corrected.

Action: The following general actions can be taken for each 82xx return code. Other specific actions are given in each return code description. You can either:

- Continue processing without the device.
- Release the device or close the file, correct the problem, and acquire the device or open the file again. A subsequent operation could be successful if the error occurred because of some temporary condition such as the device being in use at the time.

If the operation is still unsuccessful, try it again only a limited number of times. (The number of times should be specified in your program.)

- If the attempted operation was an acquire operation, release the device and issue the acquire operation again.
- If the attempted operation was an open operation, close the file and issue the open operation again.

- End.

Several return codes indicate that an error condition must be corrected by changing a value in the file. To change a parameter value for the file, use the Change Display File (CHGDSPF) or Override with Display File (OVRDSPF) command.

Code	Description/Action
------	--------------------

8281	Description: A system error condition was detected on an open or acquire operation. The file may previously have been
------	--

in error, or the file could not be opened due to a system error.

Action: Determine the cause of the failure from the accompanying message. Check for any system operator messages indicating that additional corrective action must be performed.

The display device may need to be varied off and then on again to clear the error. Your program can either:

- Continue processing without the display device.
- Release the device or close the file, correct the problem, and acquire the device or open the file again.
- End.

Messages:

CPF4168 (Escape)	CPF5410 (Escape)
CPF4182 (Escape)	CPF5411 (Escape)
CPF4221 (Escape)	CPF5424 (Escape)
CPF5105 (Escape)	CPF5447 (Escape)
CPF5254 (Escape)	CPF5455 (Escape)
CPF5257 (Escape)	

8282 Description: The open or acquire operation was not successful because the display device is unusable. This may occur because a cancel reply has been taken to an error recovery message for the device or because the display has been held by a Hold Communications Device (HLDCMNDEV) command. No operations should be issued to the device. Communications with the display cannot be resumed until the device has been reset to a varied-on state.

Action: Close the display device file. If the device has been held, use the Release Communications Device (RLSCMNDEV) command to reset the device. If the device is in an error state, vary the device off and then on again. Once the device is reset, start normal operation by opening the display device file again.

Messages:

CPF4171 (Escape)
CPF4354 (Escape)
CPF5548 (Escape)

8291 Description: A permanent line error occurred on an open or acquire operation. The device has been marked unusable.

Action: Release the device in error or close the file. Vary the device off and on again to clear the error. Open the file again to continue.

Messages:

CPF4146 (Escape)
CPF4179 (Escape)
CPF4193 (Escape)
CPF4291 (Escape)
CPF5198 (Escape)
CPF5260 (Escape)

8297 Description: The open or acquire operation has ended abnormally due to an error condition detected at the display device that is not recoverable. An example of such an error is the user turning off the display device.

Action: Release the device in error or close the file. The display device may need to be varied off and then on again to clear the error. Refer to the accompanying error message for additional information regarding the source of the specific error detected. Open the file or acquire the device again to continue.

Messages:

CPF4192 (Escape)
CPF5047 (Escape)
CPF5106 (Escape)
CPF5140 (Escape)
CPF5143 (Escape)
CPF5199 (Escape)

82A6 Description: The open or acquire operation failed because the Systems Network Architecture (SNA) bind command was not successful.

Action: Ensure that the display device with which your program is communicating is configured properly. Refer to the device response codes in the accompanying error message for additional information regarding the specific error detected.

Messages:

CPF4124 (Escape)
CPF4190 (Escape)

CPF5103 (Escape)
CPF5517 (Escape)

82A8 Description: The acquire operation was not successful because the maximum number of devices allowed for the display file has been reached.

Action: Your program can recover by releasing a different device and issuing the acquire operation again. If more devices are needed, close your file and increase the MAXDEV value in the display file.

Messages:

CPF4745 (Escape)
CPF5041 (Status)
CPD4757 (Diagnostic)

82A9 Description: The acquire operation was not successful because the requesting program device is not available. The requesting program device may not be available because your program is not running in an interactive job.

Action: Your program can continue without the display, attempt to use a different display device, or end.

If your program needs to use the requesting program device, make sure that it runs in an interactive job.

Messages:

CPF4366 (Escape)
CPF5381 (Escape)

82AA Description: The open or acquire operation was not successful because the display device description was not found.

Action: Your program can continue without the display, attempt to use a different display device, or end.

Verify that the name of the display device was correctly specified in the DEV parameter on the CRTDSPF, CHGDSPF, CRTDEVDSP, or OVRDSPF command.

Messages:

CPF4103 (Escape)
CPF4747 (Escape)

82AB Description: The open or acquire operation was not successful because the display device was not varied on.

Action: Your program can continue without the display, attempt to acquire a different display device, or end. Vary on the display device and attempt the open or acquire operation again.

If you want your program to continue with the same display, release the device or close the file, correct the problem, and acquire the device or open the file again.

Messages:

CPF4285 (Escape)
CPF5333 (Escape)

82B3 Description: The open or acquire operation was not successful because the display device you are acquiring is in use in another process.

Action: Wait for the display device to become available, then issue the acquire operation again. Otherwise, you may continue other processing without the display, or end the program.

You can use the Work with Configuration Status (WRKCFGSTS) command to determine which job is using the display device.

Consider increasing the WAITFILE parameter of the CHGDSPF or OVRDSPF command to allow more time for the device to become available.

Messages:

CPF4109 (Escape)
CPF4130 (Escape)
CPF4282 (Escape)
CPF5217 (Escape)
CPF5332 (Escape)

82EE Description: An open or acquire operation was attempted to a device that is not supported for a display file.

Your program is attempting to acquire a device that is not a valid display device; or it is trying to acquire the requesting program device, but the requesting program device for the job is a communications device, not a display device.

Action: Your program can continue without the display, attempt to acquire a different display device, or close the file and end.

Verify that the name of the display device was specified correctly on the CHGDSPF, CRTDEVDSP, CRTDSPF, or OVRDSPF command.

If your program was attempting to acquire the requesting program device, verify that your program is running in an interactive job so that the requesting program device is a display device.

Messages:

CPF4105 (Escape)
CPF4223 (Escape)
CPF4760 (Escape)
CPF5038 (Escape)

82EF Description: An open or acquire operation was attempted for a device that the user is not authorized to or that is in service mode.

Action: Your program can continue without the display, attempt to acquire a different display device, or end.

If the operation was an open operation, close the file, correct the problem, and then issue the open operation again. If the operation was an acquire operation, correct the problem and issue the acquire operation again.

For authority errors, obtain authority to the device from your security officer or device owner. If the device is in service mode, the system service tools (SST) function is currently using the device. Wait until the device is available to issue the operation again.

Messages:

CPF4104 (Escape)
CPF4186 (Escape)
CPF5278 (Escape)
CPF5279 (Escape)

82F8 Description: Your program attempted an acquire operation to a device that is marked in error due to a previous error during an I/O or acquire operation.

Action: Release the device or close the file, correct the previous error, and acquire the device or open the file again.

Messages:

CPF5293 (Escape)

Major Code 83

Major Code 83—Device error occurred (recoverable).

Description: An error occurred during an I/O operation, but the display device is still usable. Recovery within your program might be possible.

Action: The following general actions can be taken for each 83xx return code. Other specific actions are given in each return code description.

- Continue processing without the display device.
- Correct the problem and continue processing with the display device. If the attempt to recover from the operation is unsuccessful, try it again only a limited number of times. (The number of times should be specified in your program.)
- End.

Several return codes indicate that an error condition must be corrected by changing a value in the display file. To change a parameter value for the file, use the Change Display File (CHGDSPF) or Override with Display File (OVRDSPF) command.

Code Description/Action

830B Description: Your program has attempted to issue an input or output operation either before the device was acquired or after it was released.

Your program may have improperly handled a *permanent device* or *acquire failed* error.

Action: Verify that your program tries no input or output operation with a display device that is not connected to the file and that return codes from acquire or I/O operations are handled properly.

Messages:

CPD4079 (Diagnostic) CPF5070 (Escape)
CPF4739 (Status) CPF5170 (Escape)
CPF5067 (Escape) CPF5217 (Escape)
CPF5068 (Escape)

831D Description: The operation just attempted by your program was rejected because a parameter was not valid, out of limits, or missing.

Action: Your program can bypass the failing step and continue, or close the file and end. Refer to the accompanying message to determine what parameter was incorrect. Correct the error in your program before attempting to try the operation again.

Messages:

CPF4912 (Notify) CPF5021 (Notify)
CPF5002 (Notify) CPF5218 (Escape)
CPF5008 (Notify) CPF5302 (Escape)
CPF5012 (Notify) CPF5303 (Escape)
CPF5014 (Notify) CPF5398 (Escape)

831E Description: The operation just issued by your program was not valid or a combination of operations that is not valid was specified. The error may have been caused by one of the following:

- Either your program issued an operation with an unrecognized code, or the operation specified by the code or DDS keyword is not supported by the display.
- A combination of operations or keywords that is not valid was requested.
- A user-defined data stream contained a command that is not valid for the display.

Action: Your program can bypass the operation that is not valid and continue, or close the file and end. Refer to the accompanying message to determine why the operation was rejected. Correct the error in your program before attempting to try the failing operation again.

Messages:

CPF4564 (Escape) CPF5055 (Notify)
CPF5005 (Notify) CPF5056 (Notify)
CPF5011 (Notify) CPF5059 (Notify)
CPF5039 (Notify) CPF5066 (Notify)
CPF5045 (Notify) CPF5149 (Escape)
CPF5051 (Notify)

831F Description: A length that is not valid was specified on the operation.

On an output operation, your program has tried to send a data record having a length that exceeds the maximum record length allowed for the display device. The data has been truncated.

Action: Issue the output operation again with a smaller output length. The record length for a non-field-level display file cannot exceed the display size. The record length for any display file must be no greater than 32 763 characters.

Messages:

CPF4010 (Diagnostic)
CPF4078 (Diagnostic)

8322 Description: The attempted operation is not valid in the current state. Either a write operation was attempted while your program was not in the send state or a subfile operation was attempted when the subfile was not active.

Action: Your program can bypass the operation that is not valid and continue, or close the file and end. Correct the sequence of operations in your program before attempting to run the job again.

Messages:

CPF5013 (Notify)
CPF5060 (Notify)

832D Description: Your program attempted an operation that is not valid when an invite operation is outstanding. Once you have issued an invite or get-no-wait operation, another invite operation cannot be issued for the same display device until the first invite has been completed by a read or read-from-invited-devices operation.

Action: Issue an input operation to receive the data that was invited before issuing another invite operation. Otherwise, close the file and end. If a coding error in your program caused the error, correct the sequence of operations in your program.

Messages:

CPF5052 (Notify)

8343 Description: An attempt was made to add another record to a subfile after the subfile was full.

Action: Your program can clear the subfile, or continue without adding more records to the subfile. Otherwise, close the file and end.

Increase the subfile length in the DDS statements. If a coding error in your program caused the error, correct your program.

Messages:

CPF5043 (Notify)

83E0 Description: Your program attempted to issue an operation using a record format that was not defined for the display file, or omitted the record format name.

Action: Check the name of the record format in your program to be sure it is correct. Then check that the record format is defined properly in the DDS for the file.

Messages:

CPF5022 (Notify)
CPF5023 (Notify)
CPF5053 (Notify)
CPF5054 (Notify)

83E1 Description: An error occurred during an I/O operation. The requesting program device was set to automatically disconnect your program. The same user signed on to the same display device, so the program was started up again. The display was cleared of any data present when the error occurred.

Action: Branch to a normal starting point in your program and rewrite the display. There is no need to perform a close or open operation on the display files that were active when the error occurred.

Messages:

CPF509F (Notify)

83E8 Description: Your CL program issued an End Receive (ENDRCV) command when there is no outstanding read-with-no-wait operation.

Action: Your program can issue an output operation to continue sending, issue an input operation to begin receiving, or close the file and end. Correct the error in your program before attempting to repeat the failing operation.

Messages:

CPF4910 (Notify)

83F6 Description: Your program sent data to the display that is not valid. The data type may not be correct for the field in which it is used.

Action: Check the name of the record format in your program to be sure it is correct. Verify that the data definition statements in your program match the output record defined in the DDS for the

file. Correct the error in your program before attempting to repeat the failing operation.

Messages:

CPF5063 (Notify)

CPF5216 (Escape)

CPF5301 (Escape)

83F8 Description: Your program attempted an I/O operation to a device that is marked in error due to a previous error during an I/O or acquire operation.

Action: Release the device or close the file, correct the previous error, and acquire the device or open the file again.

Messages:

CPF5293 (Escape)

Appendix F. Edit Codes

OS/400 Edit Codes

The following table summarizes the functions provided by OS/400 edit codes.

Table F-1 (Page 1 of 2). Summary Chart for OS/400 Edit Codes

Edit Codes	Commas ¹ Displayed	Decimal Points ¹ Displayed	Sign Displayed When Negative Value	Blank Value of QDECFMT System Value	I Value of QDECFMT System Value	J Value of QDECFMT System Value	Leading Zero Suppressed
1	Yes	Yes	No sign	.00 or 0	,00 or 0	0,00 or 0	Yes
2	Yes	Yes	No sign	Blanks	Blanks	Blanks	Yes
3		Yes	No sign	.00 or 0	,00 or 0	0,00 or 0	Yes
4		Yes	No sign	Blanks	Blanks	Blanks	Yes
A	Yes	Yes	CR	.00 or 0	,00 or 0	0,00 or 0	Yes
B	Yes	Yes	CR	Blanks	Blanks	Blanks	Yes
C		Yes	CR	.00 or 0	,00 or 0	0,00 or 0	Yes
D		Yes	CR	Blanks	Blanks	Blanks	Yes
J	Yes	Yes	–(Minus)	.00 or 0	,00 or 0	0,00 or 0	Yes
K	Yes	Yes	–(Minus)	Blanks	Blanks	Blanks	Yes
L		Yes	–(Minus)	.00 or 0	,00 or 0	0,00 or 0	Yes
M		Yes	–(Minus)	Blanks	Blanks	Blanks	Yes
N	Yes	Yes	–(Minus)	.00 or 0	,00 or 0	0,00 or 0	Yes
O	Yes	Yes	–(Minus)	Blanks	Blanks	Blanks	Yes
P		Yes	–(Minus)	.00 or 0	,00 or 0	0,00 or 0	Yes
Q		Yes	–(Minus)	Blanks	Blanks	Blanks	Yes
Y ²							Yes

Table F-1 (Page 2 of 2). Summary Chart for OS/400 Edit Codes

Edit Codes	Commas ¹ Displayed	Decimal Points ¹ Displayed	Sign Displayed When Negative Value	Blank Value of QDECFMT System Value	I Value of QDECFMT System Value	J Value of QDECFMT System Value	Leading Zero Suppressed
Z ³							Yes

Notes:

1. The QDECFMT system value determines the decimal point character (period in U.S. usage), the character used to separate groups of three digits (comma in U.S. usage), and the type of zero suppression (depending on comma and period placement). For more information on the QDECFMT system value, see the *Guide to Programming Displays*.
2. The Y edit code suppresses the farthest left zero of a date field that is three to six digits long, and it suppresses the two farthest left zeros of a field that is seven positions long. The Y edit code also inserts slashes (/) between the month, day, and year according to the following pattern:

nn/n
nn/nn
nn/nn/n
nn/nn/nn
nnn/nn/nn

If the DATE keyword is specified with EDTCDE(Y), the separator character used is the job attribute, DATSEP. The slash (/) is the default DATSEP. If, at file creation time, DATFMT is JUL (Julian), the date is normally formatted as nn/nnn and EDTCDE(Y) is not valid.

3. The Z edit code removes the sign (plus and minus) from a numeric field. The sign of the units position is changed to a hexadecimal F before the field is written.

Note: Edit code X can be specified but has no effect on display files and is ignored. The AS/400 system hardware operates with a preferred sign of F, which is equivalent to using edit code X. Edit code X causes a blank keyboard shift (position 35) to default to numeric only (attribute Y), but has no

other effect on the display file and is ignored for all other processing. The display length of the field is determined by the keyboard shift and not by edit code X (the default numeric-only Y attribute may add 1 position to the field for decimals).

Examples of Editing Using OS/400 Edit Codes

The following table shows valid edit codes with examples of unedited source data and edited output. Zero suppression and decimal characters are determined by the system value QDECFMT.

The date separator character is determined by the job attribute DATSEP. In this figure, QDECFMT is assumed to equal x, and DATSEP is assumed to equal /.

Table F-2. Valid Edit Codes, Source Data, and Edited Output

Edit Codes	Positive Number—Two Decimal Positions	Positive Number—No Decimal Positions	Negative Number—Three Decimal Positions ¹	Negative Number—No Decimal Positions ¹	Zero Balance—Two Decimal Positions ¹	Zero Balance—No Decimal Positions ¹
Unedited	1234567	1234567	xxxx.125—	xxxx.125—	xxxxxx	xxxxxx
1	12,345.67	1,234,567	.125	125	.00	0
2	12,345.67	1,234,567	.125	125		
3	12345.67	1234567	.125	125	.00	0
4	12345.67	1234567	.125	125		
A	12,345.67	1,234,567	.125CR	125CR	.00	0
B	12,345.67	1,234,567	.125CR	125CR		
C	12345.67	1234567	.125CR	125CR	.00	0
D	12345.67	1234567	.125CR	125CR		
J	12,345.67	1,234,567	.125—	125—	.00	0
K	12,345.67	1,234,567	.125—	125—		
L	12345.67	1234567	.125—	125—	.00	0
M	12345.67	1234567	.125—	125—		
N	12,345.67	1,234,567	-.125	-125	.00	0
O	12,345.67	1,234,567	-.125	-125		
P	12345.67	1234567	-.125	-125	.00	0
Q	12345.67	1234567	-.125	-125		
Y ²	123/45/67	123/45/67	0/01/25	0/01/25	0/00/00	0/00/00
Z ³	1234567	1234567	125	125		

Notes:

1. The x represents a blank.
2. The Y edit code suppresses the farthest left zero of a date field that is three to six digits long, and it suppresses the two farthest left zeros of a field that is seven positions long. For more information, see the second footnote in Table F-1 on page F-1.
3. The Z edit code removes the sign (plus or minus) and suppresses leading zeros.

User-Defined Edit Codes

You can define five edit codes to provide more editing function than is available with the OS/400 edit codes, and to handle common editing functions that would otherwise require the use of an edit word.

You can define your own edit codes using the Create Edit Description (CRTEDTD) command.

Table F-3. IBM-Supplied Edit Descriptions

Description	QEDIT5 Edit Codes ¹	QEDIT6 Edit Codes ¹	QEDIT7 Edit Codes ¹	QEDIT8 Edit Codes ¹	QEDIT9 Edit Codes ¹
Integer mask	xxx,xxx,xxx,xxx,xx0	xxx,xxx,xxx,xxx,xx0	xxx,xxx,xxx,xxx,x0x	xxx,xxx,xxx,xxx,x0x	0xx-xx-xx
Decimal point	. (period)	. (period)	. (period)	. (period)	. (period)
Fraction mask	xxxxxxxx	xxxxxxxx	xxxxxxxx	xxxxxxxx	None
Fill character	x	x	x	x	x
Floating currency symbol	None	None	None	\$	None
Zero balance	Replace with fill character	Replace with fill character	Normal editing rules	Normal editing rules	Normal editing rules
Negative status	CR	- (minus sign)	- (minus sign)	- (minus sign)	None
Positive status	DR	None	None	None	None
Left constant	None	None	\$	None	None
Right constant	None	x*	None	None	None
¹ The x represents a blank.					

An edit description contains the following items:

Integer mask

Describes the editing of the integer portion of a field. All characters except blank, zero, and ampersand (&) are treated as constants:

- Blank means to replace the blank with a digit if zero suppression has ended; otherwise, replace the blank with the fill character.
- The zero to the farthest left means to replace the zero with a digit and end zero suppression. All other zeros are treated as constants.
- Ampersand means to replace the & with a blank.

Decimal point

Defines what character is used as the decimal point. By default, a period (.) is used.

Fraction mask

Describes the editing of the fraction portion of a field. Ampersand is the same as for the integer mask. All zeros are treated as constants and all blanks are replaced with digits (no fill character is used).

Fill character

Defines what character is used in each position of a result that is zero-suppressed. By default, a blank is used.

Floating currency symbol

Defines the floating currency symbol to be used to edit the field.

Zero balance

Specifies how zero values are to be edited. They can be edited using the fill character or the integer and fraction masks.

Negative status

Defines the characters that are to follow the edited result of a field if the field is negative.

Positive status

Defines the characters that are to follow the edited result of a field if the field is positive or zero.

Left constant

Defines a constant that is to be the portion to the farthest left of the edited result of a field.

Right constant

Defines a constant that is to be the portion to the farthest right of the edited result of a field.

- Length of truncated integer mask
- Length of decimal point (which is always 1 unless no decimal point is used)
- Length of truncated fraction mask
- Length of negative or positive status value (whichever is longer)

Note: If the text you specify for negative status is a different length than the one for positive status, the CRTEDTD command pads the shorter value with blanks. This makes the shorter value equal in length to the longer value.

- Length of right constant
- If either the integer mask or fraction mask does not contain enough digit replace characters for the field to be edited, the field is not edited and is ignored.

Using User-Defined Edit Codes

The following rules apply to using edit descriptions. These rules are affected by the length and decimal positions of the field being edited.

- The field to be edited is aligned by the integer and fraction masks.
- The entire integer mask is not always used. The integer mask is truncated on the left side immediately before the farthest left significant digit or farthest left, or forced, zero.
- The decimal point immediately follows the integer mask and the fraction mask immediately follows the decimal point. If no decimal point is used, the fraction mask immediately follows the integer mask.
- The entire fraction mask is not always used. The fraction mask is truncated on the right side immediately following the farthest right significant digit.
- The width of the edited result is equal to the total of the following:
 - Length of left constant
 - Length of floating currency symbol

Example of a User-Defined Edit Code

The following Create Edit Description (CRTEDTD) command shows how to create an edit description to edit a numeric field and indicate if the value is a credit or debit (x indicates a blank):

```
CRTEDTD  EDTD(5) INTMASK('xxx,xxx,xx')
          FRACMASK('xxxx') NEGSTS('DEBITx')
          POSSTS('CREDIT') LFTCNS('$')
          RUTCNS('xB**')
```

The field that uses the previous edit description contains the value 001234 and has two decimal positions. The edited field looks like this:

```
$xx12.34CREDITx**
```

Note that when you create an edit description, you specify only the number (5, 6, 7, 8, or 9) that is associated with the edit code. The system automatically affixes QEDIT to the number you specify. (In the preceding example, EDTD(5) was specified. This would then be QEDIT5.)

Appendix G. System/36-Compatible Display Data Management

This appendix describes how to use OS/400 display data to provide System/36-compatible functions. Additional information on System/36 compatibility can be found in the *DDS Reference*.

In order to migrate System/36 applications that use display devices, OS/400 display data management has functions that allow the operating system to work like System/36 work station data management. The level of compatibility with the System/36 depends on the following:

- The User Display Management (USRDSPMGT) keyword

This keyword is automatically put in the DDS source when the \$SFGR utility or the Create System/36 Display File (CRTS36DSPF) CL command converts SFGR source to DDS source. Specifying this keyword indicates that the System/36 work station data management function is to be used instead of OS/400 display data management functions.

For example, the USRDSPMGT keyword specifies that the cursor is positioned as it is on the System/36. If the USRDSPMGT keyword is not specified, the cursor is positioned according to the OS/400 display data management rules.

- The programming language used to write the program

To get application-level System/36 compatibility, the programs must be written in System/36-compatible RPG II or System/36-compatible COBOL.

For example, if a program is written in a System/36-compatible language, the file status codes set by the high-level language and return codes set by data management are the same as the System/36. If a program is not written in a System/36-compatible language, the file status codes and return codes are the AS/400 values.

- The environment where the application runs
To get environment-level System/36 compatibility, the programs must run in the System/36 environment.

For example, if an application running in the System/36 environment uses the MSGID DDS keyword to display the message from a user message file, the message file used is the message file specified on the USER1 parameter of the MEMBER OCL statement. If this same application is not run in the System/36 environment, the message file used is a message file named USR1 in the job's library list.

The remainder of this appendix contains a section for each display data management topic you may need to know about if you are interested in S/36 compatibility. Where appropriate, each topic contains the following information:

- How the System/36 supports the function.
More information on the System/36 functions can be found in the following manuals:
 - *System/36 Creating Displays: Screen Design Aid and System Support Program*, SC21-7902
 - *System/36 Concepts and Programmer's Guide*, SC21-9019
- How the default OS/400 display data management supports the function.
- How to get the System/36-compatible function with OS/400 display data management, including which of the three level-of-compatibility items previously listed is required to get the compatible function.

Clearing Lines on the Display

When a System/36 application writes the first record in a job, System/36 work station data management clears the display before displaying the application data. The System/36 function is provided on the AS/400 system for the first write operation in a System/36-environment job if the program is written in a System/36-compatible language or the display file contains the USRDSPMGT keyword. The *Concepts and Programmer's Guide for the System/36 Environment* describes starting and ending a System/36-environment job.

OS/400 display data management normally clears the display when a display file is opened; System/36 work station data management does not. The System/36 function is provided by the OS/400 operating system for programs written in a System/36-compatible language or that open a display file that specifies the USRDSPMGT keyword.

Applications can clear all or just parts of the display by using the clear line (CLRL) keyword. The CLRL keyword is automatically put in the DDS source when the System/36 environment converts the SFGR source to DDS. The value generated for the number of lines to clear is based on the value in columns 19 and 20 of the SFGR S specification.

Because some of the OS/400 and System/36-compatible display-clearing functions are different, the following DDS keywords cannot be used in display files that specify the USRDSPMGT keyword:

- ERASE
- PUTRETAIN
- KEEP
- ASSUME

Also, the OVERLAY keyword is ignored for programs written in a System/36-compatible language and for display files that specify the USRDSPMGT keyword.

Input Data for Display File Records

On the System/36, only one record with input fields can be displayed. For example, if an application on the System/36 writes record REC1 and then record REC2, only the last record written (REC2) has input-capable fields. When REC1 is written, the input fields defined by REC1 are input-capable. When REC2 is written, REC1 fields are then no longer input-capable, and the input fields defined by REC2 are input-capable.

With the default OS/400 display data management support, many different records with input fields can be displayed at the same time. For example, record REC1 (which occupies lines 1 through 12) and record REC2 (which occupies lines 21 through 24) can be displayed at the same time.

The application program can read data from either record. Only the data for the input-capable fields defined by the specific record is returned. In the previous example, if the application program needs to get all the data from all the input-capable fields on the display, the application has to issue two read operations: one for REC1 and one for REC2.

OS/400 display data management allows only one record with input fields for programs written in a System/36-compatible language or for display files that specify the USRDSPMGT keyword.

Input Data from the Work Station Controller

The System/36 work station controller returns the data for all input-capable fields. With the default OS/400 display data management support, the work station controller returns only data from the display for the input-capable fields that the display station operator has changed.

OS/400 display data management provides the System/36 function with the Modified Data Tag (MDT) value of the DSPATR DDS keyword. The DSPATR(MDT) keyword is automatically put in the DDS source for every input-capable field when the System/36 environment converts SFGR source to DDS. This keyword sets on an indicator in the work station controller that makes the work station controller act as if the field with DSPATR(MDT) was changed by the display station operator. Because this keyword is specified for all input-capable fields, all the input data is returned to the system and to the program when the program issues a read operation.

Self-Check

On System/36, if a field specifies modulus 10 or modulus 11 self-checking (column 30 of SFGR D specification), the work station controller verifies that valid data is entered into the field. If a display station operator enters an incorrect modulus 10 or modulus 11 number for a field, the work station controller displays a blinking four-digit error code, and the user must enter data into the field again.

OS/400 display data management support for self-check, which uses the CHECK(M10) and

CHECK(M11) DDS keywords, verifies that the field has a valid modulus 10 or modulus 11 number when you press the Enter key or another function key. This verification is used in place of issuing an error message as you type data into the field. If the CHECK(M10F) or CHECK(M11F) keyword is specified, the workstation controller verifies that valid data is entered into the field as described in the previous paragraph.

If a display file contains the CHECK(M10) or CHECK(M11) DDS keyword and also the USRDSPMGT keyword, OS/400 display data management, like the System/36, issues an error message as you type the data. The DDS keywords CHECK(M10F) and CHECK(M11F) are not allowed with the USRDSPMGT keyword.

Return Input

System/36 work station data management has support to indicate to an application program whether any fields on the display have been changed by the display station operator. To use this support, the SFGR source must specify N for return input (column 22) in the SFGR S specification. If N is specified and the user does not change any fields on the display, all blanks are received as input data for a read operation.

OS/400 display data management provides the System/36 support. If the CHANGE keyword is specified at the record level without a response indicator in a display file that specifies the USRDSPMGT keyword, and the program doing the read operation is written in a System/36-compatible language, the program receives a blank record when the display station operator does not change any data on the display. The CHANGE keyword is automatically put in the DDS source when SFGR source is converted to DDS by the System/36 environment if N is specified for return input.

Erase Input Fields

On System/36, if a program writes a record to the display and the erase-input-fields function (columns 31 and 32 of the SFGR S specification) is enabled for the record, the input fields on the display are erased, but the specified record is not sent to the display. For example, if a program

writes record REC1 to the display and then writes record REC2 to the display (where REC2 has the erase-input-fields function enabled), all the input fields defined by REC1 are erased and REC2 is not sent to the display.

OS/400 display data management follows the System/36 handling of erase-input-fields when the program is written in a System/36-compatible language, the USRDSPMGT keyword is specified, and the ERASEINP keyword is enabled for the record.

On System/36, if a program writes a record to the display and the erase-input-fields and put-override functions are both enabled for the record, the input fields on the display are erased, and the put-override data for the specified record is sent to the display.

OS/400 display data management follows the System/36 handling of erase-input-fields when the program is written in a System/36-compatible language, the USRDSPMGT keyword is specified, and the ERASEINP and PUTOVR keywords are enabled for the record.

Display Attributes

Some fields do not have beginning display attributes on the System/36. A field has a beginning display attribute only if one or more of the following is true:

- The field is input-capable.
- The output data is based on an indicator (column 23-24 of SFGR D specification).
- The field specifies a display attribute (such as high intensity, blink, reverse image, underline, or column separators).
- The field appears on a row that is not cleared by the record.

To provide application compatibility with the System/36, OS/400 display data management follows the System/36 rules to determine if a field should have a beginning attribute when the USRDSPMGT keyword is specified in a display file. Also, if a field does not have a beginning attribute and the OVRATR keyword is specified on the field, the OVRATR keyword is ignored (no field attribute is sent).

On the System/36, some fields do not have ending display attributes. A field has an ending attribute only if one or more of the following is true:

- The field is input-capable.
- The output data is based on an indicator (columns 23-24 of SFGR D specification).
- The field specifies a display attribute (such as high intensity, blink, reverse image, underline, or column separators).

OS/400 display data management follows the System/36 rules to determine if a field should have an ending attribute when the USRDSPMGT keyword is specified in a display file.

Positioning the Cursor

System/36 uses the following rules to determine where the cursor should be positioned when a record is displayed:

1. The cursor is positioned to the first input field (defined by the SFGR source statements) that has an indicator specified for the position-cursor attribute, has this indicator set on, and where one of the following conditions is true:
 - This field does not have the protect attribute specified (columns 37 and 38 of the SFGR D specification).
 - This field has an indicator specified for the protect attribute, but the indicator is off.
 - This field has an unoptioned-protect attribute specified (columns 37 or 38 of the SFGR D specification is Y or N).
2. If the cursor is not positioned by rule 1, a check is made for fields with an unoptioned-position-cursor attribute (columns 32 or 33 of the SFGR D specification is Y). If there is a field with an unoptioned-position-cursor attribute, the cursor is positioned to this field.
3. If the cursor is not positioned by rule 1 or 2, the cursor is positioned to the first input field (as defined by the SFGR source statements) that does not have an unoptioned-protect attribute (columns 37 or 38 of the SFGR D specification are blank).

4. If the cursor is not positioned by any of the previous rules, the cursor is positioned to the upper-left-hand corner of the display.

OS/400 display data management positions the cursor following the System/36 rules for display files that have the USRDSPMGT keyword specified.

Displaying Messages

On System/36, fields can be defined that have message text automatically inserted into the field when a record is displayed. System/36 work station data management retrieves the message text defined for the field and supplies the message text as output data for the field. To display message text, System/36 applications must specify the following:

- M for constant type (column 56 of SFGR D specification).
- The message identification code (MIC) (columns 57 through 60 of SFGR D specification or output data supplied by the program).
- The message member identifier (columns 61 and 62 of SFGR D specification or output data supplied by the program).

OS/400 applications can display messages in a variety of different ways. For information on displaying messages, see “Creating and Displaying Your Own Messages” on page 8-1.

To provide application compatibility with System/36, the MSGID keyword can be used to display messages. The MSGID keyword is automatically generated by the System/36 environment if M is specified for constant type in the SFGR D specification.

Either of the following formats can be used to display messages that follow the System/36 conventions for sending messages:

`MSGID(message-identifier message-file)`

`MSGID(USR message-identification-code message-file)`

Message-identifier consists of two parts: a message prefix and a message-identification-code (MIC). If an application uses the first format of the MSGID keyword, the three-character message

prefix should be the first three characters of the seven-character message-identifier. If an application uses the second format of the MSGID keyword, the prefix does not need to be provided. The prefix is already specified as USR in the MSGID keyword.

The message-identification-code parameter specifies the four-character message ID of the message to be displayed.

For more information on specifying display file message-identifiers, see the *DDS Reference*.

The message-file parameter identifies the message file that contains the message to be displayed. For System/36 compatibility, this parameter can be specified in one of two formats.

The first format for specifying the message-file parameter is in a two-character field-name. The field-name must exist in the same record as the MSGID field, and the field must be defined as a character field with usage H (hidden), P (program-to-system), B (both), or O (output-only). The field identified by field-name indicates the message file that the System/36 environment uses to display a message. The values allowed for the field are:

<i>Table G-1. Message Files for MSGID</i>	
Value of Field-Name	Message File Used
U1	Message text from the message file specified on USER1 parameter on MEMBER OCL statement.
U2	Message help text from the message file specified on USER2 parameter on MEMBER OCL statement.
P1	Message text from the message file specified on PROGRAM1 parameter on MEMBER OCL statement.
P2	Message help text from the message file specified on PROGRAM2 parameter on MEMBER OCL statement.
M1	Message text from IBM-supplied message file ##MSG1.
M2	Message help text from IBM-supplied message file ##MSG1.

The second format for specifying the message-file parameter is a special value. The following special values can be specified for the message file:

<i>Table G-2 (Page 1 of 2). Message Files for MSGID</i>	
Special Value	Message File Used
*USR1	Message text from message file specified on USER1 parameter on MEMBER OCL statement.
*USR2	Message help text from message file specified on USER2 parameter on MEMBER OCL statement.
*PGM1	Message text from message file specified on PROGRAM1 parameter on MEMBER OCL statement.

Table G-2 (Page 2 of 2). Message Files for MSGID

Special Value	Message File Used
*PGM2	Message help text from message file specified on PROGRAM2 parameter on MEMBER OCL statement.
*SYS1	Message text from IBM-supplied message file ##MSG1.
*SYS2	Message help text from IBM-supplied message file ##MSG1.

The following are considerations you should be aware of when using the System/36-compatible functions of the MSGID keyword:

- If a field name or a special value is specified, the processing done by OS/400 display data management depends on the environment where the application runs. For example, if the application is run in the System/36 environment, *USR1 indicates to use the message file identified by the USER1 parameter on the MEMBER OCL statement. If the same application is not run in the System/36 environment, *USR1 indicates to use message file USR1.
- If the message is to be displayed and it only has message help, the message help is displayed.
- If the message help is to be displayed but the message has no message help, only the message is displayed.
- If the message text to be displayed is longer than the length of the output field, the message text is truncated to the length of the output field. If the message text to be displayed is shorter than the length of the output field, the message text is padded with blanks.
- If the message identifier contains any characters that are not valid (valid characters are 0-9 and A-F), the message text displayed is the message identifier followed by the two-character message file identifier.
- If the message identifier or the message file is not found, the message text displayed is the

message identification code followed by two question marks (??).

- The following DDS keywords cannot be specified on a field with the MSGID keyword:

DFT
DFTVAL
FLTFIXDEC
FLTPCN
MSGCON

Put Override

On System/36, if the put-override option is enabled (columns 33 and 34 of SFGR S specification) and the number of lines to clear (columns 19 and 20 of SFGR S specification) is specified, the number of lines to clear is ignored. System/36 work station data management does not clear the display when the put-override option is enabled. OS/400 display data management also has support to ignore the clear function (CLRL keyword) for records that have the put-override option (PUTOVR keyword) enabled. This support is used for programs written in a System/36-compatible language or using a display file that specifies the USRDSPMGT keyword.

On System/36, if the put-override option is enabled, no input-field definitions are sent to the display. Input-field definitions contain information such as length of the input-field, mandatory-fill attribute, mandatory-enter attribute, modified-data-tag attribute, and protected input-field attribute. If there are input fields currently on the display, these fields remain input-capable. The default OS/400 display data management support sends input-field definitions when the put override option is enabled. OS/400 display data management provides the System/36 function of not sending input-field definitions to the display when the put-override function is enabled and the record to be displayed is in a display file that specifies the USRDSPMGT keyword. If the application uses the System/36 function of not sending input-field definitions to the display when the put-override function is enabled, attributes that are defined by the input-field definitions cannot be changed when put-override is enabled. For example, the protected input-field attribute (DSPATR(PR)) is ignored when put-override is enabled, because the input-field definitions are not sent to the display.

On System/36, the put-override option can be specified for records that are currently displayed and for records that are not currently on the display. For example, if record REC1 is currently displayed and the application program issues a write operation with the put-override function enabled for record REC2, the request to display record REC2 is processed as a put-override request. The default support in OS/400 display data management supports the put-override function only for records that are currently displayed. For example, if record REC1 is currently displayed and the application program issues a write operation with the put-override function enabled for record REC2, the put-override function is ignored and the request to display record REC2 is processed as if the PUTOVR keyword was not enabled. If the display file specifies the USRDSPMGT keyword, OS/400 display data management provides the System/36 function of allowing the put-override function even if the record is not currently displayed.

- | During an override operation, OS/400 display data management may ignore help specifications contained in the record format that is displayed by the application program. This occurs if the
- | USRDSPMGT keyword is used. If the Help
- | Cleared (HLPCLR) keyword is also specified on the record format, no online help is available.

Handling Signed Numeric Data

System/36 does no checking when incorrect data (data other than 0 through 9) is specified for a signed numeric field on a write operation. For example, if the data in a signed numeric field is character data, the character data is displayed. The default support in OS/400 display data management is to replace any incorrect signed numeric data with nulls when the field is displayed. OS/400 display data management supports the System/36 function when the USRDSPMGT keyword is specified in the display file.

System/36 also does no checking when a read operation returns incorrect data for a signed numeric field. For example, if the data returned for a signed numeric field is character data, the character data is passed to the application program. The default support in OS/400 display

data management replaces any incorrect signed numeric data with zeros before the data is given to the application program. OS/400 display data management supports the System/36 function for programs written in a System/36-compatible language.

On System/36, if zeros are entered in a signed numeric field and the field-minus key is used to exit the field, a value of negative zero is returned to the application program. The default support in OS/400 display data management returns zeros to the application instead of negative zero. OS/400 display data management supports the System/36 function for programs written in a System/36-compatible language or using a display file that specifies the USRDSPMGT keyword.

Function Keys

On System/36, application programs can receive control when a function key is pressed. To use this support, the application must enable the desired function key in the SFGR source and the program must indicate that it can process the function key.

The default OS/400 display data management support does not allow a program not written in a System/36 compatible language to indicate which function keys the program can process. The function keys that are enabled in the DDS for the display file are the function keys that OS/400 display data management passes to the program to handle.

OS/400 display data management supports the System/36 function of a program indicating which function keys it can process for programs written in a System/36-compatible language. See the appropriate System/36-compatible language manual for information on enabling function-key handling in a program.

Help Key Considerations

The HELP and HLPRTN DDS keywords are used to indicate what processing should be done by the system when the Help key is pressed. The HELP keyword indicates that the application wants the Help key enabled. The HELP keyword is automatically put in the DDS source when SFGR

source is converted to DDS by the System/36 environment.

The HLPRTN keyword indicates that the application program wants to process the Help key when the display station operator presses the Help key. When the Help key is enabled in the SFGR key mask (columns 64 through 79 of the SFGR S specification) the HLPRTN keyword is put in the DDS source when the System/36 environment converts SFGR source to DDS.

If the HELP and HLPRTN keywords are not specified and the display station operator presses the Help key, a message is displayed by OS/400 display data management indicating that the Help key is not allowed.

If the USRDSPMGT and HELP keywords are specified, the HLPRTN keyword is not specified, and the display station operator presses the Help key, OS/400 display data management uses the following rules to determine how the Help key is be processed:

1. If the Help key is pressed when a message is being displayed, the message help for the message is displayed.
2. If the Help key is not processed by rule 1 and there is application help defined for the record, the application help for the record is displayed.
3. If the Help key is not processed by rules 1 or 2, an error message is displayed indicating that the key is not allowed.

If the USRDSPMGT, HELP, and HLPRTN keywords are specified and the display station operator presses the Help key, OS/400 display data management uses the following rules to determine how the Help key is be processed:

1. If the application program has indicated that it can process the Help key, an indication is returned to the application program that the Help key was pressed.
2. If the Help key is not processed by rule 1 and the Help key is pressed when a message is being displayed, the message help for the message is displayed.
3. If the Help key is not processed by rules 1 or 2 and there is application help defined for the

record, the application help for the record is displayed.

4. If the Help key is not processed by rules 1, 2 or 3, an error message is displayed indicating that the key is not allowed.

Using Command Keys to Exit Application Help

On System/36, if application help is displayed and the display station operator presses a command key to exit application help, an indication of what command key was pressed is given to the application program. To use this support, the application must enable the desired command key on the display where the Help key is pressed, and the key must be enabled on the application help display. If the display file containing application help specifies the USRDSPMGT keyword, OS/400 display data management returns the indication of what command key was pressed to exit application help. If the command key was not specified on both the application record and the help record, the message, Function Key not Allowed is displayed.

On System/36, if application help is displayed and the display station operator presses a command key to exit application help, the data from the display where the Help key is pressed is returned to the application program. To use this support, the application must indicate *restore yes* (columns 47 and 48 of the SFGR H specification) on the display where the Help key is pressed. OS/400 display data management returns the data from the display where the Help key is pressed if the display file containing application help specifies the USRDSPMGT keyword.

Cancel-Invite Operation

On System/36, if a program issues a cancel-invite operation and data has already been received by the system (for example, the display station operator pressed the Enter key before the cancel-invite was issued), the data is lost and the application is not notified.

The default OS/400 display data management support causes the cancel-invite operation to fail if the data is available. Message CPF4737 and

return code 0412 are sent to the application program. The application can check the return code and issue a read operation to receive the data that was returned from the display station.

OS/400 display data management supports the System/36 function and does not send message CPF4737 or set the return code for programs written in a System/36-compatible language or for display files that have the USRDSPMGT keyword specified.

Retain Command and Function Keys

On System/36, when a program issues a write operation to display a record, the application can indicate that the command and function keys currently active for the display station should be the command and function keys that are used for the new record. For example, if an application writes record REC1 (where REC1 enables command keys 1 through 12 and all of the function keys), and then the application writes record REC2 (where REC2 keeps the command and function keys from REC1), then command keys 1 through 12 and all of the function keys are enabled when REC2 is displayed. System/36 applications indicate that the command keys should be kept by specifying an R for the enable command keys option in the SFGR source (column 28 of the SFGR S specification). System/36 applications indicate that the function keys should be kept by specifying an R for the enable function keys option in the SFGR source (column 27 of the SFGR S specification).

AS/400 application programs can specify either a list of command and function keys that are valid when a record is displayed or an indication that the command and function keys that are currently active should remain active when a record is displayed.

OS/400 display data management allows an application to keep the current command keys for a record if the RETCMDKEY keyword is specified for the record. The RETCMDKEY keyword is automatically generated by the System/36 environ-

ment if R is specified for command keys in the SFGR S specification.

Also, OS/400 display data management allows an application to keep the current function keys for a record if the RETKEY keyword is specified for the record. The RETKEY keyword is automatically generated by the System/36 environment if R is specified for function keys in the SFGR S specification.

System/36 Functions Not Supported

This section describes the System/36 work station data management functions that are not supported by OS/400 display data management.

If one program issues a write operation that invites the display and another program issues a write operation with the put-override function enabled for the same display, all the write and read operations must use record formats from the same display file. For example, if program A sets up a read-under-format (RUF) request by writing record REC1 from file FILE1, the second program must also use FILE1 for any write operations with the put-override function enabled. If a different display file is used, all the input fields from REC1 are changed to output-only fields when the put-override function is handled by OS/400 display data management.

The put-override function can be used only across different jobs (for example, a single-requester-terminal (SRT) program that gives control to a multiple-requester-terminal (MRT) program) when the application programs are using RUF. If RUF is not in progress and the second job issues a write operation with the put-override function enabled, all the input fields on the display are changed to output-only fields when the put-override function is handled by OS/400 display data management.

On System/36, application help can return the data from input fields on an application help display. This is not supported by OS/400 display data management.

Restricted DDS Keywords/Functions

If the USRDSPMGT keyword is specified in the DDS source, the following DDS functions cannot be used:

- DDS keywords that control clearing the display:
 - ASSUME
 - ERASE
 - KEEP
 - PUTRETAIN
- ERRSFL DDS keyword
- HLPCMDKEY DDS keyword
- Subfile DDS keywords:
 - SFL
 - SFLCTL

Because System/36-compatible languages do not support subfiles, subfiles cannot be used in a display file if USRDSPMGT is specified.

- Response indicators

Because System/36-compatible languages do not return indicators from the read operation to a display file, response indicators should not be specified if USRDSPMGT is used.

- IGC conversion

Because only one input-capable format is maintained on the screen at one time, IGC conversion is not supported on the System/36 or on the AS/400 in the System/36 environment. The IGCCNV keyword is not allowed anywhere in the file definition when you use the USRDSPMGT keyword.

- DDS keywords:

- CHECK(M10F)
- CHECK(M11F)

Because specifying the DDS keywords CHECK(M10) and CHECK(M11) with USRDSPMGT provide the same function as CHECK(M10F) and CHECK(M11F) without USRDSPMGT.

Bibliography

The following list of manuals and guides are related to this guide. The manuals are listed with their full title, base order number, a shortened version of the title, and a description of the content. The description of each manual includes the relationship of that manual to this guide.

- *Application Development by Example*, SC41-9852. **Short title:** *Application Development by Example*

This manual provides application programmers with information needed to understand the relationships of some of the various programming tools and utilities on the AS/400 system that can be used to produce an application.

Use this publication to better understand the tools and utilities available for creating your DDS and CL and other code. This manual also contains instructions about using QUSRTOOL for sample source.

- *Security Reference*, SC41-8083. **Short title:** *Security Reference*

This manual provides information about system security concepts, planning for security, and setting up security on your system.

Use this manual to learn how to specify authority for your display files.

- *System Concepts*, GC41-9802. **Short title:** *System Concepts*

This manual explains object management, data management, work management, integrated database, communications, programming environment, security, and other general programming concepts as they relate to the AS/400 system functions and utilities.

Use this manual to gain a general understanding of the system functions available for developing applications that use displays.

The following guides and references provide reference information:

- *Application Development Tools: Character Generator Utility User's Guide*, SC09-1170. **Short title:** *CGU User's Guide*

This guide provides information about using the Application Development Tools character generator utility (CGU) to create and maintain a double-byte character set (DBCS) on the AS/400 system.

Use this guide to add user-defined characters to DBCS font tables.

- *Application Development Tools: Programming Development Manager User's Guide and*

Reference, SC09-1339. **Short title:** *PDM User's Guide and Reference*

This guide and reference provides information about using the Application Development Tools programming development manager (PDM) to work with lists of libraries, objects, members, and user-defined options to easily do such operations as copy, delete, and rename.

Use this guide and reference to learn how to enter DDS and UIM source.

- *Application Development Tools: Screen Design Aid User's Guide and Reference*, SC09-1340. **Short title:** *SDA User's Guide and Reference*

This guide and reference provides information about using the Application Development Tools screen design aid (SDA) to design, create, and maintain displays, menus, and online help information.

Use this guide and reference if you want to let the system create the DDS as you design your own displays.

- *Application Development Tools: Source Entry Utility User's Guide and Reference*, SC09-1338. **Short title:** *SEU User's Guide and Reference*

This guide provides the application programmer or programmer with information about using the Application Development Tools source entry utility (SEU) to create and edit source members. This manual explains how to start and end an SEU session and how to use the many features of this full-screen text editor.

Use this guide to understand the functions of SEU that are available for creating and editing your DDS and CL and other code.

- *Common User Access Basic Interface Design Guide*, SC26-4583.

This guide assists you in designing a user interface that is consistent within your application and across other applications. This guide presents the user interface style guidelines and implementation considerations that you, the designer and/or developer, must be concerned with.

- *Communications: Intersystem Communications Function Programmer's Guide*, SC41-9590. **Short title:** *ICF Programmer's Guide*

This guide provides the information needed to write application programs that use AS/400 communications and the OS/400 intersystem communications function (OS/400-ICF). This manual also contains information on data description specifications (DDS)

keywords, system-supplied formats, return codes, file transfer support, and program examples.

Use this guide to work with applications on remote systems.

- *Data Description Specifications Reference*, SC41-9620. **Short title:** *DDS Reference*

This reference provides detailed descriptions of the entries and keywords needed to describe database files (both logical and physical) and certain device files (for displays, printers, and ICF) external to the user's programs.

Use this reference to get detailed information about specific DDS keywords used in display files.

- *IBM 5250 Information Display System Functions Reference Manual*, SA21-9247.

This reference manual provides information about using the functions of the 5250 Information Display.

Use this manual to use the 5250 Display Data Stream.

- *Office Services Concepts and Programmer's Guide*, SC41-9758. **Short title:** *Office Services Concepts and Programmer's Guide*

This guide provides information about writing applications that use OfficeVision/400 functions.

Use this guide to develop office documents, which can be used as online help information.

- *Programming: Concepts and Programmer's Guide for the System/36 Environment*, SC41-9663. **Short title:** *Concepts and Programmer's Guide for the System/36 Environment*

This guide provides information identifying the differences in the applications process in the System/36 environment on the AS/400 system. It helps the user understand the functional and operational differences (from a System/36 perspective) when processing in the System/36 environment on the AS/400 system. This includes an environment functional overview, considerations for migration, programming, communications, security, and coexistence.

- *Programming: Control Language Programmer's Guide*, SC41-8077. **Short title:** *CL Programmer's Guide*

This guide provides a wide-ranging discussion of AS/400 programming topics, including control language (CL) programming, controlling flow and communicating between programs, working with objects in CL programs, and creating CL programs. Other topics include predefined and impromptu messages and message handling, defining and creating user-defined commands and menus, and application testing, including debug mode, breakpoints, traces, and display functions.

Use this guide to understand how to use CL for creating application programs.

- *Programming: Control Language Reference*, SC41-0030. **Short title:** *CL Reference*

This guide provides a description of the AS/400 control language (CL) and its OS/400 commands. (Non-OS/400 commands are described in the respective licensed program publications.) It also provides an overview of *all* the CL commands for the AS/400 system, and it describes the syntax rules needed to code them.

- *Programming: Extended Program Model User's Guide and Reference*, SC09-1294. **Short title:** *Extended Program Model User's Guide and Reference*

With this user's guide and reference, you can use the EPM Control Language commands and application library routines, define an EPM run-time environment, start and end an EPM environment, and debug an EPM program.

- *System Programmer's Interface Reference*, SC41-8223. **Short title:** *System Programmer's Interface Reference*

This reference provides information about using application programming interfaces (APIs) from high-level language programs to list data or retrieve descriptions and information more rapidly than using other interfaces.

Use this guide to find out more information about the APIs.

The following guides give information about other device files:

- *Data Management Guide*, SC41-9658. **Short title:** *Data Management Guide*

This guide provides information about using files in application programs. This guide includes information on fundamental structure and concepts of data management support on the system. It also includes information on overrides and file redirection (temporarily making changes to files when an application program is run), copying files by using system commands to copy data from one place to another, and tailoring a system using double-byte data.

Use this guide for general information about using files in application programs.

- *Guide to Programming for Printing*, SC41-8194. **Short title:** *Guide to Programming for Printing*

This guide provides information on how to control and understand printing, including printer connectivity, PC attached printers, and advanced function printing (AFP*) printers.

Use this guide to understand printer device files.

- *Guide to Programming for Tape and Diskette*, SC41-0012. **Short title:** *Guide to Programming for Tape and Diskette*

This guide provides information about data management support for tapes and diskette.

Use this guide to understand tape and diskette device files.

The following guides give information about the System/36:

- *System/36 Concepts and Programmer's Guide*, SC21-9019. **Short title:** *S/36 Concepts and Programmer's Guide*.

This guide tells the application programmer how the System/36 works, how to design and develop carefully planned applications that make best use of system resources and features, and how to design and develop application components.

Using this guide, a programmer can begin to understand what the system components are, how the system works, and how to design and develop application components. Actual coding will require the use of other manuals in the System/36 library.

- *System/36 Creating Displays: Screen Design Aid and System Support Program*, SC21-7902. **Short title:** *S/36 Creating Displays*

This guide describes how to use the Screen Design Aid (SDA) or the System Support Program (SSP) to create and maintain menus and display formats. This manual also describes how to do the following:

- Use SDA to create RPG II WORKSTN file specifications and WSU programs.
- Create and maintain source and procedure members using Source Edit Utility (SEU) through SDA.
- View, print, and compile display formats.

Index

Special Characters

- *DSPATR (display attribute) parameter 6-20
- *FLD (field) special value 6-30
- *JOBCCSID special value 13-2
- *MENU (menu) OS/400 object type 9-1
- *PGM (program) OS/400 object type
 - defining *PGM menu 9-11
 - menu object defining 9-11

Numerics

- 5250 display data stream
 - See user-defined data stream (UDDS)
- 5250 display station
 - avoiding record format problems 3-45
 - UNLOCK results 3-35
- 5250 engraved key restriction 17-12

A

- accelerator key
 - defining 6-16
 - definition 6-16
 - example 6-17
- acquire operation
 - C/400 function for 3-49
 - COBOL/400 statement for 3-49
 - definition 3-2
 - file resource allocation for 3-1
 - RPG/400 operation for 3-49
- acquired display station
 - additional, for I/O operations 3-2
 - releasing from I/O operations 3-49
- action list definition 17-9
- action list option prompting B-13
- action variable definition 17-9, 17-11
- ACTIONS (Menu Bar Cursor Action) dialog
 - command B-4
- active record format
 - determining 3-5
 - table 3-5
- active subfile record
 - definition 4-3
- Add Message Description (ADDMSGD)
 - command 9-9
- Add Search Index Entry (ADDSCHIDX)
 - command 20-16
- adding
 - pop-up window over another panel 17-28
 - pop-up windows using APIs 17-27
 - window over another panel 17-28
 - window to display stack 17-28

- ADDMSGD (Add Message Description)
 - command 9-9
- ADDSCHIDX (Add Search Index Entry)
 - command 20-16
- alarm
 - sounding for messages 8-7
- ALCOBJ (Allocate Object) command 3-1
- Allocate Object (ALCOBJ) command 3-1
- Allow Roll (ALWROL) keyword
 - effects on rolling 3-16
 - use 3-16
- alphabetic conversion
 - name syntax A-4
- alphanumeric application
 - converting to DBCS D-7
- alphanumeric device
 - displaying double-byte data D-7
- alternative character sets and code pages 13-1
- Alternative Data Type (IGCALTTYP) keyword D-5
- alternative keywords, specifying
 - Help (HELP) 2-13
 - Page Down (PAGEDOWN) 2-13
 - Page Up (PAGEUP) 2-13
- ALTHELP (Alternative Help) keyword 2-13
- ALTPAGEDWN (Alternative Page Down)
 - keyword 2-13
- ALTPAGEUP (Alternative Page Up) keyword 2-13
- ALWROL (Allow Roll) keyword
 - effects on rolling 3-16
 - use 3-16
- ampersand (&) symbol A-5
- analyzing
 - system error messages 8-8
- API (application programming interface)
 - adding and removing windows 17-27
 - services 16-5
- APPFMT (application formatted area) tag
 - application formatted data A-8
 - example
 - an application formatted area A-9
 - overview A-8
- application
 - help 6-29
 - interaction with menu bar 6-22
- application control of panel formatting 17-20
- application display
 - changing record formats on a 3-8
 - creating a sample 1-1
 - DBCS conversion dictionary D-19
 - defining in display file 2-1
 - determining active record formats 3-5
 - entry
 - See entry display

application display *(continued)*

- erasing unprotected input and output/input fields on 3-23
- field, defining in a record format 2-7
- functions, defining in record format 2-7
- how the system reads input from 3-40
- improving system performance 14-1
- information
 - See information display
- inviting input to 3-30
- keeping record or field on 3-23
- list 21-20
- order of record formats written to 3-9
- overlying and erasing record formats on 3-10
- placing records on 3-5
- printing 2-21
- reading input from 3-33
- reading invited input from 3-31
- rolling data between two lines 3-16
- single-choice menu
 - See menu display
- understanding which records do not occupy space 3-8
- viewing record format 2-8
- writing output to 3-5

application formatted area (APPFMT) tag

- application formatted data A-8
- example
 - an application formatted area A-9
- overview A-8

application formatted data

- selection characters A-9

application handle definition 17-1**application help**

- See also online help information
- caution for multiple display stations 18-1
- definition 18-1
- exiting, System/36 application compatibility G-8

application pop-up window

- defining 17-27

application program

- applying overrides when compiling 7-4
- converting alphanumeric applications to DBCS applications D-7
- DBCS considerations D-7
- describing data inside or outside 2-3
- display files, use with 3-1
- double-byte data, for D-7
- file resource allocation for on remote system 3-1
- opening 17-1
- overriding
 - display file attributes in HLL 7-1
 - display file names and attributes in HLL 7-3
 - display file names in HLL 7-3
- passing display data 11-1
- processing double-byte data D-7

application program *(continued)*

- record format used by 2-8

application programming

- confirmation processing 16-32
- data presentation panel 16-47
- list panel 16-26
- menu bar panel 16-64

application programming interface (API)

- adding and removing windows 17-27
- services 16-5

application record

- MNUBARDSP 6-41

application window

- defining 17-27

area

- on a panel A-2

assignments, common key

- See common key assignments

ASSUME (Assume) keyword

- considerations 11-1
- example DDS source 11-1, 11-3
- OVERLAY keyword, used with 11-2
- restriction with USRDSPMGT keyword G-10
- sharing file between programs 11-1
- System/36 application compatibility G-2

attribute

- continued
 - example A-1
- display 6-20
- display stations 3-4
- entry fields 6-37
- field
 - color 2-18
 - emphasizing 2-17
 - System/36 application compatibility G-3
- modified data tag 2-10
- overriding 3-18
- UIM-defined variable A-160
- z-variable A-160

attribute character 2-8**attribute interaction table A-91****automatic confirmation processing 16-31****availability of choices**

- controlling 6-11

B**backward field-exit processing 6-36****BASETYPE**

- summary table A-16
- values A-14

basic character D-4**BASIC statement**

- I/O requests for subfiles 4-12
- mapping to I/O operations 3-49

- beginning attribute character**
 - definition 2-8
- bibliography** H-1
- bidirectional considerations**
 - formatting A-78
- binary return codes for program menus** 9-10
- binary value**
 - display form A-22, A-23
 - formatting A-22
- blank**
 - how to convert alphanumeric to DBCS D-25
- blank lines for separating** 17-33
- border of window** 5-7
- BOTINST (bottom instruction) tag**
 - overview A-10
- bottom instruction (BOTINST) tag**
 - overview A-10
- built-in function**
 - CHKOBJ (check object) A-26, A-77
 - CHKUSRCLS (check user class) A-26, A-78

C

- C/400 functions**
 - I/O requests for subfiles 4-12
 - mapping to I/O operations 3-49
- CALL (Call Program) dialog command** B-4
- Call Program (CALL) dialog command** B-4
- CANCEL dialog command** B-6
- cancel key**
 - defining 6-18
 - definition 6-18
 - menu panel 9-2
- cancel read operation, CL command for** 3-49
- cancel-invite operation**
 - C/400 function for 3-49
 - CL command for 3-49
 - COBOL/400 statement for 3-49
 - RPG/400 operation for 3-49
 - System/36 application compatibility G-8
 - when to use 3-41
- CAnn (command attention) key**
 - defining 2-12
 - returning to program from online help
 - information 18-20
 - system performance considerations 14-3
 - validity considerations 3-45
- CAnn (Command Attention) keyword**
 - for keyboard control 2-11
- CFnn (command function) key**
 - CHCACCEL keyword 6-16
 - defining 2-12
 - returning to program from online help
 - information 18-20
 - system performance considerations 14-3
 - validity considerations 3-45

- CFnn (Command Function) keyword** 2-11, 2-12
- CGU (character generator utility)**
 - DBCS sort table
 - copying from data file D-13
 - copying to data file D-12
 - Japanese DBCS master sort table
 - copying from data file D-13
 - copying to data file D-12
- CHANGE (Change) keyword** 3-36
- Change Command Default (CHGCMDDFT)**
 - command 9-16
- Change Device Description (Display) (CHGDEVDSPP)**
 - command 2-22
- Change Display File (CHGDSPF) command**
 - Change Display File (CHGDSPF)
 - changing file description 2-2
 - changing
 - display files 2-5
 - file description 2-2
 - DFRWRT (defer write) parameter
 - creating display file 3-26
 - described 14-1
 - ENHDSP (enhance display) parameter 6-3
 - indicating DBCS files D-5
 - running 2-5
 - SHARE parameter 14-2
- Change Job (CHGJOB) command** 8-7
- Change Library List (CHGLIBL) command** D-8
- Change Menu (CHGMNU) command** 9-16
- Change Printer File (CHGPRTF) command** D-5
- Change View (CHGVVIEW) dialog command** B-6
- changing**
 - DBCS conversion dictionaries
 - See editing DBCS conversion dictionaries
 - display file 2-5
 - file description 2-2
 - file descriptions 2-5
 - window 5-9
- character**
 - basic D-4
 - double-byte
 - size D-4
 - system processing of D-4
 - extended D-4
 - selection 6-15, A-9
 - sentence-ending A-2
 - shift-control
 - See shift-control characters
 - symmetric
 - Arabic A-21
 - Hebrew A-21
- character beginning attribute** 2-8
- character ending attribute** 2-8
- character field attribute** 2-8
- character generator utility (CGU)**
 - DBCS sort table
 - copying from data file D-13

- character generator utility (CGU)** *(continued)*
 - DBCS sort table *(continued)*
 - copying to data file D-12
 - Japanese DBCS master sort table
 - copying from data file D-13
 - copying to data file D-12
- Character Identifier (CHRID) keyword**
 - description 13-2
 - example 13-2
- character set and code page**
 - considerations when printing 17-5
 - conversion, DDS 13-1
 - conversion, UIM A-18
- character translation**
 - using 13-2
- character value**
 - display form A-23
- CHECK (Check) keyword**
 - parameters for cursor movement 2-16
 - RL and RLTB parameters 2-16
- CHECK (validity checking) tag**
 - example, validity checking A-12
 - overview A-11
- check box**
 - definition 6-1
 - example 6-1
- CHECK(FE) (Field Exit) keyword 6-13**
- CHGCMDDFT (Change Command Default)**
 - command 9-16
- CHGDEVDS (Change Device Description (Display))**
 - command 2-22
- CHGDSPF (Change Display File) command**
 - changing
 - display files 2-5
 - file description 2-2
 - DFRWRT (defer write) parameter
 - described 3-26
 - when creating display file 3-26
 - DFRWRT parameter 14-1
 - ENHDSP (enhance display) parameter 6-3
 - indicating DBCS files D-5
 - running 2-5
 - SHARE parameter 14-2
- CHGJOB (Change Job) command 8-7**
- CHGLIBL (Change Library List) command D-8**
- CHGMNU (Change Menu) command 9-16**
- CHGPRTF (Change Printer File) command D-5**
- CHGVVIEW (Change View) dialog command B-6**
- CHKOBJ (Check Object) function A-26, A-77**
- CHKUSRCLS (Check User Class) function A-26, A-78**
- choice entry field, Common User Access 21-50**
- choice-level help 6-29**
- CHRID (Character Identifier) keyword**
 - description 13-2
 - example 13-2

- CHRID (Character Identifier) parameter**
 - specifying 13-3
 - values, table of 13-5
- CIT (title citation) tag**
 - example, title citations A-13
 - overview A-13
 - use in help module 20-4
- CL (control language) program**
 - examples
 - program menu 9-12
 - RTNPNT(*NO) for program menu 9-14
 - I/O operations using 3-49
 - inviting input from 3-30
 - reading-from-invited-devices from 3-33
- CLASS (class definition) tag**
 - BASETYPE summary table A-16
 - decision tree for orientation A-20
 - display forms
 - character value A-23
 - date value A-23
 - numeric values A-22
 - time value A-23
 - example
 - class definitions A-22
 - numeric values table A-22
 - overview A-14
 - tags allowed table A-14
- class definition (CLASS) tag**
 - BASETYPE summary table A-16
 - decision tree for orientation A-20
 - display forms
 - character value A-23
 - date value A-23
 - numeric values A-22
 - time value A-23
 - example
 - class definitions A-22
 - example numeric values table A-22
 - overview A-14
 - tags allowed table A-14
- CLEAR (Clear) keyword 2-11**
- Clear Lines (CLRL) keyword**
 - example
 - differences between OVERLAY and 3-15
 - with (*NO) value 3-14
 - S/36 environment considerations G-1
 - system performance considerations 14-2
 - when to use 3-13
- clearing**
 - environment considerations G-1
 - lines on display
 - S/36 environment considerations G-1
 - using the CLRL keyword 3-13
- close operation**
 - BASIC statement for 3-49
 - C/400 function for 3-49

close operation *(continued)*

CL command for 3-49
COBOL/400 statement for 3-49
definition 3-49
files shared in job 3-52
FORTRAN/400 statement 3-49
RPG/400 operation for 3-49

CLRL (Clear Lines) keyword

example
 differences between OVERLAY and 3-15
 with (*NO) value 3-14
S/36 environment considerations G-1
system performance considerations 14-2
use 3-13

CMD (System Command) dialog command B-7**CMDLINE (Command Line) dialog command B-7****CMDLINE (command line) tag**

overview A-24

COBOL/400 statement

I/O requests for subfiles 4-12
mapping to I/O operations 3-49

code page

alternative display 13-1
conversion, UIM A-18
page 420 A-19
page 424 A-19
part of CHRID keyword for display files 13-2

code page and character set considerations when printing 17-5**codes, major/minor return**

See major/minor return code

colon (:) symbol A-5**COLOR (Color) keyword 2-18****color attribute**

available choice 6-20
default 6-20
selected choice 6-20
unavailable choice 6-20

color, adding to displays 2-18**column data**

formatting A-97

column heading

list display 21-22

command attention (CAnn) key

defining 2-12
returning to program from online help
 information 18-20
system performance considerations 14-3
validity considerations 3-45

Command Attention (CAnn) keyword

for keyboard control 2-11

command function (CFnn) key

defining 2-12
returning to program from online help
 information 18-20
system performance considerations 14-3

command function (CFnn) key *(continued)*

validity considerations 3-45

Command Function (CFnn) keyword 2-12**command key**

See command attention (CAnn) key

See command function (CFnn) key

command line

entered too long 17-17
interpretation 17-16
optional 21-32
pop-up window 17-29
restrictions 17-16
tools 21-35
window 17-29
window example 17-29

Command Line (CMDLINE) dialog command B-7**command line (CMDLINE) tag**

overview A-24

command prompting B-13**command, CL**

Add Message Description (ADDMSGD) 9-9
Add Search Index Entry (ADDSCHIDX) 20-16
ADDMSGD (Add Message Description) 9-9
ADDSCHIDX (Add Search Index Entry) 20-16
ALCOBJ (Allocate Object) 3-1
Allocate Object (ALCOBJ) 3-1
canceling read operation with 3-49
Change Command Default (CHGCMDDFT) 9-16
Change Device Description (CHGDEVDS) 2-22
Change Display File (CHGDSPF)
 changing file description 2-5
 indicating DBCS files D-5
 running 2-5
 SHARE parameter 14-2
Change Job (CHGJOB) 8-7
Change Library List (CHGLIBL) D-8
Change Menu (CHGMNU) 9-16
Change Printer File (CHGPRTF) D-5
CHGCMDDFT (Change Command Default) 9-16
CHGDEVDS (Change Device Description) 2-22
CHGDSPF (Change Display File)
 changing file description 2-5
 DFRWRT parameter 14-1
 indicating DBCS files D-5
 SHARE parameter 14-2
CHGJOB (Change Job) 8-7
CHGLIBL (Change Library List) D-8
CHGMNU (Change Menu) 9-16
CHGPRTF (Change Printer File) D-5
Copy DBCS Font Table (CPYIGCTBL) D-9
Copy DBCS Sort Table (CPYIGCSRT)
 copying DBCS master sort table from data
 file D-13
 copying DBCS master sort table to data
 file D-12
CPYIGCSRT (Copy DBCS Sort Table)
 copying DBCS master sort table from data
 file D-13

command, CL (continued)

CPYIGCSRT (Copy DBCS Sort Table) *(continued)*
 copying DBCS master sort table to data
 file D-12

CPYIGCTBL (Copy DBCS Font Table) D-9

Create Command (CRTCMD) 20-15

Create Control Language Program (CRTCLPGM)
 program menus 9-12

Create DBCS Conversion Dictionary
 (CRTIGCDCT) D-15

Create Display File (CRTDSPF)
 building display with 1-5
 creating display files 2-4
 DFRWRT parameter 14-1
 display file menus 9-9
 indicating DBCS files D-5
 program menus 9-12
 SHARE parameter 14-2

Create Document (CRTDOC) 20-17

Create Duplicate Object (CRTDUPOBJ)
 DBCS conversion dictionary D-15
 use 9-16

Create Edit Description (CRTEDTD) 2-19

Create Menu (CRTMNU)
 display file menus 9-9
 program menus 9-13

Create Message File (CRTMSGF) 9-9

Create Panel Group (CRTPNLGRP)
 building display with 1-5
 use 20-14

Create Printer File (CRTPRTF) D-5

Create Search Index (CRTSCHIDX) 20-15

Create Table (CRTTBL) 13-4
 creating your own 20-15

CRTCLPGM (Create Control Language Program)
 program menus 9-12

CRTCMD (Create Command) 20-15

CRTDOC (Create Document) 20-17

CRTDSPF (Create Display File)
 building display with 1-5
 creating display files 2-4
 DFRWRT (defer write) parameter 14-1
 display file menus 9-9
 indicating DBCS files D-5
 program menus 9-12
 SHARE parameter 14-2

CRTDUPOBJ (Create Duplicate Object)
 saving and restoring DBCS dictionaries D-15
 use 9-16

CRTEDTD (Create Edit Description) 2-19

CRTIGCDCT (Create DBCS Conversion
 Dictionary) D-15

CRTMNU (Create Menu)
 display file menus 9-9
 program menus 9-13

CRTMSGF (Create Message File) 9-9

command, CL (continued)

CRTPNLGRP (Create Panel Group)
 building display with 1-5
 use 20-14

CRTPRTF (Create Printer File) D-5

CRTSCHIDX (Create Search Index) 20-15

CRTTBL (Create Table) 13-4

Delete DBCS Conversion Dictionary
 (DLTIGCDCT) D-19

Delete DBCS Font Table (DLTIGCTBL) D-10

Delete DBCS Sort Table (DLTIGCSRT) D-14

Delete Menu (DLTMNU) 9-17

Delete Override (DLTOVR) 7-5

Delete Panel Group (DLTPNLGRP) 20-14

Delete Search Index (DLTSCHIDX) 20-16

Display DBCS Conversion Dictionary
 (DSPIGCDCT) D-19

Display Edit Description (DSPEDTD) 2-19

Display File Description (DSPFD) 2-7

Display File Field Description (DSPFFD) 2-7

Display Help Document (DSPHLPDOC) 20-18

Display Menu Attributes (DSPMNUA) 9-16

Display Override (DSPOVR) 7-6

Display Program References (DSPPGMREF) 2-7

DLTIGCDCT (Delete DBCS Conversion
 Dictionary) D-19

DLTIGCSRT (Delete DBCS Sort Table) D-14

DLTIGCTBL (Delete DBCS Font Table) D-10

DLTMNU (Delete Menu) 9-17

DLTOVR (Delete Override) 7-5

DLTPNLGRP (Delete Panel Group) 20-14

DLTSCHIDX (Delete Search Index Entry) 20-16

DSPEDTD (Display Edit Description) 2-19

DSPFD (Display File Description) 2-7

DSPFFD (Display File Field Description) 2-7

DSPHLPDOC (Display Help Document) 20-18

DSPIGCDCT (Display DBCS Conversion
 Dictionary) D-19

DSPMNUA (Display Menu Attributes) 9-16

DSPOVR (Display Override) 7-6

DSPPGMREF (Display Program References) 2-7

Edit DBCS Conversion Dictionary
 (EDTIGCDCT) D-16

EDTIGCDCT (Edit DBCS Conversion
 Dictionary) D-16

End Receive (ENDRCV) 3-31

ENDRCV (End Receive) 3-31

GO (Go to Menu)
 generic menu specification 9-16
 use 9-1

Go to Menu (GO)
 generic menu specification 9-16
 use 9-1

help for, assigning 20-15

Initialize Diskette (INZDKT) D-9

INZDKT (Initialize Diskette) D-9

command, CL *(continued)*

Move Object (MOV OBJ) D-15
 MOV OBJ (Move Object) D-15
 OVERLAY (Overlay) keyword
 effect on help-list updating 18-16
 Override with Display File (OVRDSPF)
 compared to CHGDSPF 2-2
 file attributes 7-1
 file names 7-3
 file names and attributes 7-3
 indicating DBCS files D-5
 Override with Printer File (OVRPRTF) D-5
 overrides
 commands that restrict 7-9
 improving performance for 14-2
 OVRDSPF (Override with Display File)
 compared to CHGDSPF 2-2
 file attributes 7-1
 file names 7-3
 file names and attributes 7-3
 indicating DBCS files D-5
 OVRPRTF (Override with Printer File) D-5
 Remove Search Index Entry (RMV SCHIDX E) 20-16
 Rename Object (RNMOBJ) D-15
 Restore Library (RSTLIB) D-15
 Restore Object (RSTOBJ)
 DBCS conversion dictionary D-15
 DBCS sort table D-12
 RMV SCHIDX E (Remove Search Index Entry) 20-16
 RNMOBJ (Rename Object) D-15
 RSTLIB (Restore Library) D-15
 RSTOBJ (Restore Object)
 DBCS conversion dictionary D-15
 DBCS sort table D-12
 RVKOBJAUT (Revoke Object Authority) D-15
 SAVCHGOBJ (Save Changed Object) D-15
 Save Changed Object (SAVCHGOBJ) D-15
 Save Library (SAVLIB) D-15
 Save Object (SAVOBJ)
 DBCS conversion dictionaries D-15
 DBCS sort table D-12
 Save System (SAVSYS)
 DBCS conversion dictionary D-15
 saving DBCS sort tables D-12
 SAVLIB (Save Library) D-15
 SAVOBJ (Save Object)
 DBCS conversion dictionaries D-15
 DBCS sort table D-12
 SAVSYS (Save System)
 DBCS conversion dictionaries D-15
 saving DBCS sort tables D-12
 Start Character Generator Utility (STRCGU) D-10
 Start Programming Development Manager
 (STRPDM) 1-1
 Start Source Entry Utility (STRSEU) 2-7
 STRCGU (Start Character Generator Utility) D-10

command, CL *(continued)*

STRPDM (Start Programming Development
 Manager) 1-1
 STRSEU (Start Source Entry Utility) 2-7
 Vary Configuration (VRYCFG) D-10
 VRYCFG (Vary Configuration) D-10
commands that are too long 17-17
comment A-6
common feedback area
 definition 3-3
common key assignments 21-36
Common User Access (CUA)
 choice entry field 21-50
 description 21-47
 entry dialog actions, table of 21-48
 entry display 21-50
 entry fields 21-51
 function key area 21-49
 information displays 21-52
 list display, example 21-52
 menu display, single-choice 21-49
 message line relationship 21-49
 relationship to AS/400 system 21-1
 selection choices 21-50
 single selection field operation, guidelines 21-50
compact definition list
 example A-56
concatenation symbol A-5
COND (condition definition) tag
 CHKOBJ (Check Object) built-in function A-26
 CHKUSRCLS (Check User Class) built-in
 function A-26
 example, conditioning option A-27
 overview A-25
condition definition (COND) tag
 CHKOBJ (Check Object) built-in function A-26
 CHKUSRCLS (Check User Class) built-in
 function A-26
 example, conditioning option A-27
 overview A-25
condition name, screen size 2-20
conditional expression A-25, A-77
conditional operator A-25
conditioning
 option
 example A-27
confirmation list panel, creating 16-27
confirmation panel source 16-28
confirmation processing
 application programming 16-32
 automatically 16-31
constant field
 definition 2-10
 inserting text from message description 2-15
 using 2-10

- content separator** A-1
- contextual help**
 - defining in UIM 17-14
 - defining on display 18-3
 - definition 19-2
- continued attribute**
 - example A-1
- continued-entry field**
 - backward field-exit processing 6-36
 - creating 6-33
 - example 6-34
 - forward field-exit processing 6-36
 - keyboard function 6-34
- control character, shift**
 - description of D-3
 - inserting D-6
- control language (CL) program**
 - examples
 - program menu 9-12
 - RTNPNT(*NO) for program menu 9-14
 - I/O operations using 3-49
 - inviting input from 3-30
 - reading-from-invited-devices from 3-33
- control value** 6-12
- controller, display station** G-2
- controlling**
 - availability of choices 6-11
 - list entries on list display 17-8
- convention**
 - recommended
 - list action (LISTACT) tag A-92
 - pull-down field choice (PDFLDC) tag A-133
 - required
 - list action (LISTACT) tag A-92
 - pull-down field choice (PDFLDC) tag A-133
- conversion**
 - alphabetic A-4
 - character set and code page, DDS 13-1
 - character set and code page, UIM A-18
- conversion, DBCS**
 - alphanumeric applications to DBCS
 - applications D-7
 - alphanumeric blanks to DBCS blanks D-25
 - changing DBCS conversion dictionaries used D-20
 - deleting unwanted DBCS words D-25
 - description D-19
 - entering double-byte data D-21
 - function D-20
 - many alphanumeric entries at one time D-24
 - one alphanumeric entry to double-byte entry D-22
 - performing (including example operations) D-21
 - use while editing DBCS conversion dictionary D-25
 - where you can use D-20
- Copy DBCS Font Table (CPYIGCTBL) command**
 - copying from tape or diskette D-9
 - copying onto tape or diskette D-9

- Copy DBCS Sort Table (CPYIGCSRT) command**
 - copying DBCS master sort table from data file D-13
 - copying DBCS master sort table to data file D-12
- copying**
 - DBCS files
 - from tape or diskette D-9
 - onto tape or diskette D-9
 - DBCS font table
 - copying from tape or diskette (restoring) D-9
 - copying onto diskette (saving) D-9
 - DBCS sort table
 - copying from file (move from System/36) D-13
 - copying to file (move to System/36 or AS/Entry) D-12
- COPYR (copyright) tag**
 - overview A-28
- copyright (COPYR) tag**
 - overview A-28
- country-designated selection character** 17-11
- CPA8424 inquiry message** D-10
- CPF4001-40FF message** 8-10
- CPF4101-43FF message** 8-10
- CPF4401-44FF message** 8-10
- CPF4501-46FF message** 8-10
- CPF4701-48FF message** 8-10
- CPF4901-49FF message** 8-10
- CPF5001-50FF message** 8-10
- CPF5101-53FF message** 8-10
- CPF5501-56FF message** 8-10
- CPYIGCSRT (Copy DBCS Sort Table) command**
 - copying DBCS master sort table from data file D-13
 - copying DBCS master sort table to data file D-12
- CPYIGCTBL (Copy DBCS Font Table) command**
 - copying from tape or diskette D-9
 - copying onto tape or diskette D-9
- Create Command (CRTCMD) command** 20-15
- Create Control Language Program (CRTCLPGM) command** 9-12
- Create DBCS Conversion Dictionary (CRTIGCDCT) command** D-15
- Create Display File (CRTDSPF) command**
 - building display with 1-5
 - creating display files 2-4
 - DFRWRT (defer write) parameter
 - improving performance with 14-1
 - write operation 3-26
 - display file menus 9-9
 - ENHDSP (enhance display) parameter 6-3
 - indicating DBCS files D-5
 - program menus 9-12
 - SHARE parameter 14-2
- Create Document (CRTDOC) command** 20-17
- Create Duplicate Object (CRTDUPOBJ) command**
 - DBCS conversion dictionaries D-15
 - use 9-16

Create Edit Description (CRTEDTD) command

example F-5
running 2-19
use F-5

Create Menu (CRTMNU) command

display file menus 9-9
program menus 9-13

Create Message File (CRTMSGF) command 9-9**Create Panel Group (CRTPNLGRP) command**

building display with 1-5
use 20-14

Create Printer File (CRTPRTF) command D-5**Create Search Index (CRTSCHIDX) command 20-15****Create Table (CRTTBL) command 13-4****creating**

application display with online help information, steps for 1-1
confirmation list panel 16-27
continued-entry field 6-33
data presentation panel 16-32
DBCS conversion dictionaries D-15
display file and description 2-4
edit description F-5
list panel 16-13
menu bar panel 16-51
menu panel 16-6
message 8-1
object 16-3
pull-down menu 6-13
window 5-3

CRTCLPGM (Create Control Language Program) command 9-12**CRTCMD (Create Command) command 20-15****CRTDOC (Create Document) command 20-17****CRTDSPF (Create Display File) command**

building display with 1-5
creating display files 2-4
DFRWRT (defer write) parameter
improving performance with 14-1
write operation 3-26
display file menus 9-9
ENHDSP (enhance display) parameter 6-3
indicating DBCS files D-5
program menus 9-12
SHARE parameter 14-2

CRTDUPOBJ (Create Duplicate Object) command

DBCS conversion dictionaries D-15
use 9-16

CRTEDTD (Create Edit Description) command

example F-5
running 2-19
use F-5

CRTIGCDCT (Create DBCS Conversion Dictionary) command D-15**CRTMNU (Create Menu) command**

display file menus 9-9

CRTMNU (Create Menu) command (continued)

program menus 9-13

CRTMSGF (Create Message File) command 9-9**CRTPNLGRP (Create Panel Group) command**

building display with 1-5
use 20-14

CRTPRTF (Create Printer File) command D-5**CRTSCHIDX (Create Search Index) command 20-15****CRTTBL (Create Table) command 13-4****CSRLOC (Cursor Location) keyword 3-28****CUA (Common User Access)**

choice entry field 21-50
description 21-47
entry dialog actions, table of 21-48
entry display 21-50
entry fields 21-51
function key area 21-49
information displays 21-52
list display, example 21-52
menu display, single-choice 21-49
message line relationship 21-49
relationship to AS/400 system 21-1
selection choices 21-50
single selection field operation, guidelines 21-50

cursor

actions 6-33
movement, right-to-left 2-16
position when help text displayed 17-14
positioning
after output operation 3-28
during I/O operations 3-41
each page of the subfile record 4-20
rules for list displays 21-29
subfiles 4-21
System/36 application compatibility for display files G-4
returning position to an application 3-29

cursor in window 5-5**cursor key**

movement 6-39

cursor movement

cursor keys 6-39
tab key 6-39

cursor progression

entry field 6-36

D**damaged DBCS devices D-10****data**

ASSUME keyword considerations for passing 11-1
checking validity of 3-37
data
receiving 3-4
describing inside or outside your program 2-3
externally described
definition 2-3

data (continued)

- externally described (*continued*)
 - using 2-3
- input
 - handling negative numeric 3-39
 - keeping 3-36
- KEEP keyword considerations for passing 11-1
- levels of description 2-2
- passing
 - between programs 11-1
 - between programs in same routing step 11-1
 - between routing steps 11-3
- program-described
 - definition 2-3
 - described 2-4
 - using 2-22
- receiving 3-4
- relationship to display file 2-2
- rolling between two lines on display 3-16
- sending and receiving 3-4

DATA (data presentation area) tag

- example
 - data entry panel A-32
 - data entry panel with nested data group A-34
 - data presentation area with menu area A-34
 - two presentation areas for data items A-33
 - two-column format in data entry panel A-32
- overview A-29
- tags allowed table A-29

data area help 19-6

data column (DATACOL) tag

- overview A-37

data description specifications (DDS)

- See also* display file
- See also* keyword, DDS
- CAnn keys, restrictions 2-13
- changing 2-5
- CHECK(FE) (Field Exit) keyword 6-13
- DBCS capabilities D-5
- DDS form 2-7
- definition 1-1
- display files
 - passing data between programs 11-1
 - passing data between routing steps 11-3
 - use in 2-7
- DSPRL (Display Right-to-Left) keyword 2-16
- entry displays 21-43
- ERRMSG (Error Message) keyword 5-6
- ERRMSGID (Error Message ID) keyword 5-6
- ERRSFL (Error Subfile) keyword 5-5
- example
 - 5250 display station problems 3-45
 - CLRL and OVERLAY keywords, differences between 3-15
 - display file menu 9-8
 - display file source 2-7
 - DSPATR(PC) keyword 4-21

data description specifications (DDS) (continued)

example (continued)

- DSPMOD keyword 3-27
- DSPMOD keyword with subfiles 4-14
- ERRSFL keyword 8-4
- HLPCMDKEY keyword 18-20
- HLPCMDKEY keyword with response indicators 18-21
- HLPDOC keyword 18-10
- HLPDOC keyword with option indicators 18-11
- HLPPNLGRP keyword 18-7
- HLPPNLGRP keyword with option indicators 18-8
- HLPRCD keyword 18-13
- HLPRCD keyword with option indicators 18-14
- message subfile 4-20
- OVERLAY and CLRL keywords, differences between 3-15
- program menu 9-11
- PUTOVR keyword 3-18
- PUTOVR keyword for more efficient coding 3-20
- PUTOVR keyword for repeatedly entered data 3-21
- PUTRETAIN keyword, field level 3-24
- PUTRETAIN keyword, record level 3-24
- ROLLUP, SFLSIZ, and SFLPAG keywords 4-16
- secondary help 18-18
 - SFLMSGID keyword 8-5
- SFLNXTCHG keyword 4-18
- SFLPAG, SFLSIZ, and ROLLUP keywords 4-16
- SFLSIZ, ROLLUP, and SFLPAG keywords 4-16
- subfiles for two display sizes 2-20
- two display sizes 2-20
- variable-length record 4-17
- field
 - color (table) 2-18
 - emphasizing (table) 2-17
- help record 5-6
- information displays 21-44
- keywords ignored if display modes are changed 3-28
- list display 21-45
- menu displays 21-42
- MSGLOC (Message Location) keyword 5-5
- NOCCSID (No CCSID) keyword 13-2
- processing order for subfile control 4-7
- program logic 4-28
- programming example 5-14
- RMVWDW (Remove Window) keyword 5-11
- SFLMSG (Subfile Message) keyword 5-6
- SFLMSGID (Subfile Message identifier) keyword 5-6
- subfile, describing with 4-3
- use 2-1
- USRRSTDSP (User Restore Display) keyword 5-11
- validity-checking keyword 5-6

data description specifications (DDS) (continued)

WDWBORDER (Window Border) keyword 5-7

window 5-1

WINDOW (Window) keyword 5-3

data entry panel

example A-32

introduction 16-50

nested data group example A-34

data group (DATAGRP) tag

overview A-38

data item (DATAI) tag

overview A-40

data item choices (DATAC) tag

overview A-36

data item extender (DATAIX) tag

overview A-45

data item group scrolling 17-14

data presentation area (DATA) tag

example

data entry panel A-32

data entry panel with nested data group A-34

data presentation area with menu area A-34

two presentation areas for data items A-33

two-column format in data entry panel A-32

overview A-29

tags allowed table A-29

data presentation panel application

programming 16-47

data presentation panel creating 16-32

data presentation panel source 16-36

data queue

waiting on display file and ICF file 12-1

data selection field (DATASLT) tag

example

data entry panel A-51

multiple-selection field A-51

overview A-49

tags allowed table A-49

data selection field choice (DATASLTC) tag

overview A-53

data stream, 5250 display

See user-defined data stream (UDDS)

data stream, user-defined

See user-defined data stream (UDDS)

data tag, modified 2-10

DATAC (data item choices) tag

overview A-36

DATACOL (data column) tag

overview A-37

DATAGRP (data group) tag

overview A-38

DATAI (data item) tag

overview A-40

DATAIX (data item extender) tag

overview A-45

DATASLT (data selection field) tag

example

data entry panel A-51

multiple-selection field A-51

overview A-49

tags allowed table A-49

DATASLTC (data selection field choice) tag

overview A-53

date value

display form A-23

DBCS (double-byte character set) printing 17-34

DBCS and national language considerations 20-11

DBCS applications, converted from alphanumeric applications D-7

DBCS code scheme D-1

DBCS codes, not valid D-3

DBCS command

See command

DBCS conversion

alphanumeric blanks to DBCS blanks D-25

changing DBCS conversion dictionaries used D-20

deleting unwanted DBCS words D-25

description D-19

entering double-byte data D-21

function D-20

many alphanumeric entries at one time D-24

one alphanumeric entry to double-byte entry D-22

performing (including example operations) D-21

use while editing DBCS conversion dictionary D-25

where you can use D-20

DBCS conversion dictionary

adding the first entries to D-17

beginning editing D-17

creating D-15

deleting D-19

deleting entry D-18

description D-14

displaying and printing D-19

editing (adding and changing terms) D-16

editing suggestions D-18

ending editing D-18

moving entries D-18

printing after displaying D-19

system-supplied D-14

user-created D-15

DBCS device

damaged D-10

display stations D-6

DBCS display stations and number of input fields D-6

DBCS field, determining the length D-4

DBCS file

description of D-5

restrictions D-6

specifying D-5

DBCS font table

- checking for existence of D-8
- copying
 - from tape (restore) D-9
 - onto diskette (save) D-9
- deleting D-10
- description of D-8
- restoring from tape or diskette D-9
- saving onto diskette D-9
- system-supplied D-8

DBCS master sort table, Japanese

- copying from data file D-13
- copying to data file D-13

DBCS sort table

- checking for existence of D-12
- copying
 - from data file (move from System/36) D-13
 - to data file (move to System/36 or AS/Entry) D-12
- deleting D-14
- description D-11
- restoring from tape or diskette D-12
- saving onto diskette D-12

DBCS words, deleting during DBCS**conversion D-25****DBCS-graphic and shift control characters D-6****DBCS-graphic fields on double-byte displays D-7****DDS (data description specifications)**

See also display file

See also keyword, DDS

CAnn keys, restrictions 2-13

changing 2-5

CHECK(FE) (Field Exit) keyword 6-13

DBCS capabilities D-5

DDS form 2-7

definition 1-1

display files

- passing data between programs 11-1

- passing data between routing steps 11-3

- use in 2-7

DSPRL (Display Right-to-Left) keyword 2-16

entry displays 21-43

ERRMSG (Error Message) keyword 5-6

ERRMSGID (Error Message ID) keyword 5-6

ERRSFL (Error Subfile) keyword 5-5

example

- 5250 display station problems 3-45

- CLRL and OVERLAY keywords, differences between 3-15

- display file menu 9-8

- display file source 2-7

- DSPATR(PC) keyword 4-21

- DSPMOD keyword 3-27

- DSPMOD keyword with subfiles 4-14

- ERRSFL keyword 8-4

- HLPCMDKEY keyword 18-20

- HLPCMDKEY keyword with response indicators 18-21

DDS (data description specifications) (continued)

example (continued)

- HLPDOC keyword 18-10

- HLPDOC keyword with option indicators 18-11

- HLPPNLGRP keyword 18-7

- HLPPNLGRP keyword with option indicators 18-8

- HLPRCD keyword 18-13

- HLPRCD keyword with option indicators 18-14

- message subfile 4-20

- OVERLAY and CLRL keywords, differences between 3-15

- program menu 9-11

- PUTOVR keyword 3-18

- PUTOVR keyword for more efficient coding 3-20

- PUTOVR keyword for repeatedly entered data 3-21

- PUTRETAIN keyword, field level 3-24

- PUTRETAIN keyword, record level 3-24

- ROLLUP, SFLSIZ, and SFLPAG keywords 4-16

- secondary help 18-18

- SFLMSGID keyword 8-5

- SFLNXTCHG keyword 4-18

- SFLPAG, SFLSIZ, and ROLLUP keywords 4-16

- SFLSIZ, ROLLUP, and SFLPAG keywords 4-16

- subfiles for two display sizes 2-20

- two display sizes 2-20

- variable-length record 4-17

field

- color (table) 2-18

- emphasizing (table) 2-17

help record 5-6

information displays 21-44

keywords ignored if display modes are changed 3-28

list display 21-45

menu displays 21-42

MSGLOC (Message Location) keyword 5-5

NOCCSID (No CCSID) keyword 13-2

processing order for subfile control 4-7

program logic 4-28

programming example 5-14

RMVWDW (Remove Window) keyword 5-11

SFLMSG (Subfile Message) keyword 5-6

SFLMSGID (Subfile Message identifier)

- keyword 5-6

subfile, describing with 4-3

use 2-1

USRRSTDSP (User Restore Display) keyword 5-11

validity-checking keyword 5-6

WDWBORDER (Window Border) keyword 5-7

window 5-1

WINDOW (Window) keyword 5-3

DDS form 2-7**DDS keyword**

See keyword, DDS

DDS record

See record, DDS

decimal point, edit description for F-4**Default (DFT) keyword**

use 3-26

with ASSUME keyword 11-1

default value

fields 3-26

defining

accelerator key 6-16

application help 6-29

application pop-up window 17-27

application window 17-27

attributes for entry fields 6-37

cancel key 6-18

choice colors and attributes 6-19

choice-level help 6-29

contextual help in UIM 17-14

cursor progression for entry fields 6-36

dialog variables 17-1

function keys 17-17

function keys and VARUPD value 17-18

header area 17-33

help for field 6-31

lists 17-6

menu object 16-6

menu-bar switch key 6-17

mnemonic 6-19

MNUBARDSP (Menu-Bar Display) keyword

application record 6-22, 6-41

menu-bar record 6-24, 6-43

panel group object 16-13

prolog area 17-33

scrollable areas 17-12

definition

panel A-2

definition list

device C-4

definition list (DL) tag

example

compact definition list A-56

definition list A-56

overview A-55

tags allowed table A-55

use in help module 20-5

Delete DBCS Conversion Dictionary (DLTIGCDCT)

command D-19

Delete DBCS Font Table (DLTIGCTBL) command

deleting D-10

use D-10

Delete DBCS Sort Table (DLTIGCSRT)

command D-14

Delete Menu (DLTMNU) command 9-17**Delete Override (DLTOVR) command 7-5****Delete Panel Group (DLTPNLGRP) command 20-14****Delete Search Index Entry (RMVSCHIDX)**

command 20-16

deleting

DBCS conversion dictionary D-19

DBCS font table D-10

DBCS sort tables D-14

DBCS words D-25

menu displays 9-17

overrides 7-5

panel group 20-14

search index 20-16

window 5-11

description

field-level

definition 2-2

use 2-2

file-level

definition 2-3

use 2-3

record-level

definition 2-3

use 2-3

description, file

changing

reasons for 2-2

with the CHGDSPF command 2-5

creating for display file 2-4

definition 1-1

detecting changes in 2-6

determining 2-2

descriptive text area, entry displays 21-15**device**

DBCS

damaged D-10

display stations D-6

device definition list

definition 3-3

part of open feedback area C-4

DFRWRT (defer write) parameter

improving performance with 14-1

restrictions 3-26

using 3-26

DFT (Default) keyword

use 3-26

with ASSUME keyword 11-1

DFTVAL (Default Value) keyword 3-26**dialog command**

ACTIONS (Menu Bar Cursor Action) B-4

CALL (Call Program) B-4

Call Program (CALL) B-4

CANCEL (Cancel) B-6

Change View (Change View) B-6

CHGVIEW (Change View) B-6

CMD (System Command) B-7

CMDLINE (Command Line) B-7

Command Line (CMDLINE) B-7

dialog command *(continued)*

Display Help (DSPHELP) B-7
 Display Home Menu (HOME) B-10
 Display Message (MSG) B-11
 Display More Function Keys (MOREKEYS) B-10
 DSPHELP (Display Help) B-7
 effects of B-1
 ENTER (Enter) B-8
 entry field prompting B-13
 EXIT (Exit Display) B-8
 Exit Display (EXIT) B-8
 Extended Help (EXTHelp) B-9
 EXTHelp (Extended Help) B-9
 HELP (Help) B-9
 HELPHelp (Help Help) B-9
 HELPIDX (Help Index) B-9
 HOME (Display Home Menu) B-10
 introduction B-1
 KEYSHELP (Keys Help) B-10
 MENU (Menu) B-10
 Menu Bar Cursor Action (ACTIONS) B-4
 MOREKEYS (Display More Function Keys) B-10
 Move to Top (MOVETOP) B-11
 MOVETOP (Move to Top) B-11
 MSG (Display Message) B-11
 PAGEDOWN (Page Down) B-12
 PAGEUP (Page Up) B-12
 PRINT (Print Display) B-12
 Print Display (PRINT) B-12
 PROMPT (Prompt) B-12
 prompting an entry field B-13
 PULLDOWN (Display Pull-down Menu) B-14
 RETRIEVE (Retrieve Command String) B-14
 Retrieve Command String (RETRIEVE) B-14
 RETURN (Return Control to Application) B-14
 Return Control to Application (RETURN) B-14
 System Command (CMD) B-7
 valid uses B-1
 variable update (VARUPD) attribute B-4
 VARUPD attribute B-4

dialog variable

defined by UIM A-160
 defining 17-1
 definition 17-1
 displaying panel field value using 17-4
 error messages 17-3
 incorrect display characters 17-4
 initial value 17-2
 restrictions 17-2
 variable pool 17-1
 Z36ENV A-160
 ZCANCEL A-160
 ZDBCS A-160
 ZDSPSIZ A-160
 ZEXIT A-160
 ZJOB A-160

dialog variable *(continued)*

ZJOBNBR A-160
 ZLMTCPB A-160
 ZMENU A-160
 ZMNULIB A-160
 ZSYSNAM A-160
 ZUSER A-160

dictionary, DBCS conversion

adding the first entries to D-17
 beginning editing D-17
 creating D-15
 deleting D-19
 deleting entry D-18
 description D-14
 displaying and printing D-19
 editing (adding and changing terms) D-16
 editing suggestions D-18
 ending editing D-18
 moving entries D-18
 printing after displaying D-19
 system-supplied D-14
 user-created D-15

differences between pull-down menus and pop-up windows 17-25**diskette file**

DBCS D-5

display

creating UIM 16-13
 list 17-7
 panel field value using dialog variables 17-4
 UIM 16-13
 user interface manager 16-13

display attribute

available choice 6-20
 color fields 2-18
 emphasizing fields 2-17
 selected choice 6-20
 unavailable choice 6-20

display attribute (*DSPATR) parameter 6-20**Display Attribute (DSPATR) keyword**

example source for PC value 4-21
 use 3-28
 with ASSUME keyword 11-1
 with program-to-system field 2-17

display character

incorrect 17-4

Display DBCS Conversion Dictionary (DSPIGCDCT) command D-19**display device file**

See display file

display device support, DBCS D-6**Display Edit Description (DSPEDTD)**

command 2-19

display file

See also data description specifications (DDS)
 See also subfile

display file *(continued)*

See also window

ASSUME (Assume)

considerations 11-1

attributes for fields, System/36 application compatibility G-3

cancel-invite operation, System/36 application compatibility G-8

characteristics of 2-1

closing 3-49

command key validity 3-45

creating

ways for 2-5

with DDS 2-4

without DDS 2-22

cursor positioning, System/36 application compatibility G-4

DBCS D-5

defining input and output 2-24

defining your display in 2-1

definition 1-1

description

creating 2-4

how changes are applied to 2-6

display station controller, System/36 application compatibility G-2

displaying messages, System/36 application compatibility G-4

edit codes, user-defined F-4

edit descriptions F-1

erase-input-fields function, System/36 application compatibility G-3

establishing 2-1

example, programming 5-14

examples

assigning space to program-described 2-22

building with online help 1-1

DDS source 2-7

replacing record formats on display 3-8

file entry field attributes 12-1

function keys, System/36 application compatibility G-7

HELP and HLPRTN keywords, System/36 application compatibility G-7

input data

System/36 application compatibility G-2

input data, System/36 application compatibility G-2

input-only, defining 2-23

lock 3-1

maximum number of record formats in 2-15

obtaining information about 3-3

online help information

See online help information

opening 3-2

operations supported by the system and high-level languages

BASIC statements 3-49

display file *(continued)*

operations supported by the system and high-level languages *(continued)*

C/400 functions 3-49

CL commands 3-49

COBOL/400 statements 3-49

FORTRAN/400 statements 3-49

RPG/400 operations 3-49

operator changes, System/36 application compatibility G-3

output-only, defining 2-23

overriding

attributes in HLL programs 7-1

file names and attributes in HLL programs 7-3

file names in HLL programs 7-3

passing data

between programs 11-1

between routing steps 11-3

put with explicit override, System/36

compatibility G-6

relationship to data 2-2

retain command and function keys, System/36 application compatibility G-9

return codes E-1

screen size, specifying to improve performance 14-1

self-check, System/36 application compatibility G-2

sharing in same job 3-50

signed numeric data, System/36 application compatibility G-7

suspended 3-42

System/36 application compatibility G-1

System/36 functions not supported G-9

use 3-1

waiting for data with ICF file, data queue 12-1

window use 5-1

display file attribute

See file attribute

Display File Description (DSPFD) command 2-7**Display File Field Description (DSPFFD) command 2-7****display file menu**

See menu display

display form

binary value A-22

character value A-23

date value A-23

example numeric values A-22

numeric value A-22

time value A-23

Display Help (DSPHELP) dialog command B-7**Display Help Document (DSPHLPDOC) command 20-18****Display Home Menu (HOME) dialog command B-10****display I/O feedback area C-9**

Display Menu Attributes (DSPMNUA)**command** 9-16**Display Message (MSG) dialog command** B-11**display mode**

changing 4-14

DDS keywords ignored if changed 3-28

definition 4-14

displaying subfiles horizontally with 4-14

Display Mode (DSPMOD) keyword

description 3-27

example for subfiles 4-14

sample subfile display for *DS3 4-15

sample subfile display for *DS4 4-15

subfile use 4-14

Display More Function Keys (MOREKEYS) dialog**command** B-10**Display Override (DSPOVR) command** 7-6**display panel (PANEL) tag**

example

panel definition A-124

overview A-120

tags allowed table A-120

display panel field value using dialog**variables** 17-4**Display Program References (DSPPGMREF)****command** 2-7**Display Right-to-Left (DSPRL) keyword** 2-16**Display Size (DSPSIZ) keyword** 2-20**display station**

acquired, releasing from I/O operations 3-49

calculating maximum number of fields 3-39

device description, changing for printers 2-22

enhanced capabilities 6-3

models

3180-2 3-27

3197 3-27

5250, avoiding record format problems on 3-45

obtaining information about 3-3

types 5-2, 6-2

user-defined data streams, differences for 10-1

with UNLOCK 3-35

display station controller, System/36 application compatibility G-2**display, application**

See application display

displaying

list 17-7

message

about 8-1

in field 8-3

in program message queue 8-4

on message line 8-2

on message line using message field 8-3

on message line when subfile control record written 8-2

through subfile 8-4

displaying *(continued)*

override 7-6

panel using request processor program 17-30

System/36 application compatibility G-4

DL (definition list) tag

example

a definition list A-56

compact definition list A-56

overview A-55

tags allowed table A-55

use in help module 20-5

DLTIGCDCT (Delete DBCS Conversion Dictionary)**command** D-19**DLTIGCSRT (Delete DBCS Sort Table)****command** D-14**DLTIGCTBL (Delete DBCS Font Table) command**

deleting D-10

use D-10

DLTMNU (Delete Menu) command 9-17**DLTOVR (Delete Override) command** 7-5**DLTPNLGRP (Delete Panel Group) command** 20-14**DLTSCHIDX (Delete Search Index Entry)****command** 20-16**document, office**

comparing with panel groups and records 18-2

creating for help 20-17

definition for help 1-6

examples

HLPDOC keyword 18-10

HLPDOC keyword with option indicators 18-11

steps for creating sample 20-17

help, defining for 20-17

help, specifying for 18-9

viewing without Help key 20-18

double strike 17-33**double-byte character**

basic D-4

code scheme D-1

DBCS-graphic D-6

examples

alphabetic characters coded in single-byte and

double-byte scheme D-1

converting and entering an entry into a

field D-22

copying DBCS font table to diskette D-9

copying DBCS font table to system D-9

copying DBCS font table to tape D-9

extended D-4

identifying a string of D-3, D-6

maximum number (extended) that can be

displayed D-6

maximum number input fields displayed D-6

processing extended characters D-4

shift-control characters D-6

shift-control characters, inserting D-6

size D-4

- double-byte character** *(continued)*
 - system processing of D-4
- double-byte character set**
 - continued entry field 6-33
 - mnemonics 6-19
- double-byte code**
 - effects of printing invalid D-3
- double-byte data**
 - basic information D-1
 - considerations for using D-3
 - designing application programs that process D-7
 - fields, determining the length D-4
 - identifying D-3
 - restrictions on D-4
 - where you can use D-3
- double-byte display**
 - effects of displaying DBCS-graphic fields D-7
- DSPATR (Display Attribute) keyword**
 - example source for PC value 4-21
 - use 3-28
 - with ASSUME keyword 11-1
 - with program-to-system field 2-17
- DSPEDTD (Display Edit Description)**
 - command 2-19
- DSPFD (Display File Description) command** 2-7
- DSPFFD (Display File Field Description)**
 - command 2-7
- DSPHELP (Display Help) dialog command** B-7
- DSPHLPDOC (Display Help Document)**
 - command 20-18
- DSPIGCDCT (Display DBCS Conversion Dictionary)**
 - command D-19
- DSPMNUA (Display Menu Attributes)**
 - command 9-16
- DSPMOD (Display Mode) keyword**
 - description 3-27
 - Display Mode (DSPMOD) 4-14
 - example for subfiles 4-14
 - sample subfile display for *DS3 4-15
 - sample subfile display for *DS4 4-15
 - subfile use 4-14
 - use 3-27
- DSPOVR (Display Override) command** 7-6
- DSPPGMREF (Display Program References)**
 - command 2-7
- DSPRL (Display Right-to-Left) keyword** 2-16
- DSPSIZ (Display Size) keyword**
 - specifying to improve performance 14-1
 - use 2-20
- DTAQ (data queue) parameter** 12-1
- duplicate object**
 - creating D-15
- duplicating window** 5-9
- dynamic list column heading formatting**
 - example A-86

E

- edit code**
 - defining your own 2-19
 - definition 2-18
 - description F-4
 - IBM-supplied F-1
 - use 2-19
- Edit Code (EDTCDE) keyword** 2-19
- Edit DBCS Conversion Dictionary (EDTIGCDCT)**
 - command D-16
- edit description**
 - creating F-5
 - about F-5
 - example F-5
 - decimal point F-4
 - description F-4
 - IBM-supplied F-4
 - rules F-5
- edit mask**
 - creating 6-38
- Edit Related Words display** D-17
- edit word**
 - definition 2-18
- Edit Word (EDTWRD) keyword** 2-19
- editing**
 - DBCS conversion dictionary D-16
- EDTCDE (Edit Code) keyword** 2-19
- EDTIGCDCT (Edit DBCS Conversion Dictionary)**
 - command D-16
- EDTWRD (Edit Word) keyword** 2-19
- effects of displaying DBCS-graphic fields on**
 - double-byte displays D-7
- elements within a panel group** 16-3
- embed**
 - See imbed
- emphasis values table** A-99
- emphasizing fields** 2-17
- End Receive (ENDRCV) command** 3-31
- ending attribute character**
 - definition 2-8
- ENDRCV (End Receive) command** 3-31
- engraved key restrictions** 17-12
- enhanced display (ENHDSP) parameter**
 - writing records 6-3
- ENHDSP (enhanced display) parameter**
 - writing records 6-3
- ENTER dialog command** B-8
- entering**
 - commands that are too long 17-17
- entry dialog actions, table of CUA** 21-48
- entry display**
 - CUA entry field 21-50
 - description 21-10
 - descriptive text area 21-15
 - entry fields 21-13

entry display *(continued)*

examples

AS/400-style 21-10

CUA entry field 21-50

field prompts 21-11

instruction lines 21-11

online help information

DDS considerations 21-43

description 21-42

help areas for 21-43

types 21-42

operating guidelines 21-16

possible choices information 21-15

prompt areas 21-11

title 21-10

entry field

attributes for 6-37

CUA 21-51

cursor progression for 6-36

entry displays 21-13

menu selection 21-9

prompting B-13

protecting using Edit Masks 6-38

rules for displays 21-14

entry field attribute

creating 6-37

entry pointer for list 17-8

ERASE (Erase) keyword

erasing records 3-10

restriction with USRDSPMGT keyword G-10

System/36 application compatibility G-2

with OVERLAY keyword 3-10

Erase Input (ERASEINP) keyword

system performance considerations 14-3

use 3-23

erase-input-fields function, System/36 application

compatibility G-3

ERASEINP (Erase Input) keyword

system performance considerations 14-3

use 3-23

erasing input 3-23

ERRMSG (Error Message) keyword 5-6, 8-2

ERRMSGID (Error Message Identifier) keyword 5-6, 8-2

error

See also major/minor return code

See also message

field validation 3-34

recovering from 8-11

recovering from run-time 3-52

while scrolling 17-13

error condition 17-13

error message

dialog variables 17-3

window 5-5

Error Message (ERRMSG) keyword 5-6, 8-2

Error Message ID (ERRMSGID) keyword 5-6

Error Message Identifier (ERRMSGID) keyword 8-2

Error Message Subfile (ERRSFL) keyword

example DDS source 8-4

message received from 5-5

restriction with USRDSPMGT keyword G-10

use 8-4

ERRSFL (Error Message Subfile) keyword

example DDS source 8-4

message received from 5-5

restriction with USRDSPMGT keyword G-10

use 8-4

example

accelerator key 6-17

alternate view of list 16-15

application formatted area A-9

building sample display with online help 1-1

check box 6-1

CL programs

program menu 9-12

RTNPNT(*NO) for program menu, CL source
for 9-14

class definition A-22

command line pop-up window 17-29

compact definition A-56

conditioning option A-27

continued attribute A-1

continued-entry field 6-34

data description specifications (DDS)

5250 display station problems 3-45

ALWROL keyword 3-16

CHRID keyword 13-2

CLRL and OVERLAY keywords, differences
between 3-15

CLRL(*NO) keyword 3-14

display file menu 9-8

display file source 2-7

display size, for more than one 2-20

DSPATR(PC) keyword 4-21

DSPMOD keyword 3-27

DSPMOD keyword with subfiles 4-14

ERRSFL keyword 8-4

HLPCMDKEY keyword 18-20

HLPCMDKEY keyword with response

indicators 18-21

HLPDOC keyword 18-10

HLPDOC keyword with option indicators 18-11

HLPPNLGRP keyword 18-7

HLPPNLGRP keyword with option

indicators 18-8

HLPRCD keyword 18-13

HLPRCD keyword with option indicators 18-14

INZRCD and UNLOCK keywords 3-36

message subfile 4-20

OVERLAY and CLRL keywords, differences
between 3-15

example (continued)

data description specifications (DDS) (continued)

- program logic for subfiles 4-28
- program menu 9-11
- PUTOVR keyword 3-18
- PUTOVR keyword for repeatedly entered data 3-21
- PUTOVR keyword, more efficient coding 3-20
- PUTRETAIN keyword, field level 3-24
- PUTRETAIN keyword, record level 3-24
- ROLLUP, SFLSIZ, and SFLPAG keywords 4-16
- RSTDSP parameter 3-43
- secondary help 18-18
- SFLMSGID keyword 8-5
- SFLNXTCHG keyword 4-18
- SFLPAG, SFLSIZ, and ROLLUP keywords 4-16
- SFLSIZ, ROLLUP, and SFLPAG keywords 4-16
- SLNO(*VAR) keyword 3-12
- subfiles for two display sizes 2-20
- UNLOCK and INZRCD keywords 3-36
- variable-length record 4-17
- data entry panel A-32, A-51
- data entry panel with nested data group A-34
- data entry panel, two-column format A-32
- data presentation panel 16-32
- data presentation panel after scrolling 16-34
- defining MNUBARDSP on application record 6-22, 6-41
- defining MNUBARDSP on menu-bar record 6-24, 6-43
- definition list A-56
- display with output and input fields displayed in response to request 2-10
- documents, office
 - HLPDOC keyword 18-10
 - HLPDOC keyword with option indicators 18-11
- double-byte characters
 - alphabetic characters coded in single-byte and double-byte scheme D-1
 - converting and entering entry into field D-22
 - copying DBCS font table to diskette D-9
 - copying DBCS font table to system D-9
 - copying DBCS font table to tape D-9
 - inserting shift-control characters D-6
- dynamic list column heading A-86
- edit description, creating F-5
- entry displays
 - CUA 21-50
 - typical 21-10
- formatting example A-164
- heading tags A-63
- help modules
 - command help 20-15
 - imbedded 20-2
 - imported 20-3
 - ISCH tag 20-8
 - ISCHSYN tag 20-8

example (continued)

help modules (continued)

- LINK tag 20-14
- panel group with 20-2
- help panel definition A-59
- hypertext link A-78
- imbedded help A-64
- index search A-68
- index search synonym A-70
- information display 21-17
- key definitions A-73
- key list A-74
- left-to-right formatting on left-to-right panel A-147
- left-to-right formatting on right-to-left panel A-147
- list
 - ordered A-117
 - simple A-149
 - translation A-152
 - unordered A-158
- list actions A-93
- list area
 - example, UIM source A-84
 - list column groups A-85
 - three layout columns A-85
- list display
 - CUA 21-52
 - extended action entry 21-20
- list panel 16-14
- list part A-105
- menu area with groups A-110
- menu bar
 - choices 6-6
 - DDS 6-41
 - panel 16-51
 - UIM A-106
- menu displays
 - display file menu 9-8
 - message file, adding messages to 9-9
 - message file, describing menu actions in 9-5
 - naming help formats in message file 9-6
 - program menu 9-11
 - program menu, CL source for 9-12
 - RTNPNT(*NO) for program menu, CL source for 9-14
 - single choice 21-7
 - using options and GO command 9-2
- menu panel 16-6
 - creating 16-6
- menu source 16-9
- menu-bar choice help 6-29
- menu-bar help list 6-31
- message
 - ERRSFL keyword 8-4
 - SFLMSGID keyword 8-5
- message, trailer A-145
- mnemonic, not valid DDS for 6-19

example (continued)

- multiple-choice selection field 6-9
- multiple-selection field A-51
- note A-115
- numeric values table A-22
- online help information
 - command help 20-15
 - display showing help areas 18-4
 - HLPCMDKEY keyword 18-20
 - HLPCMDKEY keyword with response indicators 18-21
 - HLPDOC keyword 18-10
 - HLPDOC keyword with option indicators 18-11
 - HLPPNLGRP keyword 18-7
 - HLPPNLGRP keyword with option indicators 18-8
 - HLPRCD keyword 18-13
 - HLPRCD keyword with option indicators 18-14
 - imbedded help modules in panel group 20-2
 - imported help modules in panel group 20-3
 - ISCH tag 20-8
 - ISCHSYN tag 20-8
 - LINK tag 20-14
 - panel groups with help modules 20-2
 - secondary help 18-18
- ordered list A-117
- output operation
 - effect of OVERLAY and ERASE on 3-10
- overrides
 - applying when compiling program 7-5
 - attribute of display file 7-1
 - different display file 7-3
 - different display file and attributes 7-4
- panel definition A-124
- panel groups
 - command help 20-15
 - help modules 20-2
 - HLPPNLGRP keyword 18-7
 - HLPPNLGRP keyword with option indicators 18-8
 - imbedded help modules 20-2
 - imported help modules 20-3
 - ISCH tag 20-8
 - ISCHSYN tag 20-8
 - LINK tag 20-14
- paragraph continuation A-128
- paragraph tag A-119
- parameter list A-127
- passing data
 - between routing steps 11-3
 - in same routing step 11-1
- print title line A-142
- program-described display file 2-22
- pull-down menu 6-13, 6-41
- PULLINPUT parameter 6-26
- radio button 6-1

example (continued)

- record format, replacing 3-8
- record, DDS
 - HLPCMDKEY keyword 18-20
 - HLPCMDKEY keyword with response indicators 18-21
 - HLPRCD keyword 18-13
 - HLPRCD keyword with option indicators 18-14
 - secondary help 18-18
- return-field (RTNFLD) parameter 6-28
- roll operation 3-16
- sample figure A-57
- sample heading A-163
- simple list A-149
- simple menu area A-110
- single-choice selection field 6-9
- single-choice selection field choice help 6-30
- SLNO (Starting Line Number) keyword 3-12
- subfile
 - *DS3 mode display 4-15
 - *DS4 mode display 4-15
 - DSPATR(PC) keyword 4-21
 - DSPMOD keyword 4-14
 - message subfile 4-20
 - program logic for subfiles 4-28
 - ROLLUP, SFLSIZ, and SFLPAG keywords 4-16
 - sample display for changing information 4-2
 - sample display for display only 4-1
 - sample display for input only 4-2
 - sample display for task combination 4-2
 - sample display with selection 4-1
 - sample displays when rolling two or more records 4-25
 - SFLNXTCHG keyword 4-18
 - SFLPAG, SFLSIZ, and ROLLUP keywords 4-16
 - SFLSIZ, ROLLUP, and SFLPAG keywords 4-16
 - variable-length record 4-17
 - vertical and horizontal, displayed at same time 4-12
- suppressed selection character 6-15
- title citation A-13
- translation list A-152
- truth table A-155
- two presentation areas
 - data items A-33
 - menu area A-34
- unavailable choice 6-12
- unformatted lines A-75
- unordered list A-158
- valid DDS for mnemonic 6-19
- validity checking A-12
- window use 5-14

example (XMP) tag

- example, formatting an example A-164
- help module 20-5
- overview A-164

- EXIT (Exit Display) dialog command** B-8
- Exit Display (EXIT) dialog command** B-8
- Exit key, using on menus** 9-2
- expression**
 - conditional A-25, A-77
- extended action entry**
 - list displays 21-23
- extended alphabetic**
 - definition 13-1
- extended character**
 - processing D-4
 - what happens when not processed D-4
- extended help**
 - definition 18-3, 19-2
- Extended Help (EXTHELP) dialog command** B-9
- extended help heading (XH1 through XH4) tag**
 - example, sample heading A-163
 - formatting rules A-163
 - overview A-163
 - use in help module 20-4
- externally described data**
 - advantages of 2-3
 - definition 2-3
 - use 2-3
- EXTHELP (Extended Help) dialog command** B-9

F

- feedback area**
 - common 3-3
 - error information 3-4
 - file-dependent 3-3
 - function keys 2-12
 - get attributes C-12
 - I/O
 - common C-6
 - definition 3-3
 - display C-9
 - for function keys 2-12
 - open
 - definition 3-3
 - device definition list C-4
 - individual descriptions C-1
- field**
 - attribute
 - defining 6-37
 - attributes, System/36 application compatibility G-3
 - calculating maximum number for display
 - station 3-39
 - character, maximum length 2-11
 - characteristics of 2-2
 - choice entry, Common User Access 21-50
 - color 2-18
 - constant 2-10
 - cursor progression
 - defining 6-36

- field (continued)**
 - default values, specifying 3-26
 - defining
 - attribute 6-37
 - cursor progression 6-36
 - definition 2-2
 - display 2-7
 - displaying 2-8
 - emphasizing 2-17
 - entry
 - See* entry field
 - erasing unprotected input and output/input 3-23
 - hidden 2-9
 - input 2-9
 - input and output, displayed in response to request 2-10
 - input-capable, limitations on number of 3-39
 - keeping on display 3-23
 - list 21-23
 - maximum number in record format 2-10
 - menu selection entry 21-9
 - message 2-10
 - numeric
 - maximum length 2-11
 - output 2-9
 - output/input 2-9
 - overriding attributes or content of 3-18
 - previously described 2-11
 - program-to-system
 - understanding how to use 2-10
 - with DSPATR keyword 2-17
 - record format 2-9
 - reference 2-11
 - validation errors 3-34
 - zoned decimal, maximum length 2-11
- field (*FLD) special value** 6-30
- field attribute character** 2-8
- Field Exit (CHECK(FE)) keyword** 6-13
- field location**
 - input and output records 2-9
 - when to specify 2-11
- field prompt, entry displays** 21-11
- field value for display panel using dialog variables** 17-4
- field-exit processing**
 - backward 6-36
 - forward 6-36
- field-level description**
 - definition 2-2
 - use 2-2
- field, graphic** A-6
- FIG (figure) tag**
 - example, sample figure A-57
 - overview A-57
 - use in help module 20-5

figure (FIG) tag

- example, sample figure A-57
- overview A-57
- use in help module 20-5

file**DBCS**

- diskette D-5
- display D-5
- ICF D-5
- printer D-5
- tape D-5

definition 2-3**display**

- See display file

shared in job

- close operation for 3-52
- input/output operation for 3-51
- open operation for 3-51

source 1-2**file attribute**

- building 7-1
- overriding
 - along with display file name in HLL programs 7-3
- display files in HLL programs 7-1

file description

- changing
 - reasons for 2-2
 - with the CHGDSPF command 2-5
- creating for display file 2-4
- definition 1-1
- detecting changes in 2-6
- determining 2-2

file redirection

- definition 7-6
- different file types 7-6
- level checking 7-6
- same file types 7-6
- table of defaults for combinations 7-7
- valid for input and output 7-7

file resource

- how allocated 3-1

file-dependent feedback area 3-3**file-level description 2-3****folding**

- list panel 17-23
- multiple panels when EXIT requested 17-21
- when EXIT requested 17-21

font

- highlighting 17-33

font table, DBCS

- description of D-8
- determining existence D-8
- restoring from tape or diskette D-9
- saving onto diskette D-9

format, record

- See record format

formatting

- bidirectional considerations A-78
- column data A-97
- display form
 - binary value A-22
 - character value A-23
 - date value A-23
 - time value A-23
- example A-164
- function keys 17-17
- IGC (ideographic characters)
 - BOTINST (bottom instruction) tag A-10
 - DATAC (data item choices) tag A-36
 - PDFLDC (pull-down field choice) tag A-133
 - TOPINST (top instruction) tag A-154
- numeric value
 - example values table A-22
- panel
 - concepts 17-19
 - user control 17-21
- panels 17-19
- printed
 - information area A-67
 - list area A-83

FORTRAN/400 statements, mapping to I/O operations 3-49**forward field-exit processing 6-36****full screen mode**

- help information A-59

function key

- assignments, table 21-36
- common assignments on AS/400-style displays 21-36
- CUA entry dialog actions, table of 21-48
- DDS keywords for 2-11
- defining
 - in DDS 2-11
 - in UIM 17-17
- formatting in UIM 17-17
- handling in UIM 17-18
- optional for AS/400-style displays, table of 21-7
- required for AS/400-style displays, table of 21-7
- retain command, System/36 application compatibility G-9
- scrolling in UIM 17-12
- System/36 application compatibility G-7
- VARUPD value 17-18

function key area

- CUA 21-49
- menu displays, single-choice 21-7

function key area help 19-13**function, built-in**

- CHKOBJ (check object) A-26, A-77
- CHKUSRCLS (check user class) A-26, A-78

G

get-attributes feedback area C-12

get-attributes operation

C/400 function for 3-49

COBOL/400 statement for 3-49

definition 3-4

RPG/400 operation for 3-49

table of information available from 3-4

get-next-changed operation

definition 4-10

get-next-changed operation for subfiles

BASIC statement for 4-12

C/400 function for 4-12

COBOL/400 statement for 4-12

RPG/400 operation for 4-12

get-relative operation

definition 4-10

get-relative operation for subfiles

BASIC statement for 4-12

C/400 function for 4-12

COBOL/400 statement for 4-12

RPG/400 operation for 4-12

GETRETAIN (Get Retain) keyword 3-36

GO (Go to Menu) command

generic menu specification 9-16

use 9-1

Go to Menu (GO) command

generic menu specification 9-16

use 9-1

Grant Object Authority (GRTOBJAUT)

command D-15

graphics

field A-6

literal A-6

group object, panel A-2

GRTOBJAUT (Grant Object Authority)

command D-15

guideline

CUA, single selection field operation 21-50

message 21-46

operating

entry displays 21-16

information displays 21-20

list display 21-24

menu displays 21-9

H

H specification

definition 18-4

effect on help-list updating 18-16

entering in DDS source 18-4

order in DDS source 18-4

paging order 18-16

H1 through H4 (headings)

example

heading tags A-63

help module 20-4

overview A-63

handle on list entry 17-7

handling function keys and VARUPD value 17-18

header area

defining 17-33

heading (H1 through H4) tag

example

heading tags A-63

overview A-63

use in help module 20-4

heading, column 21-22

help

choice-level 6-29

data area 19-6

defining for application 6-29

displayed in window 5-6, 5-8

field 6-31

function key area 19-13

item specific 6-30

list area 19-3

menu area 19-4

menu bar area 19-11

panels A-3

HELP (help module) tag

example, help panel definition A-59

overview A-58

placement in UIM source 20-2

UIM source showing panel groups with help

modules 20-2

HELP (Help) keyword

enabling the Help key 18-2

function key use 2-12

specifying alternative 2-13

System/36 application compatibility G-7

help area

See online help information

Help Area (HLPARA) keyword 18-4

help boundary

definition 18-17

Help Boundary (HLPBDY) keyword

secondary help 18-18

use 18-17

Help Command Key (HLPCMDKEY) keyword

restriction with USRDSPMGT keyword G-10

use 18-20

HELP dialog command B-9

help display

See online help information

Help Document (HLPDOC) keyword

for specifying the document name 18-9

with HLPBCD and HLPPNLGRP 18-11

with option indicators 18-11

Help Exclude (HLPXCLD) keyword 18-6

help for field 6-31

Help Full (HLPFULL) keyword 18-6

help group
definition 18-17

help information
See online help information

Help key 19-1
See also ALTHELP (Alternate Help) keyword
See also HELP (Help) keyword
enabling 18-2
results when pressed 18-1
returning to program after pressing 18-20
returning to program without pressing 18-21

help list
defining for application 6-31
definition 18-16

help module
contained in different help panel group, using 20-3
definition 20-2
emphasizing and formatting text within 20-4
examples
command help 20-15
imbedded 20-2
imported 20-3
ISCH tag 20-8
ISCHSYN tag 20-8
LINK tag 20-14
panel group with 20-2
headings, adding 20-4
highlighting text 20-4
hypertext 20-12
linking 20-12
making lists 20-5
names 20-2
organizing panel group with 20-2
paragraphs and notes, defining 20-4
programming keywords and variables, identifying 20-5
structured text, indicating 20-5
using more than once 20-2

help module (HELP) tag
example, help panel definition A-59
overview A-58
placement in UIM source 20-2

Help Panel Group (HLPNLGRP) keyword
use 18-6
with HLPBCD and HLPDOC keywords 18-8
with option indicators 18-8

Help Record (HLPBCD) keyword
with HLPDOC keyword in same file 18-15
with HLPNLGRP keyword in same file 18-12
with option indicators 18-13

Help Return (HLPRTN) keyword
returning to your program after help 18-21
System/36 application compatibility G-7

Help Search Index (HLPCHIDX) keyword 18-6

Help Sequencing (HLPSEQ) keyword 18-17

help sublist
definition 18-17

help text
See online help information

help text displayed according to cursor position 17-14

Help Title (HLPRTITLE) keyword 18-6

HELPHelp dialog command B-9

HELPIIDX dialog command B-9

hexadecimal data A-6

hidden field
definition 2-9
using 2-9

hierarchy, InfoSeeker 20-10

high-level language (HLL)
overriding display file attributes in programs 7-1
overriding display file names and attributes in programs 7-3
overriding display file names in programs 7-3
recognizing the I/O requests supported by 3-49
System/36 application compatibility G-1

highlight phrases table A-61

highlighted phrase (HP0 through HP9) tag
overview A-61
use in help module 20-4

highlighting
selection characters A-9

highlighting and fonts 17-33

HLL (high-level language)
overriding display file attributes in programs 7-1
overriding display file names and attributes in programs 7-3
overriding display file names in programs 7-3
recognizing the I/O requests supported by 3-49
System/36 application compatibility G-1

HLPARA (Help Area) keyword 18-4

HLPBDY (Help Boundary) keyword
secondary help 18-18
use 18-17

HLPBCDKEY (Help Command Key) keyword
response indicators, sample source with 18-21
restriction with USRDSPMGT keyword G-10
sample DDS source 18-20
use 18-20

HLPDOC (Help Document) keyword
examples
option indicators, sample source with 18-11
sample DDS source 18-10
specifying the document name 18-9
with HLPBCD and HLPNLGRP keywords 18-11
with option indicators 18-11

HLPXCLD (Help Exclude) keyword 18-6

HLPFULL (Help Full) keyword 18-6

HLPPNLGRP (Help Panel Group) keyword

example

- option indicators, sample source with 18-8
- sample DDS source 18-7

use 18-6

with HLPBCD and HLPDOC keywords 18-8

with option indicators 18-8

HLPBCD (Help Record) keyword

example

- option indicators, sample source with 18-14
- sample DDS source 18-13

secondary help 18-18

with HLPDOC keyword in same file 18-15

with HLPPNLGRP keyword in same file 18-12

with option indicators 18-13

HLPRTN (Help Return) keyword

returning to your program after help 18-21

System/36 application compatibility G-7

HLPSEARCH (Help Search Index) keyword 18-6**HLPSEQ (Help Sequencing) keyword 18-17****HLPSTRT (Help Title) keyword 18-6****HOME (Display Home Menu) dialog command B-10****HOME (Home) keyword 2-12****HP0 through HP9 (highlighted phrase) tag**

overview A-61

use in help module 20-4

hypertext*See also* online help information

definition 20-12

hypertext link

example A-78

hypertext link definition (LINK) tag

conditional expressions

CHKOBJ built-in function A-77

CHKUSRCLS (check user class) built-in function A-78

example, hypertext link A-78

overview A-76

placement in UIM source 20-14

hypertext reference phrase*See also* online help information

definition 20-13

I**I/O feedback area**

common C-6

contents 3-3

definition 3-3

display C-9

I/O operation

acquiring a display station for 3-2

locking keyboard and positioning cursor 3-41

mapping to HLL operations

BASIC statements 3-49

C/400 functions 3-49

CL commands 3-49

I/O operation (continued)

mapping to HLL operations (continued)

COBOL/400 statements 3-49

FORTRAN/400 statements 3-49

RPG/400 operations 3-49

obtaining information about 3-3

releasing an acquired display station from 3-49

requesting

for subfile control record formats 4-11

for subfile record formats 4-9

for subfiles 4-9

I/O request

high-level languages, table of subfile 4-12

supported by high-level languages 3-49

ICF file

DBCS D-5

file entry field attributes 12-1

waiting for data with display file, data queue 12-1

identifier fields for menu displays 21-32**identifier, level 2-6****ideographic characters (IGC)**

formatting

BOTINST (bottom instruction) tag A-10

DATAC (data item choices) tag A-36

PDFLDC (pull-down field choice) tag A-133

TOPINST (top instruction) tag A-154

IGC (ideographic characters)

formatting

BOTINST (bottom instruction) tag A-10

DATAC (data item choices) tag A-36

PDFLDC (pull-down field choice) tag A-133

TOPINST (top instruction) tag A-154

IGCALTTYP (Alternative Data Type) keyword D-5**imbed help (IMHELP) tag**

example, imbedded help A-64

overview A-64

placement in UIM source 20-2

imbedding

nesting source files A-6

imbedding source files

nesting imbeds A-6

imbedding UIM source files A-6**IMHELP (imbed help) tag**

example, imbedded help A-64

overview A-64

placement in UIM source 20-2

UIM source showing panel groups using 20-2

UIM source showing panel groups with help

modules 20-2

IMPORT (import) tag

overview A-65

placement in UIM source 20-3

UIM source showing panel groups using 20-3

improving

productivity with UIM 15-1

system performance with displays 14-1

improving productivity with UIM 15-1

inactive subfile record

definition 4-3

incorrect characters in dialog variable 17-4

incorrect display characters 17-4

incorrect printer characters 17-4

INDARA (Indicator Area) keyword 2-14

index search

See online help information

index search (ISCH) tag

parameter list A-68

placement in UIM source 20-8

index search subtopic (ISCHSUBT) tag

parameter list A-69

placement in UIM source 20-10

index search synonym (ISCHSYN) tag

parameter list A-70

placement in UIM source 20-8

indicator

definition 2-14

option

definition 2-14

for display files 2-14

passing information via 2-14

response

definition 2-12

for display files 2-14

setting off 2-15

setting when data is changed 3-36

types for display files 2-14

Indicator Area (INDARA) keyword 2-14

INFO (information area) tag

overview A-66

print formatting considerations A-67

information area

printed A-67

scrolling 17-13

information area (INFO) tag

overview A-66

print formatting considerations A-67

information area scrolling 17-13

information display

CUA 21-52

description 21-17

example 21-17

instruction lines 21-19

location information 21-18

online help information

DDS considerations 21-44

description 21-43

help areas for 21-43

operating guidelines 21-20

prompt areas 21-18

titles 21-18

information, help

See online help information

information, location

See location information, displays

information, online help

See online help information

InfoSeeker function

See online help information

InfoSeeker hierarchy 20-10

InfoSeeker key (F11) 20-6

initial menu

definition 9-3

Initialize Diskette (INZDKT) command D-9

Initialize Record (INZRCD) keyword 3-35

initializing

list display 17-6

output/input fields 3-29

initializing list 17-6

input data

from the display

how the system reads 3-40

reading 3-33

reading invited 3-31

handling negative numeric 3-39

inviting

from CL programs 3-30

to the display 3-30

keeping 3-36

reading while writing output 3-40

System/36 application compatibility G-2

input field

definition 2-9

displayed characters on DBCS display D-6

erasing 3-23

example, display with output and 2-10

improving performance when sending records

with 14-2

using 2-9

input file

defining 2-24

input not waited for, canceling 3-41

input operation

effect of INZRCD and UNLOCK keywords on 3-36

input-capable field

limitations on number of 3-39

input-only file

defining 2-23

input/output feedback area

common C-6

contents 3-3

definition 2-12, 3-3

display C-9

input/output operation

acquiring a display station for 3-2

files shared in a job 3-51

locking keyboard and positioning cursor 3-41

mapping to HLL operations

BASIC statements 3-49

C/400 functions 3-49

input/output operation *(continued)*

mapping to HLL operations *(continued)*

CL commands 3-49

COBOL/400 statements 3-49

FORTRAN/400 statements 3-49

RPG/400 operations 3-49

obtaining information about 3-3

releasing an acquired display station from 3-49

requesting

for subfile control record formats 4-11

for subfile record formats 4-9

for subfiles 4-9

input/output request

high-level languages, table of subfile 4-12

supported by high-level languages 3-49

inserting

entry from list display 17-7

inserting entry from list 17-7

instruction line

entry displays 21-11

information displays 21-19

list display 21-21

menu displays, single-choice 21-8

interaction

between menu bar and application 6-22

between menu bar and pull-down menu 6-32

interactive response time for list displays 17-9

interpretation of command line 17-16

INVITE (Invite) keyword

system performance considerations 14-3

use 3-30

invite operation

C/400 function for 3-49

CL command for 3-49

COBOL/400 statement for 3-49

definition 3-30

RPG/400 operation for 3-49

system performance considerations 14-3

invited input, reading from the display 3-31

INZDKT (Initialize Diskette) command D-9

INZINP (Initialize Input) keyword

performance considerations 14-3

INZRCD (Initialize Record) keyword

example with UNLOCK keyword 3-36

use 3-35

ISCH (index search) tag

parameter list A-68

placement in UIM source 20-8

ISCHSUBT (index search subtopic) tag

parameter list A-69

placement in UIM source 20-10

ISCHSYN (index search synonym) tag

parameter list A-70

placement in UIM source 20-8

item-specific help 6-30

J

job

close operation for files shared in 3-52

input/output operation for files shared in 3-51

open operation for files shared in 3-51

K

KEEP (Keep) keyword

considerations 11-1

example DDS source 11-3

restriction with USRDSPMGT keyword G-10

sharing file between programs 11-1

System/36 application compatibility G-2

key

Cancel and Exit, using on menus 9-2

CAnn and CFnn, defining 2-12

CFnn (command function), validity

considerations 3-45

command

defining 2-12

validity considerations 3-45

command attention (CAnn) 2-12

command function (CFnn) 2-12

function

defining 2-11

System/36 application compatibility G-7

key assignments, common

See common key assignments

key definition

example A-73

key interaction for menu bars and pull-down menus 6-32

key list (KEYL) tag

example, key list A-74

overview A-74

tags allowed table A-74

key list item (KEYI) tag

example, key definitions A-73

overview A-72

keyboard

locking 3-10

locking during I/O operations 3-41

unlocking while the program is processing

data 3-35

keyboard function

continued-entry field 6-34

KEYI (key list item) tag

example, key definitions A-73

overview A-72

KEYL (key list) tag

example, key list A-74

overview A-74

tags allowed table A-74

KEYSHELP dialog command B-10

keyword, DDS

Alternative Help (ALTHELP) 2-13
ALTHELP (Alternative Help) 2-13
ALTPAGEDWN (Alternative Page Down) 2-13
ALTPAGEUP (Alternative Page Up) 2-13
ALWROL (Allow Roll)
 example 3-16
 use 3-16
ASSUME (Assume)
 example DDS source 11-1, 11-3
 use 11-1
 with DFT keyword 11-1
CAnn (Command Attention) 2-11
CFnn (Command Function) 2-11
CHANGE (Change) 3-36
CHECK (Check)
 AB value 3-37
 description 2-16
 M10 value 3-37
 M11 value 3-37
 ME value 3-37
 MF value 3-37
 VN value 3-37
 VNE value 3-37
CHRID (Character Identifier) keyword 13-2
CLEAR (Clear) 2-11
CLRL (Clear Line) 3-13
 example with *NO value
 example with OVERLAY 3-15
 system performance considerations 14-2
coding, more efficient 3-20
COLOR (Color) 2-18
COMP (Comparison) 3-37
CSRLOC (Cursor Location) 3-28
data, repeatedly entered 3-21
DFT (Default)
 description 3-26
 with ASSUME keyword 11-1
DFTVAL (Default Value) 3-26
Display Attribute (DSPATR)
 adding color to fields with 2-18
 emphasizing fields with 2-17
 PC value 3-28, 4-21
 table of values for 2-17, 2-18
 with ASSUME keyword 11-1
Display Right-to-Left (DSPRL) keyword 2-16
Display Size (DSPSIZ)
 use 2-20
DSPATR (Display Attribute)
 adding to color to fields with 2-18
 emphasizing fields with 2-17
 PC value 3-28, 4-21
 table of color effects 2-18
 table of values for 2-17
 with ASSUME keyword 11-1

keyword, DDS (continued)

DSPMOD (Display Mode)
 description 3-27
 example for subfiles 4-14
 subfile display for *DS3 4-15
 subfile display for *DS4 4-15
DSPRL (Display Right-to-Left) keyword 2-16
DSPSIZ (Display Size)
 specifying to improve performance 14-1
 use 2-20
Edit Code (EDTCDE) 2-19
Edit Word (EDTWRD) 2-19
EDTCDE (Edit Code) 2-19
EDTWRD (Edit Word) 2-19
ERASE (Erase)
 effect on output operation 3-10
 example of effects with OVERLAY 3-10
Erase Input (ERASEINP)
 system performance considerations 14-3
 use 3-23
ERASEINP (Erase Input)
 system performance considerations 14-3
 use 3-23
ERRMSG (Error Message) 8-2
ERRMSGID (Error Message Identifier) 8-2
Error Message (ERRMSG) 8-2
Error Message Identifier (ERRMSGID) 8-2
Error Subfile (ERRSFL)
 description 8-4
 example DDS source 8-4
ERRSFL (Error Subfile)
 description 8-4
 example DDS source 8-4
field
 color (table) 2-18
 emphasizing (table) 2-17
field level 3-24
function keys, defining with 2-11
GETRETAIN (Get Retain) 3-36
H specifications
 See H specifications
HELP (Help)
 enabling Help key 18-2
 function key use 2-12
Help Area (HLPARA) 18-4
Help Boundary (HLPBDY)
 use 18-17
Help Command Key (HLPAMDKEY)
 use 18-20
Help Document (HLPDOC)
 description 18-9
 with option indicators 18-11
Help Exclude (HLPEXCLD) 18-6
Help Full (HLPFULL) 18-6
Help Panel Group (HLPPNLGRP)
 description 18-6
 with option indicators 18-8

keyword, DDS (continued)

Help Record (HLPRCD)
 description 18-12
 with option indicators 18-13
 Help Return (HLPRTN) 18-21
 Help Search Index (HLPCHIDX) 18-6
 Help Sequencing (HLPSEQ) 18-17
 Help Title (HLPTITLE) 18-6
 HLPARA (Help Area) 18-4
 HLPBDY (Help Boundary)
 secondary help 18-18
 use 18-17
 HLPAMDKEY (Help Command Key)
 response indicators, sample source with 18-21
 sample DDS source 18-20
 use 18-20
 HLPDOC (Help Document)
 description 18-9
 option indicators, sample source with 18-11
 sample DDS source 18-10
 with option indicators 18-11
 HLPXCLD (Help Exclude) 18-6
 HLPFULL (Help Full) 18-6
 HLPNLPGRP (Help Panel Group)
 description 18-6
 option indicators, sample source with 18-8
 sample DDS source 18-7
 with option indicators 18-8
 HLPRCD (Help Record)
 description 18-12
 option indicators, sample source with 18-14
 sample DDS source 18-13
 secondary help 18-18
 with option indicators 18-13
 HLPRTN (Help Return) 18-21
 HLPCHIDX (Help Search Index) 18-6
 HLPSEQ (Help Sequencing) 18-17
 HLPTITLE (Help Title) 18-6
 HOME (Home) 2-12
 INDARA (Indicator Area) 2-14
 Indicator Area (INDARA) 2-14
 Initialize Record (INZRCD)
 use 3-35
 INVITE (Invite)
 description 3-30
 system performance considerations 14-3
 INZINP (Initialize Input), system performance consid-
 erations 14-3
 INZRCD (Initialize Record)
 example with UNLOCK keyword 3-36
 use 3-35
 KEEP (Keep)
 description 11-1
 example DDS source 11-3
 keywords ignored if display modes are
 changed 3-28

keyword, DDS (continued)

LOCK (Lock) 3-42
 MDTOFF (Modified Data Tag Off) 3-23
 MSGALARM (Message Alarm) 8-7
 MSGID (Message Identifier) 8-3
 OVERLAY (Overlay)
 description 3-10
 effect on output operation 3-10
 example of effects with ERASE 3-10
 example with CLRL 3-15
 system performance considerations 14-3
 Override Attribute (OVRATR)
 system performance considerations 14-2
 use 3-18
 Override Data (OVRDTA) 3-20
 system performance considerations 14-2
 OVRATR (Override Attribute)
 system performance considerations 14-2
 use 3-18
 OVRDTA (Override Data) 3-20
 system performance considerations 14-2
 Page Down (PAGEDOWN) 2-12
 Page Up (PAGEUP)
 defining 2-12
 PAGEDOWN (Page Down) 2-12
 PAGEUP (Page Up) 2-12
 PASSRCD (Passed Record) 11-3
 PRINT (Print)
 enabling 2-21
 for function key 2-12
 results available (table) 2-21
 Put with Explicit Override (PUTOVR)
 description 3-18
 system performance considerations 14-2
 Put-Retain (PUTRETAIN)
 description 3-23
 PUTOVR (Put with Explicit Override)
 description 3-18
 example 3-18
 system performance considerations 14-2
 PUTRETAIN (Put-Retain)
 description 3-23
 for record level 3-24
 RANGE (Range) 3-37
 Return Cursor Location (RTNCSRLOC) 3-29
 Roll Down (ROLLDOWN)
 defining 2-12
 response indicators for 2-15
 Roll Up (ROLLUP)
 example with SFLSIZ and SFLPAG 4-16
 for function key 2-12
 improving subfile performance 14-1
 response indicators for 2-15
 ROLLDOWN (Roll Down)
 defining 2-12
 response indicators for 2-15

keyword, DDS (continued)

ROLLUP (Roll Up)
 example with SFLSIZ and SFLPAG 4-16
 for function key 2-12
 improving subfile performance 14-1
 response indicators for 2-15

RTNCSRLOC (Return Cursor Location) 3-29

Set Off (SETOF or SETOFF) 2-15

SETOF or SETOFF (Set Off) 2-15

SFL (Subfile) 4-3

SFLCLR (Subfile Clear) 4-4

SFLCSRNRN (Subfile Cursor Relative Record Number) 3-29

SFLCTL (Subfile Control) 4-3

SFLDLT (Subfile Delete) 4-4

SFLDROP (Subfile Drop) 4-4

SFLDSP (Subfile Display) 4-3

SFLDSPCTL (Subfile Display Control) 4-4

SFLEND (Subfile End) 4-4

SFLENTER (Subfile Enter) 4-4

SFLFOLD (Subfile Fold) 4-4

SFLINZ (Subfile Initialize) 4-4

SFLLIN (Subfile Line) 4-4

SFLMODE (Subfile Mode) 3-29

SFLMSG (Subfile Message)
 defining 4-4
 description 4-4
 displaying on message line when subfile control record written 8-2

SFLMSGID (Subfile Message Identifier)
 defining 4-4
 description 4-4
 displaying on message line when subfile control record written 8-2
 sample DDS 8-5

SFLMSGKEY (Subfile Message Key)
 description 4-4
 displaying messages from a program message queue 8-4

SFLMSGRCRD (Subfile Message Record)
 description 4-4
 displaying messages from a program message queue 8-4

SFLNXTCHG (Subfile Next Changed)
 description 4-4
 example 4-18

SFLPAG (Subfile Page)
 example with ROLLUP and SFLSIZ 4-16
 use in subfile control record format 4-3

SFLPGMQ (Subfile Program Message Queue)
 description 4-4
 displaying messages from a program message queue 8-4

SFLRCNBR (Subfile Record Number)
 description 4-4
 improving subfile performance 14-1

keyword, DDS (continued)

SFLRNA (Subfile Records Not Active) 4-4

SFLROLVAL (Subfile Roll Value) 4-4

SFLSIZ (Subfile Size)
 example with ROLLUP and SFLPAG 4-16
 use in subfile control record format 4-3

SLNO (Starting Line Number)
 example with *VAR value 3-12
 use 3-11

Starting Line Number (SLNO)
 example with *VAR value 3-12
 use 3-11

Subfile Clear (SFLCLR) 4-4

Subfile Control (SFLCTL) 4-3

Subfile Cursor Relative Record Number (SFLCSRNRN) 3-29

Subfile Delete (SFLDLT) 4-4

Subfile Display (SFLDSP) 4-3

Subfile Display Control (SFLDSPCTL) 4-4

Subfile Drop (SFLDROP) 4-4

Subfile End (SFLEND) 4-4

Subfile Enter (SFLENTER) 4-4

Subfile Fold (SFLFOLD) 4-4

Subfile Initialize (SFLINZ) 4-4

Subfile Line (SFLLIN) 4-4

Subfile Message (SFLMSG)
 defining 4-4
 description 4-4
 displaying on message line when subfile control record written 8-2

Subfile Message Identifier (SFLMSGID)
 defining 4-4
 description 4-4
 displaying on message line when subfile control record written 8-2
 sample DDS 8-5

Subfile Message Key (SFLMSGKEY)
 description 4-4
 displaying messages from a program message queue 8-4

Subfile Message Record (SFLMSGRCRD)
 description 4-4
 displaying messages from a program message queue 8-4

Subfile Mode (SFLMODE) 3-29

Subfile Next Changed (SFLNXTCHG)
 description 4-4
 example 4-18

Subfile Page (SFLPAG)
 example with ROLLUP and SFLSIZ 4-16
 use in subfile control record format 4-3

Subfile Program Message Queue (SFLPGMQ)
 description 4-4
 displaying messages from a program message queue 8-4

Subfile Record Number (SFLRCNBR)
 description 4-4

keyword, DDS (continued)

- Subfile Record Number (SFLRCDNBR) (continued)
 - improving subfile performance 14-1
- Subfile Records Not Active (SFLRNA) 4-4
- Subfile Roll Value (SFLROLVAL) 4-4
- Subfile Size (SFLSIZ)
 - example with ROLLUP and SFLPAG 4-16
 - use in subfile control record format 4-3
- UNLOCK (Unlock)
 - effects on input operation 3-36
 - example with INZRCD keyword 3-36
 - unlocking while program is processing data 3-35
- USRDFN (User-Defined) 10-1
- validity-checking 3-37
- VALUES (Values) 3-37

L

layout

- title lines table A-140

layout and positions summary table A-103, A-104

left-to-right formatting on a left-to-right panel

- example A-147

left-to-right formatting on a right-to-left panel

- example A-147

level identifier

- changes in 2-6
- definition of 2-6
- determining 2-6

library

- QUSRSYS library 13-3
- QUSRTOOL
 - definition 1-6
 - display examples 21-1
 - panel groups, using word processing functions when creating 18-2

limitations

- panel formatter 17-21

line

- clearing a specified number of 3-13
- rolling data between 3-16

line, instruction

- See instruction line

line, options 21-21

LINES (unformatted lines) tag

- example, unformatted lines A-75
- overview A-75
- use in help module 20-5

LINK (hypertext link) tag

- conditional expressions
 - CHKOBJ built-in function A-77
 - CHKUSRCLS (check user class) built-in function A-78
- example, hypertext link A-78
- overview A-76
- placement in UIM source 20-14

LINK (hypertext link) tag (continued)

- UIM source showing panel groups using 20-14

list

- displaying 17-7
- initializing 17-6
- inserting entry from 17-7
- key A-74
- managing 17-6
- ordered A-116
- parameter A-126
- part A-105
- removing entry from 17-7
- simple A-149
- unordered A-157
- updating 17-7

LIST (list area) tag

- example
 - dynamic list column heading formatting A-86
 - list area A-84
 - list area with list group columns A-85
 - list area with three layout columns A-85
- overview A-80
- print formatting considerations A-83
- tags allowed table A-81

list action (LISTACT) tag

- example, list actions A-93
- overview A-88
- recommended conventions A-92
- required conventions A-92

list area

- example
 - with list group columns A-85
 - with three layout columns A-85
- help 19-3
- printed A-83
- scrolling 17-13

list area (LIST) tag

- example
 - dynamic list column heading formatting A-86
 - list area A-84
 - list area with list group columns A-85
 - list area with three layout columns A-85
- overview A-80
- print formatting considerations A-83
- tags allowed table A-81

list area scrolling 17-13

list column (LISTCOL) tag

- formatting considerations A-97
- overview A-94

list column group (LISTGRP) tag

- overview A-101

list defining in UIM

list definition (LISTDEF) tag

- emphasis values table A-99
- overview A-98

list display

- changing list control field 21-27
- column headings 21-22
- description 21-20
- error condition rules 21-30
- example
 - CUA 21-52
 - extended action entry 21-20
- extended action entry 21-23
- format in an empty situation 21-31
- instruction line 21-21
- list entries on 17-8
- list fields 21-23
- list format, empty list 21-31
- list one selection item 21-31
- online help information
 - DDS considerations 21-45
 - description 21-44
 - help areas for 21-44
 - types 21-44
- operating
 - controlling entry field 21-25
 - extended action entry 21-25
 - guidelines 21-24
 - lists when options are specified 21-27
- options line 21-21
- paging location information 21-23
- positioning
 - lists 21-26
 - lowercase names in a list 21-27
 - rules for cursor 21-29
- prompt areas 21-21
- response time for 17-9
- rules, error condition 21-30
- titles 21-20

list entries on a list display 17-8

list entry handle 17-7

list entry pointer 17-8

list fields on list displays 21-23

list panel

- application programming 16-26
- creating 16-13
- source 16-18

list part (LP) tag

- example, list part A-105
- overview A-105
- use in help module 20-5

list view (LISTVIEW) tag

- layout and positions summary table A-103, A-104
- overview A-103

LISTACT (list action) tag

- example, list actions A-93
- overview A-88
- recommended conventions A-92
- required conventions A-92

LISTCOL (list column) tag

- formatting considerations A-97
- overview A-94

LISTDEF (list definition) tag

- emphasis values table A-99
- overview A-98

LISTGRP (list column group) tag

- overview A-101

LISTVIEW (list view) tag

- layout and positions summary table A-103, A-104
- overview A-103

literal, graphic A-6

location information, displays 21-18

location of window 5-4, 5-6

LOCK (Lock) keyword 3-42

locked display file 3-1

locking keyboard and positioning cursor 3-41

LP (list part) tag

- example, list part A-105
- overview A-105
- use in help module 20-5

M

Main Menu display 9-2

major/minor return code

major return code definitions

- 00 8-11
- 02 8-11
- 03 8-11
- 04 8-11
- 08 8-11
- 11 8-11
- 34 8-11
- 80 8-11
- 81 8-11
- 82 8-11
- 83 8-11

recovering from errors

- completion with exceptions 8-12
- device or session error on open or acquire operation 8-14
- normal completion 8-11
- permanent device or session error on I/O operation 8-13
- permanent system or file errors 8-13
- recoverable device or session errors on I/O operation 8-14

understanding 8-10

managing

panel functions 17-11

managing list 17-6

managing panel functions 17-11

markup separator A-1

MBAR (menu bar) tag

- example, menu bar A-106

MBAR (menu bar) tag *(continued)*

- overview A-106
- tags allowed table A-106

MBARC (menu bar choice) tag

- overview A-108
- tags allowed table A-108

MDT (modified data tag)

- character translation 13-2
- definition 2-10
- resetting 3-23
- with ASSUME keyword 11-1

MDTOFF (Modified Data Tag Off) keyword 3-23**member**

- source
- definition 1-2

MENU (menu area) tag

- example
 - menu area with groups A-110
 - simple menu area A-110
- tags allowed table A-109

menu area

- help 19-4
- scrolling 17-13
- with groups
 - example A-110

menu area (MENU) tag

- example
 - menu area with groups A-110
 - simple menu area A-110
- tags allowed table A-109

menu bar

- area help 19-11
- creating 6-6
- definition 6-6
- example 6-6, 6-41
- interaction with application 6-22
- interaction with pull-down menu 6-32
- using 17-24

menu bar (MBAR) tag

- example, menu bar A-106
- overview A-106
- tags allowed table A-106

menu bar choice (MBARC) tag

- overview A-108
- tags allowed table A-108

Menu Bar Cursor Action (ACTIONS) dialog**command** B-4**menu bar panel**

- application programming 16-64
- creating 16-51
- source 16-54

menu definition 16-2**MENU dialog command** B-10**menu display**

- See also* application display
- Cancel key, using on 9-2

menu display *(continued)*

- changing attributes 9-16
- choosing which to display at sign-on time 9-3
- creating UIM 16-6
- CUA 21-49
- deleting 9-17
- description 21-7
- determining the previous menu 9-1
- display file
 - building 9-7
 - creating for 9-9
 - creating menu object for 9-9
 - creating message file for 9-9
 - DDS considerations 9-4
 - DDS, specifying 9-7
 - defining 9-4
 - definition 9-1
 - help for 9-4
 - menu and help information, describing 9-7
 - message file, adding messages to 9-9
 - message file, describing menu actions in 9-5
 - naming help formats for 9-6
 - parts of 9-4

- displaying attributes 9-16

example

- display file menu 9-8
- message file, adding messages to 9-9
- message file, describing menu actions in 9-5
- naming help formats in message file 9-6
- program menu 9-11
- program menu, CL source for 9-12
- RTNPNT(*NO) for program menu, CL source for 9-14
- sample single-choice 21-7
- using options and GO command 9-2

- Exit key, using on 9-2

- function key area 21-7

- identifier fields 21-32

- initial 9-3

- instruction line 21-8

- menu displays, single-choice 21-8, 21-9

- menu selection entry field 21-9

- menu stack 9-1

- naming conflicts, avoiding

 - changing command default after command duplication 9-16

 - generic menu specifications 9-16

 - naming, deciding how to 9-15

 - placement in library list 9-16

 - specifying library 9-16

 - ways 9-15

- online help information

 - DDS considerations 21-42

 - description 21-41

 - help areas for 21-41

 - types 21-41

menu display *(continued)*

- operating guidelines 21-9
- optional 21-32
- options 21-8
- program
 - building 9-11
 - creating CL program for 9-12
 - creating display file 9-12
 - creating menu for 9-13
 - defining 9-10
 - definition 9-1
 - describing 9-11
 - entering CL source for 9-12
 - exiting without returning to previous menu 9-13
 - passing parameters for 9-10
- returning to after running the GO command 9-1
- selection entry field 21-9
- system, running 9-1
- user interface manager (UIM) 16-6
- user-defined
 - running 9-1
 - types 9-1

menu group (MENUGRP) tag

- tags allowed table A-112

menu group (MNUGRP) tag

- overview A-112

menu item (MENU) tag

- overview A-113

MENU object type 9-1

menu object, defining

- *DSPF menu 9-7
- *UIM menu 16-6

menu-bar choice

- defining 6-6
- translation of 6-7

menu-bar choice help

- example 6-29

Menu-Bar Display (MNUBARDSP) keyword

- application record 6-22, 6-41
- menu-bar record 6-24, 6-43

menu-bar help list

- example 6-31

menu-bar record

- MNUBARDSP 6-43

menu-bar separator

- creating 6-6
- defining 6-6
- definition 6-6

menu-bar switch key

- defining 6-17
- definition 6-17

MENUGRP (menu group) tag

- overview A-112
- tags allowed table A-112

MENU (menu item) tag

- overview A-113

message

- automatically handling error 8-7
- available functions for display files 8-1
- CPF4001-40FF 8-10
- CPF4101-43FF 8-10
- CPF4401-44FF 8-10
- CPF4501-46FF 8-10
- CPF4701-48FF 8-10
- CPF4901-49FF 8-10
- CPF5001-50FF 8-10
- CPF5101-53FF 8-10
- CPF5501-56FF 8-10
- creating and displaying 8-1
- description 21-46
- displaying
 - in field 8-3
 - in program message queue 8-4
 - message line for 8-3
 - on message line 8-2
 - on message line when subfile control record written 8-2
 - priorities for 8-3
 - through subfile 8-4
- error
 - displaying from subfiles 4-19
- examples
 - ERRSFL keyword 8-4
 - SFLMSGID keyword 8-5
- guidelines 21-46
- line relationship, CUA 21-49
- reasons for 8-1
- sounding alarm for 8-7
- system
 - alert 8-9
 - analyzing 8-8
 - detecting 8-8
 - diagnostic 8-8
 - escape 8-8
 - file status code 8-8
 - message queues 8-8
 - notifying 8-8
 - permanent 8-9
 - reporting 8-8
 - status 8-8
- System/36 application compatibility G-4
- understanding 8-9
- window 5-5

Message Alarm (MSGALARM) keyword 8-7

message description 2-15

message field to display message on message line 8-3

message file

- adding messages to 9-9
- creating 9-9
- describing menu action in 9-5

message line

- definition 2-10
- scrolling 17-12
- use 2-10

Message Location (MSGLOC) keyword 5-5

message subfile 4-20

message text symbol A-5

message, monitor

See message

messages displayed on message line priorities 8-3

mnemonic

- coding, not valid 6-19
- defining 6-19
- definition 6-1
- valid coding for 6-19

MNUBARDSP (Menu-Bar Display) keyword

- application record 6-22, 6-41
- menu-bar record 6-24, 6-43

mode, display

- changing 4-14
- definition 4-14
- displaying subfiles horizontally with 4-14

modified data tag (MDT)

- character translation 13-2
- definition 2-10
- resetting 3-23
- with ASSUME keyword 11-1

Modified Data Tag Off (MDTOFF) keyword 3-23

monitor message 8-9

MOREKEYS (Display More Function Keys) dialog command B-10

Move Object (MOV OBJ) command D-15

Move to Top (MOVETOP) dialog command B-11

MOVETOP (Move to Top) dialog command B-11

moving

- window 5-9

moving cursor

- using cursor keys 6-39
- using tab key 6-39

MOV OBJ (Move Object) command D-15

MSG (Display Message) dialog command B-11

MSGALARM (Message Alarm) keyword 8-7

MSGID (Message Identifier) keyword 8-3

MSGLOC (Message Location) keyword 5-5

multiple panel foldup when EXIT requested 17-21

multiple-choice selection field

- colors and display attributes 6-21
- creating 6-10
- definition 6-9
- example 6-9

multiple-selection field

- example A-51

N

name syntax

- alphabetic conversion A-4
- object name
 - restrictions A-4
- on HELP tag
 - restrictions A-4

national language considerations and DBCS 20-11

national language translation

- sentence-ending characters A-2

negative numeric input data, handling 3-39

nesting

- imbeds
 - source files A-6

No CCSID (NOCCSID) keyword 13-2

NOCCSID (No CCSID) keyword 13-2

node (hypertext), definition

See online help information, hypertext

note (NT) tag

- example, using a note A-115
- overview A-115
- tags allowed table A-115
- use in help module 20-4

NT (note) tag

- example, using a note A-115
- overview A-115
- tags allowed table A-115
- use in help module 20-4

numeric input data, handling negative 3-39

numeric value

- display form A-22
 - binary A-22
- example values table A-22

O

object

- creating 16-3
- definition 2-1
- enhancements to object management D-15
- panel group A-3

object name

- name syntax A-4
- restrictions A-4

ODP (open data path)

- definition 3-50
- for improving system performance 14-2
- sharing for same job 14-2

office document

See document, office

OfficeVision/400* document

See document, office

OL (ordered list) tag

- example, ordered list A-117
- overview A-116

OL (ordered list) tag *(continued)*

tags allowed table A-116

use in help module 20-5

online help information

adding to a display 18-1

contextual help 18-3

creating a sample display with 1-1

description 21-41

documents, office

comparing with panel groups and records 18-2

creating for help 20-17

help, defining for 20-17

help, specifying for 18-9

HLPDOC keyword 18-10

HLPDOC keyword with option indicators 18-11

option indicators, specifying with 18-11

panel groups and records in same file,
with 18-11

viewing without Help key 20-18

enabling Help key 18-2

entry displays

DDS considerations 21-43

description 21-42

help areas for 21-42

types 21-42

example

building with display file 1-1

command help 20-15

display showing help areas 18-4

HLPCMDKEY keyword 18-20

HLPCMDKEY keyword with response
indicators 18-21

HLPDOC keyword 18-10

HLPDOC keyword with option indicators 18-11

HLPPNLGRP keyword 18-7

HLPPNLGRP keyword with option
indicators 18-8

HLPRCD keyword 18-13

HLPRCD keyword with option indicators 18-14

imbedded help modules in panel group 20-2

imported help modules 20-3

ISCH tag 20-8

ISCHSYN tag 20-8

LINK tag 20-14

panel groups with help modules 20-2

secondary help 18-18

exiting, System/36 application compatibility G-8

extended help 18-3

H specifications

definition 18-4

entering in DDS source 18-4

order in DDS source 18-4

help areas

DDS keywords for 18-4

defining 18-3

office documents, specifying for 18-9

panel groups, specifying 18-6

online help information *(continued)*

help areas *(continued)*

record 18-4

records, specifying for 18-12

required DDS source 18-3

Help key

enabling 18-2

returning control to program after pressing 18-20

returning control to program without
pressing 18-21

help text displayed according to cursor

position 17-14

hypertext

creating links 20-13

definition 20-12

designing links 20-13

reference phrase, definition 20-13

index search function

See InfoSeeker function

information display

DDS considerations 21-44

description 21-43

help areas for 21-43

InfoSeeker function

deciding topics 20-8

function 20-6

root words, choosing for topic 20-9

root words, defining 20-8

root words, including as synonyms 20-8

synonyms for root words, designating 20-8

synonyms, choosing for topic 20-9

topics, defining 20-8

UIM tags for 20-6

list display

DDS considerations 21-45

description 21-44

help areas for 21-44

menu display

DDS considerations 21-42

help areas for 21-41

types 21-41

overview 19-2

panel groups

adding entries to search index 20-16

command help, assigning 20-15

comparing with documents and records 18-2

creating 20-14

creating hypertext links 20-13

creating search index 20-15

DDS functions for 18-6

deleting 20-14

deleting search index 20-16

designing hypertext links 20-13

documents and records in same file with 18-8

emphasizing and formatting text in help

modules 20-4

entering UIM source for 20-1

online help information (continued)

panel groups (continued)

- full-screen help, indicating 18-6
 - headings in help modules, adding 20-4
 - help modules, linking 20-12
 - help modules, using more than once 20-2
 - help, specifying for 18-6
 - highlighting text in help modules 20-4
 - HLPPNLGRP keyword 18-7
 - HLPPNLGRP keyword with option indicators 18-8
 - hypertext 20-12
 - hypertext reference phrase 20-13
 - InfoSeeker function 20-6
 - InfoSeeker function, adding UIM tags for 20-6
 - InfoSeeker topics, deciding 20-8
 - InfoSeeker, enabling 18-6
 - making lists in help modules 20-5
 - name of help screen, defining 18-6
 - option indicators, specifying with 18-8
 - organizing with help modules 20-2
 - paragraphs and notes, defining in help modules 20-4
 - programming keywords and variables, identifying in help modules 20-5
 - purpose of UIM tags 20-1
 - records and documents in same file with 18-8
 - removing entries from search index 20-16
 - root words, choosing for InfoSeeker topic 20-9
 - root words, defining 20-8
 - root words, including as InfoSeeker synonyms 20-8
 - secondary help, excluding as 18-6
 - structured text in help modules, indicating 20-5
 - synonyms for root words, designating 20-8
 - synonyms, choosing for InfoSeeker topic 20-9
 - topics, defining 20-8
 - uses for 20-1
 - using a help module contained in different 20-3
- record, DDS
- comparing with panel groups and documents 18-2
 - entering source 18-14
 - help boundaries 18-17
 - help group 18-17
 - help list 18-16
 - help sublist 18-17
 - help, defining for 20-18
 - help, specifying for 18-12
 - HLPCMDKEY keyword 18-20
 - HLPCMDKEY keyword with response indicators 18-21
 - HLPRCD keyword 18-13
 - HLPRCD keyword with option indicators 18-14
 - option indicators, specifying with 18-13
 - paging between help displays 18-16
 - paging through H specifications 18-16

online help information (continued)

record, DDS (continued)

- primary help 18-16
- restrictions on 18-15
- restrictions on secondary help 18-19
- secondary help 18-16, 18-18
- secondary help, displaying 18-17
- secondary, determining the sequence of 18-17
- with documents in same file 18-15
- with panel groups in same file 18-12
- returning control to program after pressing Help key 18-20
- returning control to program without pressing Help key 18-21

open data path (ODP)

- definition 3-50
- for improving system performance 14-2
- sharing for same job 14-2

open feedback area

- contents 3-3
- definition 3-3
- device definition list C-4
- individual descriptions C-1

open operation

- BASIC statement for 3-49
- C/400 function for 3-49
- COBOL/400 statement for 3-49
- definition 3-2
- file resource allocation for 3-1
- files shared in job 3-51
- FORTTRAN/400 statement for 3-49
- obtaining information about 3-3
- RPG/400 operation for 3-49

opening

- UIM application 17-1

operating guideline

- entry displays 21-16
- information displays 21-20
- list display
 - See list display
- menu displays, single choice 21-9

operator

- conditional A-25
- relational A-11

option indicator

- example
 - HLPDOC keyword with option indicators 18-11
 - HLPPNLGRP keyword with option indicators 18-8
 - HLPRCD keyword with option indicators 18-14
 - MNUBARHC (Menu Bar Choice) keyword 6-7
 - secondary help 18-18
- office documents, defining for help with 18-11
- panel groups, defining with 18-8
- records, defining with 18-13
- removing from record area 2-14

option line (OPTLINE) tag

overview A-118

options line, list displays 21-21**OPTLINE (option line) tag**

overview A-118

ordered list (OL) tag

example, ordered list A-117

overview A-116

tags allowed table A-116

use in help module 20-5

organization

panel outline A-4

UIM menu outline A-4

outline, panel

organization A-4

UIM menu outline A-4

outline, UIM menu

organization A-4

output data

writing and reading input at same time 3-40

writing to display 3-5

output field

definition 2-9

editing 2-18

examples

displayed in response to request, display with
input and 2-10

using 2-9

output file

defining 2-24

output operation

effect of OVERLAY and ERASE on 3-10

positioning cursor after 3-28

returning cursor position to application 3-29

output-only file, defining 2-23**output/input field**

definition 2-9

erasing 3-23

using 2-9

OVERLAY (Overlay) keyword

description 3-10

effect on help-list updating 18-16

erasing records 3-10

example

differences between CLRL and 3-15

examples

with ERASE keyword 3-10

system performance considerations 14-3

System/36 application compatibility G-2

override

applying when compiling program 7-4

attributes 3-18

CL programs

included in 7-1

QCMDEXC, use of 7-1

commands that ignore or restrict 7-9

override (continued)

Delete Override (DLTOVR) command 7-5

deleting 7-5

determining whether or not to use 7-1

different file types 7-6

display file attributes in HLL programs 7-1

display file names and attributes in HLL
programs 7-3

display file names in HLL programs 7-3

Display Override (DSPOVR) command 7-6

displaying 7-6

effect on other jobs 7-1

entering 7-1

examples

applying when compiling program 7-5

attribute of display file 7-1

different display file 7-3

different display file and attributes 7-4

file redirection

definition 7-6

different file types 7-6

level checking (LVLCHK) 7-6

same file types 7-6

table of defaults for combinations 7-7

valid for input and output 7-7

Override with Display File (OVRDSPF) command

file attributes 7-1

file names 7-3

file names and attributes 7-3

performance considerations 14-2

properties of 7-1

same file types 7-6

when in effect 7-1

when to apply 7-1

Override Attribute (OVRATR) keyword

system performance considerations 14-2

use 3-18

Override Data (OVRDTA) keyword

description 3-20

system performance considerations 14-2

Override with Display File (OVRDSPF) command

compared to CHGDSPF 2-2

file attributes 7-1

file names 7-3

file names and attributes 7-3

Override with Printer File (OVRPRTF)

command D-5

overriding and sharing printer file 17-34**OVRATR (Override Attribute) keyword**

system performance considerations 14-2

use 3-18

OVRDSPF (Override with Display File) command

compared to CHGDSPF 2-2

file attributes 7-1

file names 7-3

file names and attributes 7-3

OVRDSPF (Override with Display File) command

(continued)

indicating DBCS files D-5

OVRDTA (Override Data) keyword

description 3-20

system performance considerations 14-2

OVRPRTF (Override with Printer File)

command D-5

P

P (paragraph) tag

example, paragraph tag A-119

overview A-119

placement in UIM source 20-2

use in help module 20-4

page 420 for code page conversion A-19

page 424 for code page conversion A-19

Page Down (PAGEDOWN) keyword

for function key 2-12

specifying alternative 2-13

page eject during printing 17-34

Page Up (PAGEUP) keyword

for function key 2-12

specifying alternative 2-13

page, code

See code page

PAGEDOWN (Page Down) keyword

for function key 2-12

specifying alternative 2-13

PAGEDOWN dialog command B-12

PAGEUP (Page Up) keyword

for function key 2-12

specifying alternative 2-13

PAGEUP dialog command B-12

paging

help displays, DDS records 18-16

location information, list displays 21-23

panel

areas A-2

definition 16-2, A-2

group object A-2

help A-2

organization A-2

outline A-2

UIM menu outline A-2

PANEL (display panel) tag

example, panel definition A-124

overview A-120

tags allowed table A-120

panel contents definition 17-19

panel formatter limitations 17-21

panel formatting

application control 17-20

concepts 17-19

definition 17-19

panel group

See also tag, UIM

adding UIM tags for InfoSeeker function 20-6

command help, assigning 20-15

comparing with documents and records 18-2

creating 20-14

definition 1-1, 16-2

deleting 20-14

entering UIM source for 20-1

examples

command help 20-15

help modules 20-2

HLPPNLGRP keyword 18-7

HLPPNLGRP keyword with option

indicators 18-8

imbedded help modules 20-2

imported help modules 20-3

ISCH tag 20-8

ISCHSYN tag 20-8

LINK tag 20-14

heading, adding in help modules 20-4

help modules

emphasizing and formatting text 20-4

highlighting text 20-4

hypertext 20-12

linking 20-12

using more than once 20-2

using ones contained in different panel

group 20-3

help, specifying for 18-6

hypertext, definition 20-12

InfoSeeker function

function 20-6

root words, choosing for topic 20-9

root words, including as synonyms 20-8

synonyms for root words, designating 20-8

synonyms, choosing for topic 20-9

topics, deciding 20-8

making lists in help modules 20-5

organizing with help modules 20-2

paragraphs and notes, defining in help

modules 20-4

programming keywords and variables,

identifying 20-5

search index

adding entries to 20-16

creating 20-15

deleting 20-16

removing entries from a search index 20-16

structured text in help modules, indicating 20-5

topics, defining 20-8

uses for 20-1

panel group (PNLGRP) tag

overview A-136

placement in UIM source 20-2

tags allowed table A-136

panel group definition language

- imbedding source files A-6
- markup/content separator A-1
- national language translation
 - sentence-ending characters A-2
- overview A-2

panel group element 16-3**panel group object**

- creating 16-13
- definition A-3

panel list foldup 17-23**panel markup tag**

- See also* tag
- definition 20-4

paragraph (P) tag

- example, paragraph tag A-119
- overview A-119
- placement in UIM source 20-2
- use in help module 20-4

paragraph continuation (PC) tag

- example, paragraph continuation A-128
- overview A-128
- use in help module 20-4

parameter

- data queue (DTAQ) 12-1
- DTAQ (data queue) 12-1
- passed for program menus 9-10
- restore display (RSTDSP)
 - example 3-43
- return point (RTNPNT) parameter
 - for display file menus 9-1
 - for program menus 9-1
- RSTDSP (restore display)
 - example 3-43
- RTNPNT (return point) parameter
 - for display file menus 9-1
 - for program menus 9-1, 9-13
- SHARE (share) 14-2

parameter list (PARML) tag

- example, parameter list A-127
- overview A-126
- tags allowed table A-126
- use in help module 20-5

PARML (parameter list) tag

- example, parameter list A-127
- overview A-126
- tags allowed table A-126
- use in help module 20-5

Passed Record (PASSRCD) keyword 11-3**passing data**

- between routing steps 11-3
- in the same routing step 11-1

PASSRCD (Passed Record) keyword

- example DDS source 11-3
- use 11-3

PC (paragraph continuation) tag

- example, paragraph continuation A-128
- overview A-128
- use in help module 20-4

PDACCEL (pull-down accelerator) tag

- overview A-129

PDFLD (pull-down field) tag

- overview A-130
- tags allowed table A-130

PDFLDC (pull-down field choice) tag

- overview A-131
- recommended conventions A-133
- required conventions A-133

PDM (programming development manager)

- definition 1-2

performance

- command attention keys versus command function keys 14-3
- DDS windows 14-4
- deferring write operation 14-1
- designating primary screen size 14-1
- ERASEINP keyword, considerations with 14-3
- invite operation 14-3
- INZINP keyword, considerations with 14-3
- overlapping but not deleting records 14-2
- OVERLAY keyword, considerations with 14-3
- override commands 14-2
- PUTOVR, OVRDTA and OVRATR keywords, considerations with 14-2
- restoring display 14-3
- RSTDSP (restore display)
 - keywords that require 14-3
 - system performance considerations 14-3
- sending records with input fields 14-2
- sharing open data paths for same job 14-2
- subfile use 14-1
- ways to improve using displays 14-1
- window application 5-11

period (.) symbol A-5**PK (programming keyword) tag**

- overview A-135
- use in help module 20-5

placement of window 5-4, 5-6**PNLGRP (panel group) tag**

- overview A-136
- placement in UIM source 20-2
- tags allowed table A-136
- UIM source showing panel groups with help modules 20-2

pop-up window

- adding 17-28
- adding over another panel 17-24
- adding to display stack 17-28
- help information A-59
- removing 17-28

- pop-up window and pull-down menu
 - differences 17-25
- position of window 5-4, 5-6
- possible choices information, entry displays 21-15
- primary help, definition 18-16
- PRINT (Print Display) dialog command** B-12
- PRINT (Print) keyword**
 - enabling 2-21
 - for function key 2-12
 - results available (table) 2-21
- Print Display (PRINT) dialog command** B-12
- print head panel (PRTHEAD) tag**
 - example, print title lines A-142
 - layout of title lines tables A-141, A-142
 - overview A-139
 - tags allowed table A-139
- print head panel printing** 17-32
- Print key**
 - enabling 2-21
 - results available (table) 2-21
- print panel (PRTPNL) tag**
 - overview A-143
 - tags allowed table A-143
- print panel printing** 17-32
- print title lines**
 - example A-142
- print trailer message (PRTRAIL) tag**
 - example, trailer message A-145
 - overview A-145
- printer characters, incorrect** 17-4
- printer file sharing and overriding** 17-34
- printer files in DBCS** D-5
- PRINTER parameter** 2-22
- printing**
 - concepts 17-30
 - DBCS conversion dictionary D-19
 - display 2-21
 - double-byte character set (DBCS)
 - considerations 17-34
 - information area A-67
 - introduction 17-30
 - list area A-83
 - page eject 17-34
 - print head panel 17-32
 - print panel 17-32
 - trailer 17-33
- priorities for displaying messages on message line** 8-3
- problem analysis**
 - damaged DBCS devices D-10
- Problem Handling menu** 9-2
- productivity gains with UIM** 15-1
- productivity improvements with UIM** 15-1
- program menu**
 - See also* menu display
 - definition 9-1
- program menu** (*continued*)
 - return code values, table of 9-10
- program-described data**
 - definition 2-3
 - description 2-4
 - example for assigning display space 2-22
 - program versus system view 2-4
 - using 2-22
- program-to-system field**
 - understanding how to use 2-10
 - with DSPATR keyword 2-17
- program, CL**
 - See* CL programs
- program, IBM-supplied**
 - QRCVDTAQ (receive data queue) 12-1
 - QSNDDTAQ (send data queue) 12-1
- programming development manager (PDM)**
 - definition 1-2
- programming example**
 - window use 5-14
- programming keyword (PK) tag**
 - overview A-135
 - use in help module 20-5
- Programming menu** 9-2
- programming variable (PV) tag**
 - overview A-146
 - use in help module 20-5
- prolog area**
 - defining 17-33
- prolog section**
 - panel group A-4
- prompt area**
 - entry displays 21-11
 - list display 21-21
- PROMPT dialog command** B-12
- prompt, field**
 - See* field prompts
- prompting**
 - action list option B-13
 - command B-13
 - entry field B-13
- protecting entry field** 6-38
- PRTHEAD (print head panel) tag**
 - example, print title lines A-142
 - layout of title lines tables A-141, A-142
 - overview A-139
 - tags allowed table A-139
- PRTPNL (print panel) tag**
 - overview A-143
 - tags allowed table A-143
- PRTRAIL (print trailer message) tag**
 - example, trailer message A-145
 - overview A-145
- pull-down accelerator (PDACCEL) tag**
 - overview A-129

pull-down field (PDFLD) tag

overview A-130
tags allowed table A-130

pull-down field choice (PDFLDC) tag

overview A-131
recommended conventions A-133
required conventions A-133

pull-down menu

CHECK(FE) keyword 6-13
creating 6-13
definition 6-6
example 6-13, 6-41
interaction with menu bar 6-32
receiving input 6-25
removing after receiving input 6-27
single-choice selection field 6-13
updating before displaying 6-28

pull-down menu and pop-up window differences 17-25**PULLDOWN dialog command B-14****PULLINPUT (Pull-Down Menu Input) parameter**

example 6-26

Put with Explicit Override (PUTOVR) keyword

for repeatedly entered data 3-21
more efficient coding 3-20
sample DDS source 3-18

put-relative operation for subfiles

BASIC statement for 4-12
C/400 function for 4-12
COBOL/400 statement for 4-12
definition 4-9
RPG/400 operation for 4-12

Put-Retain (PUTRETAIN) keyword

example
field level 3-24
record level 3-24
restriction with USRDSPMGT keyword G-10
System/36 application compatibility G-2
using 3-23

PUTOVR (Put with Explicit Override) keyword

description 3-18
example
more efficient coding 3-20
repeatedly entered data 3-21
sample DDS source 3-18
system performance considerations 14-2
System/36 application compatibility G-6

PUTRETAIN (Put-Retain) keyword

example
field level 3-24
record level 3-24
restriction with USRDSPMGT keyword G-10
System/36 application compatibility G-2
using 3-23

PV (programming variable) tag

overview A-146

PV (programming variable) tag (continued)

use in help module 20-5

Q**QIGC system value**

DBCS conversion dictionaries
creating D-15
deleting D-19
display D-19
edit, examples of D-17
editing (adding and changing terms) D-16
perform object management functions with D-15
printing D-19

QIGC2424 (DBCS font table) D-8**QRCVDTAQ (receive data queue) program 12-1****QSNDDTAQ (send data queue) program 12-1****QSYSIGCDCT (system-supplied DBCS conversion dictionary)**

contents D-14
definition D-14

queue, data

See DTAQ (data queue) parameter

QUSRIGCDCT (user-created dictionary) D-15**QUSRSYS library 13-3****QUSRTOOL library**

definition 1-6
display examples 21-1
panel groups, using word processing functions when creating 18-2

R**radio button**

definition 6-1
example 6-1

read operation

canceling read operation, CL command for 3-49
definition 3-33
definition for subfile 4-12
subfiles
BASIC statement 4-12
C/400 function for 4-12
COBOL/400 statement for 4-12
RPG/400 operation for 4-12
with no wait
BASIC statement for 3-49
CL command for 3-49
COBOL/400 statement for 3-49
RPG/400 operation for 3-49
with wait
BASIC statement for 3-49
C/400 function for 3-49
CL command for 3-49
COBOL/400 statement for 3-49
FORTRAN/400 statement for 3-49
RPG/400 operation for 3-49

read-from-invited-program-devices operation

- after inviting input 3-30
- C/400 function for 3-49
- COBOL/400 statement for 3-49
- from CL programs,
 - reading-from-invited-devices 3-33
- RPG/400 operation for 3-49
- understanding 3-32

reading

- data from window 5-9

receiving

- data 3-4

receiving input

- from pull-down menu 6-25
- using PULLINPUT 6-26

recommended convention

- list action (LISTACT) tag A-92
- pull-down field choice (PDFLDC) tag A-133

record area, removing option and response indicators from 2-14**record format**

- changing on display 3-8
- checking for changes to 2-7
- contents 2-7
- defining display fields and functions in 2-7
- definition 1-1
- description 2-7
- determining active 3-5
- field, how to use 2-9
- maximum number for display file 2-15
- maximum number of fields in 2-10
- order written to display 3-9
- output and input, for 3-4
- overlying and erasing on display 3-10
- replacing 3-9
- replacing on display 3-8
- starting on specific line 3-11
- viewing on display 2-8

record format table, active 3-5**record-level description**

- definition 2-3
- with field-level descriptions 2-3
- with no field-level descriptions 2-3

record, DDS

- comparing with panel groups and documents 18-2
- containing input fields, improving performance with 14-2
- definition 2-3
- definition for help 1-6
- displaying secondary help 18-17
- displaying two or more 3-10
- entering for help 18-14
- erasing from display during overlay 3-10
- examples
 - HLPCMDKEY keyword 18-20
 - HLPCMDKEY keyword with response indicators 18-21

record, DDS (continued)**examples (continued)**

- HLPRCD keyword 18-13
- HLPRCD keyword with option indicators 18-14
- secondary help 18-18
- help
 - defining for 20-18
 - specifying for 18-12
- improving performance when sending 14-2
- initializing (diagram) 3-36
- keeping on display 3-23
- mode to display 3-27
- not occupying space on display 3-8
- overlapping but not deleting to improve system performance 14-2
- paging between display 18-16
- placing on display 3-5
- resetting modified data tags for 3-23
- restrictions on 18-15
- restrictions on secondary help 18-19
- retrieving with WAIT command 3-33
- rules for displaying on more than one line 3-5
- secondary help, determining sequence of 18-17
- use by I/O statements 3-4
- valid placement of, figure 3-6

recovering from errors 8-11**reference field**

- definition 2-11

relational operator A-11**release operation**

- C/400 function for 3-49
- COBOL/400 statement for 3-49
- definition 3-49
- RPG/400 operation for 3-49

Remove Search Index Entry (RMVSEARCHIE) command 20-16**Remove Window (RMVWDW) keyword 5-11****removing**

- entry from list 17-7
- pop-up window 17-27
- pop-windows using APIs 17-27
- pull-down menu 6-27
- window 5-11, 17-27

Rename Object (RNMOBJ) command D-15**request processor program when displaying panel 17-30****required convention**

- list action (LISTACT) tag A-92
- pull-down field choice (PDFLDC) tag A-133

resource allocation

- description 3-1
- effect on display station error handling 3-1
- understanding how system allocates 3-1

response indicator

- CAnn key, use with 2-13
- CFnn key, use with 2-12

response indicator *(continued)*

- definition 2-12
- enabling simultaneously 2-15
- function keys, use with 2-12
- HLPCMDKEY keyword, use with 18-21
- removing from record area 2-14
- restriction with USRDSPMGT G-10
- ROLLDOWN keyword, use with 2-15
- ROLLUP keyword, use with 2-15
- SETOF or SETOFF keyword, use with 2-15

response time

- for list displays 17-9
- list displays 17-9
- window application 5-12

restore display (RSTDSP) parameter

- example 3-43
- keywords that require 14-3
- system performance considerations 14-3
- use 3-43

Restore Library (RSTLIB) command D-15**Restore Object (RSTOBJ) command**

- DBCS conversion dictionaries D-15
- DBCS sort table D-12

restoring DBCS font tables

- copying from tape or diskette (restoring) D-9
- copying onto diskette (saving) D-9

restoring DBCS sort tables

- copying from file (move from System/36) D-13
- copying to file (move to System/36 or AS/Entry) D-12

restrictions

- 5250 engraved keys 17-12
- command line 17-16
- name syntax
 - HELP tag A-4
 - object names A-4
- on command line 17-16
- using dialog variables 17-2

retain command and function keys

- System/36 application compatibility G-9

Retain Command Keys (RETCMDKEY) keyword

- System/36 application compatibility G-9

Retain Function Keys (RETKEY) keyword

- System/36 application compatibility G-9

RETCMDKEY (Retain Command Keys) keyword

- System/36 application compatibility G-9

RETKEY (Retain Function Keys) keyword

- System/36 application compatibility G-9

RETRIEVE (Retrieve Command String) dialog command B-14**Retrieve Command String (RETRIEVE) dialog command** B-14**RETURN (Return Control to Application) dialog command** B-14**return code**

- binary program menus 9-10

return code *(continued)*

- display file
 - description E-1
 - major 00 E-1
 - major 02 E-1
 - major 03 E-2
 - major 04 E-2
 - major 08 and 11 E-3
 - major 34 E-3
 - major 80 E-3
 - major 81 E-6
 - major 82 E-7
 - major 83 E-10
- major/minor

See major/minor return code

Return Control to Application (RETURN) dialog command B-14**Return Cursor Location (RTNCSRLOC)**

keyword 3-29

return point (RTNPNT) parameter

- for program menus 9-13

return-field (RTNFLD) parameter

- description 6-28
- example 6-28

returning cursor position within subfile to application 3-29**returning mode of subfile to application** 3-29**returning to menu after running GO command** 9-1**reverse text (RT) tag**

- example
 - left-to-right formatting on a left-to-right panel A-147
 - left-to-right formatting on right-to-left panel A-147
- overview A-147

Revoke Object Authority (RVKOBJAUT)

command D-15

right slash (/) symbol A-5**right-to-left cursor movement** 2-16**right-to-left display processing** 2-16**RMV SCHIDX (Remove Search Index Entry)**

command 20-16

RMVWDW (Remove Window) keyword 5-11**RNM OBJ (Rename Object) command** D-15**Roll Down (ROLLDOWN) keyword**

- for function keys 2-12

Roll Up (ROLLUP) keyword

- example with SFLSIZ and SFLPAG 4-16

ROLLDOWN (Roll Down) keyword

- function keys 2-12
- response indicators for 2-15

ROLLUP (Roll Up) keyword

- example with SFLSIZ and SFLPAG 4-16
- function keys 2-12
- improving subfile performance 14-1
- response indicators for 2-15

root words for InfoSeeker

See online help information

routing step

passing data between programs in same 11-1
passing data between steps 11-3

RPG/400 operation

I/O requests for subfiles 4-12
mapping to I/O operations 3-49

RSTDSP (restore display) parameter

example 3-43
keywords that require 14-3
system performance considerations 14-3
use 3-43

RSTLIB (Restore Library) command D-15

RSTOBJ (Restore Object) command

DBCS conversion dictionaries D-15
DBCS sort table D-12

RT (reverse text) tag

example
left-to-right formatting on left-to-right panel A-147
left-to-right formatting on right-to-left panel A-147
overview A-147

RTNCSRLOC (Return Cursor Location)

keyword 3-29

RTNFLD (return field) parameter

description 6-28
example 6-28

rule

edit description use F-5
entry fields 21-14
list display
cursor positioning 21-29
error conditions 21-30

run-time errors, recovering from 3-52

running

system and user-defined menus 9-1

RVKOBJAUT (Revoke Object Authority)

command D-15

S

sample figure

example A-57

sample heading

example A-163

SAVCHGOBJ (Save Changed Object)

command D-15

Save Changed Object (SAVCHGOBJ)

command D-15

Save Library (SAVLIB) command D-15

Save Object (SAVOBJ) command

DBCS conversion dictionaries D-15
DBCS sort table D-12

Save System (SAVSYS) command

DBCS conversion dictionaries D-15
DBCS sort tables D-12

saving

DBCS sort tables D-12

SAVLIB (Save Library) command D-15

SAVOBJ (Save Object) command

DBCS conversion dictionaries D-15
DBCS sort table D-12

SAVSYS (Save System) command

DBCS conversion dictionaries D-15
DBCS sort tables D-12

screen design aid (SDA)

compared to direct DDS source entry 2-5
definition 1-6

screen size

alternate 3-27
condition names 2-20
examples
DDS for subfiles for two 2-20
DDS for two 2-20
improving performance with 14-1
primary and secondary 2-20
valid 2-20

scrollable area definition 17-12

scrolling

area definition 17-12
areas that can be scrolled 17-12
data item groups 17-14
defining 17-12
error conditions 17-13
function keys 17-12
incomplete list 17-13
information area 17-13
list area 17-13
menu area 17-13
message line 17-12
status information 17-12
support 17-12

SDA (screen design aid)

compared to direct DDS source entry 2-5
definition 1-6

search index

See online help information

secondary help

definition 18-16
determining the sequence of records 18-17
displaying records 18-17

selection

choices, Common User Access 21-50
list where singular item can be selected, list displays 21-31

selection character

country-designated 17-11
definition 6-15
highlighting A-9
suppressing 6-15

selection field choice

colors and display attributes 6-21

selection field choice (*continued*)

- defining 6-9
- multiple 6-10
- single 6-9

selection list 17-10

self-check, System/36 application compatibility G-2

sending

- data 3-4

sentence-ending characters A-2

separating with blank lines 17-33

separator

- content A-1
- markup A-1

Set Off (SETOF or SETOFF) keywords

- response indicators for 2-15

SETOF or SETOFF (Set Off) keyword

- response indicators for 2-15

SEU (source entry utility)

- definition 1-4
- Edit display 1-4

SFL (Subfile) keyword 4-3

SFLCLR (Subfile Clear) keyword

- description 4-4

SFLCSRRRN (Subfile Cursor Relative Record Number) keyword 3-29

SFLCTL (Subfile Control) keyword 4-3

SFLDLT (Subfile Delete) keyword 4-4

SFLDROP (Subfile Drop) keyword 4-4

SFLDSP (Subfile Display) keyword 4-3

SFLDSPCTL (Subfile Display Control) keyword 4-4

SFLEND (Subfile End) keyword 4-4

SFLENTER (Subfile Enter) keyword 4-4

SFLFOLD (Subfile Fold) keyword 4-4

SFLINZ (Subfile Initialize) keyword 4-4

SFLLIN (Subfile Line) keyword 4-4

SFLMODE (Subfile Mode) keyword 3-29

SFLMSG (Subfile Message) keyword

- description 4-4
- displaying on message line when subfile control record written 8-2
- messages resulting from 5-6

SFLMSGID (Subfile Message Identifier) keyword

- description 4-4
- displaying on message line when subfile control record written 8-2
- example DDS source 8-5
- messages resulting from 5-6

SFLMSGKEY (Subfile Message Key) keyword

- description 4-4
- displaying messages from program message queue 8-4

SFLMSGRCD (Subfile Message Record) keyword

- description 4-4
- displaying messages from program message queue 8-4

SFLNXTCHG (Subfile Next Changed) keyword

- description 4-4
- example DDS 4-18

SFLPAG (Subfile Page) keyword

- example with ROLLUP and SFLSIZ 4-16
- use in subfile control record format 4-3

SFLPGMQ (Subfile Program Message Queue) keyword

- description 4-4
- displaying messages from program message queue 8-4

SFLRCDNBR (Subfile Record Number) keyword

- description 4-4
- improving subfile performance 14-1

SFLRNA (Subfile Records Not Active) keyword 4-4

SFLROLVAL (Subfile Roll Value) keyword 4-4

SFLSIZ (Subfile Size) keyword

- example with ROLLUP and SFLPAG 4-16
- use in subfile control record format 4-3

SHARE (share) parameter

- sharing display files in same job 3-50
- system performance considerations 14-2

sharing

- open data paths 14-2

sharing and overriding with printer file 17-34

shift-control character

- DBCS-graphic characters D-6
- description of D-3
- inserting D-6

sign on

- choosing sign on menu 9-3

signed numeric data, System/36 application compatibility G-7

simple list (SL) tag

- example, simple lists A-149
- overview A-149
- tags allowed table A-149
- use in help module 20-5

simple menu area

- example A-110

single selection field operation, CUA guidelines 21-50

single-choice menu display

- See menu display

single-choice selection field

- colors and display attributes 6-21
- defining 6-9
- definition 6-9
- example 6-9
- in a pull-down menu 6-13

size

- window 5-4

SL (simple list) tag

- example, simple lists A-149
- overview A-149
- tags allowed table A-149

SL (simple list) tag *(continued)*

use in help module 20-5

slash (/) symbol A-5**SLNO (Starting Line Number) keyword**

examples

restrictions 3-11

table of values and results 3-11

use 3-11

used with other DDS keywords 3-11

with *VAR value 3-12

sort table

copying DBCS master from data file D-13

copying DBCS master to data file D-12

source

example confirmation panel 16-28

example data presentation panel 16-36

example list panel 16-18

example menu 16-9

example menu bar panel 16-54

source entry utility (SEU)

definition 1-4

Edit display 1-4

source file

definition 1-2

source member

definition 1-2

Specify Members to Work with display 1-2**specifying**

enhanced display capability 6-3

right-to-left display processing 2-16

Start Character Generator Utility (STRCGU)

command D-10

Start Programming Development Manager

(STRPDM) command 1-1

Start Source Entry Utility (SEU) display 1-3**Start Source Entry Utility (STRSEU) command** 2-7**Starting Line Number (SLNO) keyword**

restrictions 3-11

table of values and results 3-11

use 3-11

used with other DDS keywords 3-11

with *VAR value 3-12

STRCGU (Start Character Generator Utility)

command D-10

stream, user-defined data

See user-defined data stream (UDDS)

STRPDM (Start Programming Development

Manager) command 1-1

STRSEU (Start Source Entry Utility) command 2-7**subfile**

See also display file

active record in, updating 4-10

adding record at a specified location in 4-9

checking validity of data 4-18

controlling appearance of 4-12

cursor, positioning

initially 4-20

subfile *(continued)*

cursor, positioning *(continued)*

when Fold or Truncate key used 4-24

when more than one record displayed 4-24

when Roll key used 4-21

definition 2-9

describing in DDS source 4-3

displaying

and processing records at the same time 4-12

error messages from 4-19

horizontally 4-12

horizontally with display modes 4-14

records 4-11

vertically 4-12

example

*DS3 mode display 4-15

*DS4 mode display 4-15

DDS for two display sizes 2-20

DSPATR(PC) keyword, use of 4-21

DSPMOD keyword, use of 4-14

message subfile 4-20

program logic for subfiles 4-28

ROLLUP, SFLSIZ, and SFLPAG keywords 4-16

sample display for changing information 4-2

sample display for display only 4-1

sample display for input only 4-2

sample display for task combination 4-2

sample display with selection 4-1

sample displays when rolling two or more
records 4-25

SFLNXTCHG keyword, use of 4-18

SFLPAG, SFLSIZ, and ROLLUP keywords 4-16

SFLSIZ, ROLLUP, and SFLPAG keywords 4-16

variable-length record 4-17

vertical and horizontal, displayed at same
time 4-12

extending full 4-6

functions for 4-4

high-level language programs, use in 4-7

maximum number active to display station 4-6

maximum number allowed in display file 4-6

multiple records 4-1

optional functions, table of 4-4

order of subfile record format and subfile control
record format 4-3

performance considerations 14-1

placing records on display for processing 4-12

positioning cursor for each page of records 4-20

program logic for 4-28

reading active record at specified location in 4-10

reading next changed record in 4-10

recognizing uses of

changing information 4-2

combination of tasks 4-2

display only 4-1

input only without validity checking 4-2

sample display with selection 4-1

subfile (*continued*)

records

- active subfile 4-3
- inactive subfile 4-3
- requesting I/O operations for 4-9
- rolling and validity checking 4-6
- SFL keyword, use of 4-3
- SFLCTL keyword, use of 4-3
- SFLDSP keyword, use of 4-3
- SFLPAG keyword, use of 4-3
- SFLSIZ keyword, use of 4-3
- size equal to page size 4-15
- size not equal to page size 4-17
- subfile control record format, purpose 4-3
- subfile control, processing order of DDS keywords for 4-7
- subfile record format, purpose 4-3
- table of I/O requests in high-level languages
 - BASIC statements 4-12
 - C/400 functions 4-12
 - COBOL/400 statements 4-12
 - RPG/400 operations 4-12
- USRDSPMGT keyword restriction G-10
- validity checking before rolling 4-6
- window 5-6

Subfile Clear (SFLCLR) keyword

- description 4-4

Subfile Control (SFLCTL) keyword 4-3

subfile control record format

- definition 4-3
- placement after subfile record format 4-3
- read operation 4-12
- requesting I/O operations for 4-11
- required DDS keywords 4-3
- SFLCTL keyword, use of 4-3
- SFLDSP keyword, use of 4-3
- SFLPAG keyword, use of 4-3
- SFLSIZ keyword, use of 4-3
- write operation 4-11
- write-read operation 4-12

Subfile Cursor Relative Record Number (SFLSCRRRN) keyword 3-29

Subfile Delete (SFLDLT) keyword 4-4

Subfile Display (SFLDSP) keyword 4-3

Subfile Display Control (SFLDSPCTL) keyword 4-4

Subfile Drop (SFLDROP) keyword 4-4

Subfile End (SFLEND) keyword 4-4

Subfile Enter (SFLENTER) keyword 4-4

Subfile Fold (SFLFOLD) keyword 4-4

Subfile Initialize (SFLINZ) keyword 4-4

Subfile Line (SFLLIN) keyword 4-4

Subfile Message (SFLMSG) keyword

- description 4-4
- displaying on message line when subfile control record written 8-2
- messages resulting from 5-6

Subfile Message Identifier (SFLMSGID) keyword

- defining in display 8-4
- description 4-4
- displaying on message line when subfile control record written 8-2
- messages resulting from 5-6

Subfile Message Key (SFLMSGKEY) keyword

- description 4-4
- displaying messages from program message queue 8-4

Subfile Message Record (SFLMSGRCRD) keyword

- description 4-4
- displaying messages from program message queue 8-4

Subfile Mode (SFLMODE) keyword 3-29

Subfile Next Changed (SFLNXTCHG) keyword

- description 4-4
- example DDS 4-18

Subfile Page (SFLPAG) keyword

- example with ROLLUP and SFLSIZ 4-16
- use in subfile control record format 4-3

Subfile Program Message Queue (SFLPGMQ) keyword

- description 4-4
- displaying messages from program message queue 8-4

subfile record format

- definition 4-3
- get-next-changed operation 4-10
- get-relative operation 4-10
- placement before subfile control record format 4-3
- put-relative operation 4-9
- requesting I/O operations for 4-9
- SFL keyword, use of 4-3
- update operation 4-10

Subfile Record Number (SFLRCDNBR) keyword

- description 4-4

Subfile Records not Active (SFLRNA) keyword 4-4

Subfile Roll Value (SFLROLVAL) keyword 4-4

Subfile Size (SFLSIZ) keyword

- example with ROLLUP and SFLPAG 4-16
- use in subfile control record format 4-3

suppressed selection character

- example 6-15

symbol

- ampersand (&) A-5
- colon (:) A-5
- concatenation A-5
- message text
 - message file default A-5
- period (.) A-5
- right slash (/) A-5

symmetric character

- Arabic A-21
- Hebrew A-21

synonym, InfoSeeker

See online help information

System Command (CMD) dialog command B-7**system menu 9-1****system message**

See message

system performance

See performance

system value

QIGC for DBCS conversion dictionaries

creating D-15

deleting D-19

display D-19

edit, examples of D-17

editing (adding and changing terms) D-16

perform object management functions with D-15

printing D-19

System/36 application compatibility

ASSUME (Assume) keyword G-2

cancel-invite operation G-8

display files G-1

ERASE (Erase) keyword G-2

function keys G-7

HELP (Help) keyword G-7

Help Return (HLPRTN) keyword G-7

high-level languages G-1

HLPRTN (Help Return) keyword G-7

input data G-2

KEEP (Keep) keyword G-2

messages G-4

OVERLAY keyword G-2

PUTOVR (Put with Explicit Override) keyword G-6

PUTRETAIN (Put-Retain) keyword G-2

T**tab key**

movement 6-39

tag

definition A-1

MENUGRP (menu group) A-112

MENUI (menu item) A-113

tag language

See panel group definition language

tag within help module

CIT (title citation)

use in help module 20-4

definition list (DL)

use in help module 20-5

DL (definition list)

use in help module 20-5

example (XMP)

use in help module 20-5

extended help headings (XH1-XH4)

use in help module 20-4

FIG (figure)

use in help module 20-5

tag within help module (continued)

figure (FIG)

use in help module 20-5

H1 through H4 (headings)

use in help module 20-4

heading (H1 through H4)

use in help module 20-4

HELP (help module)

panel groups with help modules 20-2

placement in UIM source 20-2

help module (HELP)

panel groups with help modules 20-2

placement in UIM source 20-2

highlighted phrase (HP0-HP9)

use in help module 20-4

HP0-HP9 (highlighted phrase)

use in help module 20-4

hypertext link (LINK)

placement in UIM source 20-14

imbed help (IMHELP)

placement in panel group source 20-2

IMHELP (imbed help)

panel groups using 20-2

placement in panel group source 20-2

IMPORT (import)

panel groups using 20-3

placement in UIM source 20-3

index search (ISCH)

placement in UIM source 20-8

index search synonym (ISCHSYN)

placement in UIM source 20-8

ISCH (index search)

panel groups using 20-8

placement in UIM source 20-8

ISCHSYN (index search synonym)

panel groups using 20-8

placement in UIM source 20-8

LINES (unformatted lines)

use in help module 20-5

LINK (hypertext link)

panel groups using 20-14

placement in UIM source 20-14

list part (LP)

use in help module 20-5

LP (list part)

use in help module 20-5

note (NT)

use in help module 20-4

NT (note)

use in help module 20-4

OL (ordered list)

use in help module 20-5

ordered list (OL)

use in help module 20-5

P (paragraph)

placement in UIM source 20-2

use in help module 20-4

tag within help module *(continued)*

- panel group (PNLGRP)
 - placement in UIM source 20-2
- panel markup
 - definition 20-4
- paragraph (P)
 - use in help module 20-4
- paragraph continuation (PC)
 - use in help module 20-4
- parameter list (PARML)
 - use in help module 20-5
- PARML (parameter list)
 - use in help module 20-5
- PC (paragraph continuation)
 - use in help module 20-4
- PK (programming keyword)
 - use in help module 20-5
- PNLGRP (panel group)
 - panel groups with help modules 20-2
 - placement in UIM source 20-2
- programming keyword (PK)
 - use in help module 20-5
- programming variable (PV)
 - use in help module 20-5
- purpose 20-1
- PV (programming variable)
 - use in help module 20-5
- simple list (SL)
 - use in help module 20-5
- SL (simple list)
 - use in help module 20-5
- title citation (CIT)
 - use in help module 20-4
- UL (unordered list)
 - use in help module 20-5
- unformatted lines (LINES)
 - use in help module 20-5
- unordered list (UL)
 - use in help module 20-5
- XH1 through XH4 (extended help heading)
 - use in help module 20-4
- XMP (example)
 - use in help module 20-5

tag, modified data 2-10**tag, UIM**

- APPFMT (application formatted area) A-8
- BOTINST (bottom instruction) A-10
- CHECK (validity checking) A-11
- CIT (title citation) A-13
- CLASS (class definition) A-14
- CMDLINE (command line) A-24
- COND (condition definition) A-25
- COPYR (copyright) A-28
- DATA (data presentation area) A-29
- DATAAC (data item choices) A-36
- DATA COL (data column) A-37

tag, UIM *(continued)*

- DATAGRP (data group) A-38
- DATAI (data item) A-40
- DATAIX (data item extender) A-45
- DATASLT (data selection field) A-49
- DATASLTC (data selection field choice) A-53
- DL (definition list) A-55
- FIG (figure) A-57
- H1 through H4 (heading) A-63
- HELP (help module) A-58
- HP0 through HP9 (highlighted phrase) A-61
- IMHELP (imbed help) A-64
- IMPORT (import) A-65
- INFO (information area) A-66
- ISCH (index search) A-68
- ISCHSUBT (index search subtopic) A-69
- ISCHSYN (index search synonym) A-70
- KEYI (key list item) A-72
- KEYL (key list) A-74
- LINES (unformatted lines) A-75
- LINK (hypertext link definition) A-76
- LIST (list area) A-80
- LISTACT (list action) A-88
- LISTCOL (list column) A-94
- LISTDEF (list definition) A-98
- LISTGRP (list column group) A-101
- LISTVIEW (list view) A-103
- LP (list part) A-105
- MBAR (menu bar) A-106
- MBARC (menu bar choice) A-108
- MENU (menu area) A-109
- NT (note) A-115
- OL (ordered list) A-116
- OPTLINE (option line) A-118
- P (paragraph) A-119
- PANEL (display panel) A-120
- PARML (parameter list) A-126
- PC (paragraph continuation) A-128
- PDACCEL (pull-down accelerator) A-129
- PDFLD (pull-down field) A-130
- PDFLDC (pull-down field choice) A-131
- PK (programming keyword) A-135
- PNLGRP (panel group) A-136
- PRTHEAD (print head panel) A-139
- PRTPNL (print panel) A-143
- PRTRAIL (print trailer message) A-145
- PV (programming variable) A-146
- RT (reverse text) A-147
- SL (simple list) A-149
- TI (translation list item) A-151
- TL (translation list) A-152
- TOPINST (top instruction) A-154
- TT (truth table) A-155
- TTROW (truth table row) A-156
- UL (unordered list) A-157
- VAR (variable definition) A-159

- tag, UIM** *(continued)*
 - VARRCD (variable record definition) A-162
 - XH1 through XH4 (extended help headings) A-163
 - XMP (example) A-164
- tape device file**
 - DBCS D-5
- text area, descriptive**
 - entry displays 21-15
- TI (translation list item) tag**
 - overview A-151
- time value**
 - display form A-23
- timing function on WAITRCD parameter 3-33**
- title citation (CIT) tag**
 - example
 - title citations A-13
 - overview A-13
 - use in help module 20-4
- title lines**
 - table A-141
- titles on displays**
 - entry displays 21-10
 - information displays 21-18
 - list display 21-20
 - single-choice menu displays 21-8
- TL (translation list) tag**
 - list, translation A-152
 - overview A-152
 - tags allowed table A-152
- tool, command line 21-35**
- top instruction (TOPINST) tag**
 - overview A-154
- topics, InfoSeeker**
 - See online help information
- TOPINST (top instruction) tag**
 - overview A-154
- trailer message**
 - example A-145
- trailer printing 17-33**
- translation**
 - character set and code page, UIM A-18
- translation list (TL) tag**
 - list, translation A-152
 - overview A-152
 - tags allowed table A-152
- translation list item (TI) tag**
 - overview A-151
- translation table 13-3**
- truth table (TT) tag**
 - example, truth table A-155
 - overview A-155
 - tags allowed table A-155
- truth table row (TTROW) tag**
 - overview A-156
- TT (truth table) tag**
 - example, truth table A-155

- TT (truth table) tag** *(continued)*
 - overview A-155
 - tags allowed table A-155
- TTROW (truth table row) tag**
 - overview A-156
- two presentation areas for data items**
 - example A-33
- two-column format in a data entry panel**
 - example A-32
- type**
 - display station 5-2, 6-2

U

- UDDS (user-defined data streams)**
 - 3270 Model 4 display station support 10-3
 - available functions 10-2
 - buffer format for 5250 display station 10-3
 - command attention keys, effects on 10-3
 - command function keys, effects on 10-3
 - defining output buffer 10-3
 - defining output data stream 10-3
 - display station differences, understanding 10-1
 - handling of field-level requests after user-defined requests 10-2
 - help information for 10-2
 - I/O requests, effect on 10-2
 - input operations 10-4
 - limitations 10-2
 - opening display files containing 10-3
 - output record area for record format 10-2
 - system operations to request commands 10-4
 - understanding limitations 10-2
 - using 10-1
 - USRDFN (User-Defined) keyword 10-1
 - valid keywords with USRDFN keyword 10-2
 - write-read function 10-3
 - write-read operations
 - CL (control language) 10-3
 - COBOL/400 10-3
 - RPG/400 10-3
- UIM (user interface manager)**
 - See also panel group
 - 5250 engraved key restrictions 17-12
 - action list definition 17-9
 - action variable definition 17-9, 17-11
 - adding pop-up window over another panel 17-24
 - adding window over another panel 17-24
 - after scrolling example 16-34
 - alternate view of list example 16-15
 - API services 16-5
 - application handle definition 17-1
 - application programming
 - confirmation processing 16-32
 - data presentation panel 16-47
 - list panel 16-26
 - menu bar panel 16-64

UIM (user interface manager) (continued)

- application window, defining 17-27
- automatic confirmation processing 16-31
- command line
 - entered too long 17-17
 - interpretation 17-16
 - pop-up window 17-29
 - restrictions 17-16
 - window 17-29
 - window example 17-29
- confirmation list panel, creating 16-27
- confirmation panel source 16-28
- confirmation processing
 - application programming 16-32
 - automatically 16-31
- considerations before using 15-1
- contextual help, defining 17-14
- controlling list entries on list display 17-8
- conversion of character set and code page A-18
- creating
 - confirmation list panel 16-27
 - data presentation panel 16-32
 - list panel 16-13
 - menu bar panel 16-51
 - menu panel 16-6
 - object 16-3
- cursor position when help text displayed 17-14
- data entry panel 16-50
- data presentation panel
 - application programming 16-47
 - creating 16-32
 - example 16-32
 - source 16-36
- DBCS and national language considerations 20-11
- DDS instead of 15-1
- defining
 - application window 17-27
 - contextual help 17-14
 - dialog variable 17-1
 - function keys 17-17
 - function keys and VARUPD value 17-18
 - menu object 16-6
 - panel group object 16-13
- definition 1-1
- details 17-1
- dialog variable
 - definition 17-1
 - error messages 17-3
 - incorrect characters 17-4
 - initial value 17-2
 - restrictions 17-2
- differences between pull-down menus and pop-up windows 17-25
- display characters, incorrect 17-4
- display panel field value using dialog variables 17-4
- displaying list 17-7

UIM (user interface manager) (continued)

- displaying panel using request processor program 17-30
- elements within panel group 16-3
- entry pointer for list 17-8
- error messages for dialog variables 17-3
- example
 - alternate view of list 16-15
 - list panel 16-14
 - menu bar panel 16-51
 - menu source 16-9
- exit flag 17-21
- field value for display panel using dialog variables 17-4
- folding up list panel 17-23
- folding up multiple panels when EXIT requested 17-21
- folding when EXIT requested 17-21
- formatting function keys 17-17
- function key
 - defining 17-17
 - formatting 17-17
 - scrolling 17-12
 - VARUPD value 17-18
- functions supported 16-1
- help text displayed according to cursor position 17-14
- help window 5-8
- hierarchy, InfoSeeker 20-10
- incorrect characters in dialog variable 17-4
- incorrect display characters 17-4
- incorrect printer characters 17-4
- increasing user productivity 15-1
- InfoSeeker hierarchy 20-10
- initial value of dialog variable 17-2
- initializing list 17-6
- inserting entry from list 17-7
- interactive response time for list displays 17-9
- introduction 16-1
- limitations of panel formatter 17-21
- list
 - displaying 17-7
 - initialing 17-6
 - inserting entry from 17-7
 - managing 17-6
 - removing entry from 17-7
 - updating 17-7
- list display
 - controlling list entries 17-8
- list entry
 - handle 17-7
 - on list display 17-8
 - pointer 17-8
- list panel
 - application programming 16-26
 - creating 16-13
 - example 16-14

UIM (user interface manager) (continued)

- list panel (continued)
 - fold up 17-23
 - source 16-18
- managing panel functions 17-11
- menu area, scrolling 17-13
- menu bar panel
 - application programming 16-64
 - creating 16-51
 - example 16-51
 - source 16-54
- menu bars 17-24
- menu definition 16-2
- menu object 16-6
- menu panel
 - creating 16-6
 - example 16-6
- message line, scrolling 17-12
- national language considerations and DBCS 20-11
- opening application 17-1
- panel elements supported 16-1
- panel formatter limitations 17-21
- panel formatting
 - application control 17-20
 - concepts 17-19
 - definition 17-19
 - when to perform 17-19
- panel function managing 17-11
- panel group
 - definition 16-2
 - elements 16-3
- panel group object, defining 16-13
- panel list fold up 17-23
- pop-up window
 - adding 17-27, 17-28
 - adding and removing using APIs 17-27
 - adding over another panel 17-24
 - adding to display stack 17-27, 17-28
 - API for adding and removing 17-27
 - command line 17-29
 - defining application 17-27
 - example in command line 17-29
 - removing 17-28
 - removing using APIs 17-27
 - using 17-27
- pop-up window and pull-down menu
 - differences 17-25
- printer characters, incorrect 17-4
- printing 17-30
 - blank lines for separating 17-33
 - character set and code page 17-5
 - code page and character set 17-5
 - concepts 17-30
 - DBCS (double-byte character set) 17-34
 - double-byte character set (DBCS) 17-34
 - fonts and highlighting 17-33
 - header area 17-33

UIM (user interface manager) (continued)

- printing (continued)
 - highlighting 17-33
 - highlighting and fonts 17-33
 - introduction 17-30
 - overriding with and sharing printer file 17-34
 - page eject 17-34
 - print head panel 17-32
 - print panel 17-32
 - printer file, sharing and overriding with 17-34
 - prolog area 17-33
 - separating with blank lines 17-33
 - sharing and overriding with printer file 17-34
 - trailer 17-33
- productivity
 - improvements 15-1
 - increasing application programmer 15-1
- pull-down menu and pop-up window
 - differences 17-25
- removing entry from list 17-7
- request processor program when displaying panel 17-30
- response time for list displays 17-9
- restrictions
 - 5250 engraved keys 17-12
 - using dialog variables 17-2
- routing step 17-11
- scrolling
 - area definition 17-12
 - areas that can be scrolled 17-12
 - data item groups 17-14
 - defining scrollable areas 17-12
 - error conditions 17-13
 - function key 17-12
 - incomplete list 17-13
 - information area 17-13
 - list area 17-13
 - menu area 17-13
 - message line 17-12
 - status information 17-12
- selection characters 17-11
- selection list definition 17-10
- source
 - example confirmation panel 16-28
 - example data presentation panel 16-36
 - example list panel 16-18
 - example menu 16-9
 - example menu bar panel 16-54
- updating list 17-7
- using DDS instead of 15-1
- variable pool services 17-4
- VARUPD value and function keys 17-18
- when to use to gain productivity 15-1
- window
 - adding 17-27, 17-28
 - adding and removing using APIs 17-27
 - adding over another panel 17-24

UIM (user interface manager) (continued)**window (continued)**

- adding to display stack 17-27, 17-28
- API for adding and removing 17-27
- command line 17-29
- defining application 17-27
- example in command line 17-29
- removing 17-28
- removing using APIs 17-27
- using 17-27

UIM-defined variable attributes A-160**UL (unordered list) tag**

- example, unordered list A-158
- overview A-157
- tags allowed table A-157
- use in help module 20-5

unavailable choice

- example 6-12

unformatted lines (LINES) tag

- example, unformatted lines A-75
- overview A-75
- use in help module 20-5

UNLOCK (Unlock Keyboard) keyword

- effects on input operation 3-36
- example with INZRCD keyword 3-36
- unlocking keyboard while the program is processing data 3-35

unordered list (UL) tag

- example, unordered list A-158
- overview A-157
- tags allowed table A-157
- use in help module 20-5

update operation for subfiles

- BASIC statement for 4-12
- C/400 function for 4-12
- COBOL/400 statement for 4-12
- definition 4-10
- RPG/400 operation for 4-12

updating

- list in UIM 17-7

updating pull-down menu 6-28**User Defined (USRDFN) keyword**

- See user-defined data stream (UDDS)

User Display Management (USRDSMGT) keyword

- DDS keywords that cannot be used with G-2
- use G-1

user interface manager (UIM)

- See also panel group
- 5250 engraved key restrictions 17-12
- action list definition 17-9
- action variable definition 17-9, 17-11
- adding pop-up window over another panel 17-24
- adding window over another panel 17-24
- alternate view of list example 16-15
- API services 16-5
- application handle definition 17-1

user interface manager (UIM) (continued)

- application programming
 - confirmation processing 16-32
 - data presentation panel 16-47
 - list panel 16-26
 - menu bar panel 16-64
- application window, defining 17-27
- automatic confirmation processing 16-31
- command line
 - entered too long 17-17
 - interpretation 17-16
 - pop-up window 17-29
 - restrictions 17-16
 - window 17-29
 - window example 17-29
- confirmation list panel, creating 16-27
- confirmation panel source 16-28
- confirmation processing
 - application programming 16-32
 - automatically 16-31
- considerations before using 15-1
- contextual help, defining 17-14
- controlling list entries on list display 17-8
- conversion of character set and code page A-18
- creating
 - confirmation list panel 16-27
 - data presentation panel 16-32
 - list panel 16-13
 - menu bar panel 16-51
 - menu panel 16-6
 - object 16-3
- cursor position when help text displayed 17-14
- data entry panel 16-50
- data presentation panel
 - after scrolling example 16-34
 - creating 16-32
 - example 16-32
 - source 16-36
- DBCS and national language considerations 20-11
- DDS instead of 15-1
- defining
 - application window 17-27
 - contextual help 17-14
 - dialog variable 17-1
 - function keys 17-17
 - function keys and VARUPD value 17-18
 - menu object 16-6
 - panel group object 16-13
- defining menu object 16-6
- defining panel group object 16-13
- definition 1-1
- details 17-1
- dialog variable
 - definition 17-1
 - error messages 17-3
 - incorrect characters 17-4
 - initial value 17-2

user interface manager (UIM) (continued)

- dialog variable (*continued*)
 - restrictions 17-2
- differences between pull-down menus and pop-up windows 17-25
- display characters, incorrect 17-4
- display panel field value using dialog variables 17-4
- displaying list 17-7
- displaying panel using request processor program 17-30
- elements within panel group 16-3
- entry pointer for list 17-8
- error messages for dialog variables 17-3
- example
 - alternate view of list 16-15
 - list panel 16-14
 - menu bar panel 16-50
 - menu source 16-9
- exit flag 17-21
- field value for display panel using dialog variables 17-4
- folding up list panel 17-23
- folding up multiple panels when EXIT requested 17-21
- folding when EXIT requested 17-21
- formatting function keys 17-17
- function key
 - defining 17-17
 - formatting 17-17
 - scrolling 17-12
 - VARUPD value 17-18
- functions supported 16-1
- help text displayed according to cursor position 17-14
- help window 5-8
- hierarchy, InfoSeeker 20-10
- incorrect characters in dialog variable 17-4
- incorrect display characters 17-4
- incorrect printer characters 17-4
- increasing user productivity 15-1
- InfoSeeker hierarchy 20-10
- initial value of dialog variable 17-2
- initializing list 17-6
- inserting entry from list 17-7
- interactive response time for list displays 17-9
- introduction 16-1
- limitations of panel formatter 17-21
- list
 - defining 17-6
 - displaying 17-7
 - initialing 17-6
 - inserting entry from 17-7
 - managing 17-6
 - removing entry from 17-7
 - updating 17-7
- list display
 - controlling list entries 17-8

user interface manager (UIM) (continued)

- list entry
 - handle 17-7
 - on list display 17-8
 - pointer 17-8
- list panel
 - application programming 16-26
 - creating 16-13
 - example 16-14
 - fold up 17-23
 - source 16-18
- managing panel functions 17-11
- menu area, scrolling 17-13
- menu bar 17-24
- menu bar panel 16-51
 - application programming 16-64
 - creating 16-51
 - example 16-50
 - source 16-54
- menu definition 16-2
- menu object, defining 16-6
- menu panel
 - creating 16-6
 - example 16-6
- message line, scrolling 17-12
- national language considerations and DBCS 20-11
- opening application 17-1
- panel elements supported 16-1
- panel formatter limitations 17-21
- panel formatting
 - application control 17-20
 - concepts 17-19
 - definition 17-19
 - when to perform 17-19
- panel function managing 17-11
- panel group
 - definition 16-2
 - elements 16-3
- panel group object, defining 16-13
- panel list fold up 17-23
- pop-up window
 - adding 17-27, 17-28
 - adding and removing using APIs 17-27
 - adding over another panel 17-24
 - adding to display stack 17-27, 17-28
 - API for adding and removing 17-27
 - command line 17-29
 - defining application 17-27
 - example in command line 17-29
 - removing 17-28
 - removing using APIs 17-27
 - using 17-27
- pop-up window and pull-down menu
 - differences 17-25
- printer characters, incorrect 17-4
- printing 17-30
 - blank lines for separating 17-33

user interface manager (UIM) (continued)

printing (continued)

- character set and code page 17-5
- code page and character set 17-5
- concepts 17-30
- DBCS (double-byte character set) 17-34
- double-byte character set (DBCS) 17-34
- fonts and highlighting 17-33
- header area 17-33
- highlighting and fonts 17-33
- introduction 17-30
- overriding with and sharing printer files 17-34
- page eject 17-34
- print head panel 17-32
- print panel 17-32
- printer file, sharing and overriding with 17-34
- prolog area 17-33
- separating with blank lines 17-33
- sharing and overriding with printer files 17-34
- trailer 17-33

productivity

- improvements 15-1
- increasing application programmer 15-1

pull-down menu and pop-up window

differences 17-25

removing entry from list 17-7

request processor program when displaying panel 17-30

response time for list displays 17-9

restrictions

- 5250 engraved keys 17-12
- using dialog variables 17-2

routing step 17-11

scrolling

- area definition 17-12
- areas that can be scrolled 17-12
- data item group 17-14
- defining scrollable areas 17-12
- error conditions 17-13
- function key 17-12
- incomplete list 17-13
- information area 17-13
- list area 17-13
- menu area 17-13
- message line 17-12
- status information 17-12

selection characters 17-11

selection list definition 17-10

source

- example confirmation panel 16-28
- example data presentation panel 16-36
- example list panel 16-18
- example menu bar panel 16-54

source for example menu 16-9

updating list 17-7

using DDS instead of 15-1

user interface manager (UIM) (continued)

variable pool services 17-4

VARUPD value and function keys 17-18

when to use to gain productivity 15-1

window

- adding 17-27, 17-28
- adding and removing using APIs 17-27
- adding over another panel 17-24
- adding to display stack 17-27, 17-28
- API for adding and removing 17-27
- command line 17-29
- defining application 17-27
- example in command line 17-29
- removing 17-28
- removing using APIs 17-27
- using 17-27

User Restore Display (USRRSTDSP) keyword 5-11**user-created dictionary (QUSRIGCDCT) D-15****user-defined data streams (UDDS)**

3270 Model 4 display station support 10-3

available functions 10-2

buffer format for 5250 display station 10-3

command attention keys, effects on 10-3

command function keys, effects on 10-3

defining output buffer 10-3

defining output data stream 10-3

display station differences, understanding 10-1

handling of field-level requests after user-defined requests 10-2

help information for 10-2

I/O requests, effect on 10-2

input operations 10-4

limitations 10-2

opening display files containing 10-3

output record area for record format 10-2

system operations to request commands 10-4

understanding limitations 10-2

using 10-1

USRDFN (User-Defined) keyword 10-1

valid keywords with USRDFN keyword 10-2

write-read function 10-3

write-read operations

CL (control language) 10-3

COBOL/400 10-3

RPG/400 10-3

user-defined edit code

about 2-19

edit descriptions F-4

user-defined menus

See menu display

using note

example A-115

USRDFN (User-Defined) keyword

See user-defined data stream (UDDS)

USRDSMGT (User Display Management) keyword

restricted DDS keywords G-2, G-10

USRDSMGT (User Display Management) keyword

(continued)

restrictions for response indicators G-10

restrictions for subfiles G-10

use G-1

USRRSTDSP (User Restore Display) keyword 5-11

V

valid DDS for mnemonic

example 6-19

validity checking

functions, specifying 3-37

keywords 3-37

performing 17-2

restrictions when using CAnn keys 2-13

subfile data 4-18

validity checking (CHECK) tag

example, validity checking A-12

overview A-11

validity-checking keyword 5-6

value

BASETYPE A-14

character A-23

date A-23

numeric A-22

time A-23

VAR (variable definition) tag

overview A-159

variable definition (VAR) tag

overview A-159

variable pool

definition 17-1

services 17-4

variable record definition (VARRCD) tag

overview A-162

variable update (VARUPD) attribute

dialog command B-4

function keys 17-18

KEYI tag A-73

PDFLDC tag A-132

variable value 17-4

variable-length record 4-17

VARRCD (variable record definition) tag

overview A-162

VARUPD (variable update) attribute

dialog command B-4

function keys 17-18

KEYI tag A-73

PDFLDC tag A-132

VARUPD value and function keys 17-18

Vary Configuration (VRYCFG) command D-10

VRYCFG (Vary Configuration) command D-10

W

WAIT (wait) command 3-33

WAIT(*NO) parameter 3-30

WAITFILE (wait file) parameter

for acquire operation 3-3

for open operation 3-2

for system allocation of resources 3-1

WAITRCD (wait record) parameter

timing function for 3-33

WDWBORDER (Window Border) keyword 5-7

window

adding over another panel 17-24

border 5-7

changing 5-9

creating 5-3

cursor position 5-5

defining 17-27

definition 2-22

duplicating 5-9

help displayed in 5-6, 5-8

location 5-4, 5-6

making one pop out of series 5-10

making two active 5-9

maximum displayed 5-3

message in 5-5

moving 5-9

performance 5-11

programming example 5-14

reading data from 5-9

removing 5-11

size 5-4

subfile used in 5-6

system performance considerations 14-4

WINDOW (Window) keyword 5-3

Window Border (WDWBORDER) keyword 5-7

window definition record 5-3

window reference record 5-3

words, InfoSeeker root

See online help information

Work with DBCS Conversion Dictionary

display D-16

Work with Members Using PDM display 1-3

write operation

BASIC statement for 3-49

C/400 function for 3-49

CL command for 3-49

COBOL/400 statement for 3-49

deferring until a read request is made 3-26

definition 3-5

FORTTRAN/400 statement for 3-49

RPG/400 operation for 3-49

subfiles

BASIC statement for 4-12

C/400 function for 4-12

COBOL/400 statement for 4-12

definition 4-11

write operation *(continued)*

subfiles *(continued)*

RPG/400 operation for 4-12

write-read operation

with no wait, CL command for 3-49

with wait

C/400 function for 3-49

CL command for 3-49

RPG/400 operation for 3-49

write-read operation for subfiles

C/400 function for 4-12

definition 4-12

RPG/400 operation for 4-12

X

XH1 through XH4 (extended help headings) tag

example, sample heading A-163

formatting rules A-163

overview A-163

use in help module 20-4

XMP (example) tag

example, formatting an example A-164

help module 20-5

overview A-164

Z

Z-variable

attributes A-160

definition A-160

Z36ENV dialog variable A-160

ZCANCEL dialog variable A-160

ZDBCS dialog variable A-160

ZDSPSIZ dialog variable A-160

ZEXIT dialog variable A-160

ZJOB dialog variable A-160

ZJOBNBR dialog variable A-160

ZLMTCPB dialog variable A-160

ZMENU dialog variable A-160

ZMNULIB dialog variable A-160

ZSYSNAM dialog variable A-160

ZUSER dialog variable A-160

Customer Satisfaction Feedback

Application System/400
Guide to Programming Application
and Help Displays
Version 2

Publication No. SC41-0011-02

Overall, how would you rate this manual?

	Very Satisfied	Satisfied	Dissatisfied	Very Dissatisfied
Overall satisfaction				

How satisfied are you that the information in this manual is:

Accurate				
Complete				
Easy to find				
Easy to understand				
Well organized				
Applicable to your tasks				
T H A N K Y O U !				

Please tell us how we can improve this manual:

May we contact you to discuss your responses? ☐ Yes ☐ No

Phone: (____) _____ Fax: (____) _____

To return this form:

- Mail it
 - Fax it
 - Hand it to your IBM representative.
- United States and Canada: **800+937-3430**
Other countries: **(+1)+507+253-5192**

Note that IBM may use or distribute the responses to this form without obligation.

Name _____

Address _____

Company or Organization _____


Phone No. _____



Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

ATTN DEPT 245
IBM CORPORATION
3605 HWY 52 N
ROCHESTER MN 55901-7899



Fold and Tape

Please do not staple

Fold and Tape

Customer Satisfaction Feedback

Application System/400
Guide to Programming Application
and Help Displays
Version 2

Publication No. SC41-0011-02

Overall, how would you rate this manual?

	Very Satisfied	Satisfied	Dissatisfied	Very Dissatisfied
Overall satisfaction				

How satisfied are you that the information in this manual is:

Accurate				
Complete				
Easy to find				
Easy to understand				
Well organized				
Applicable to your tasks				
THANK YOU!				

Please tell us how we can improve this manual:

May we contact you to discuss your responses? ☐ Yes ☐ No

Phone: (____) _____ Fax: (____) _____

To return this form:

- Mail it
 - Fax it
- United States and Canada: **800+937-3430**
Other countries: **(+1)+507+253-5192**
- Hand it to your IBM representative.

Note that IBM may use or distribute the responses to this form without obligation.

Name _____

Address _____

Company or Organization _____

Phone No. _____



Cut or
Along


Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES



BUSINESS REPLY MAIL

FIRST CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

ATTN DEPT 245
IBM CORPORATION
3605 HWY 52 N
ROCHESTER MN 55901-7899



Fold and Tape

Please do not staple

Fold and Tape

Cut or
Along



Program Number: 5738-SS1

Printed in Denmark by
Scanprint as, Viby J.

SC41-0011-02

