

# NAG Toolbox for MATLAB

## f07cg

### 1 Purpose

f07cg estimates the reciprocal condition number of a real  $n$  by  $n$  tridiagonal matrix  $A$ , using the  $LU$  factorization returned by f07cd.

### 2 Syntax

```
[rcond, info] = f07cg(norm_p, dl, d, du, du2, ipiv, anorm, 'n', n)
```

### 3 Description

f07cg should be preceded by a call to f07cd, which uses Gaussian elimination with partial pivoting and row interchanges to factorize the matrix  $A$  as

$$A = PLU,$$

where  $P$  is a permutation matrix,  $L$  is unit lower triangular with at most one nonzero subdiagonal element in each column, and  $U$  is an upper triangular band matrix, with two superdiagonals. f07cg then utilizes the factorization to estimate either  $\|A^{-1}\|_1$  or  $\|A^{-1}\|_\infty$ , from which the estimate of the reciprocal of the condition number of  $A$ ,  $1/\kappa(A)$  is computed as either

$$1/\kappa_1(A) = 1/(\|A\|_1\|A^{-1}\|_1)$$

or

$$1/\kappa_\infty(A) = 1/(\|A\|_\infty\|A^{-1}\|_\infty).$$

$1/\kappa(A)$  is returned, rather than  $\kappa(A)$ , since when  $A$  is singular  $\kappa(A)$  is infinite.

Note that  $\kappa_\infty(A) = \kappa_1(A^T)$ .

### 4 References

Higham N J 2002 *Accuracy and Stability of Numerical Algorithms* (2nd Edition) SIAM, Philadelphia

### 5 Parameters

#### 5.1 Compulsory Input Parameters

1: **norm\_p** – string

Specifies the norm to be used to estimate  $\kappa(A)$ .

**norm\_p** = '1' or 'O'

Estimate  $\kappa_1(A)$ .

**norm\_p** = 'I'

Estimate  $\kappa_\infty(A)$ .

*Constraint:* **norm\_p** = '1', 'O' or 'I'.

2: **dl**(\*) – double array

**Note:** the dimension of the array **dl** must be at least  $\max(1, n - 1)$ .

Must contain the  $(n - 1)$  multipliers that define the matrix  $L$  of the  $LU$  factorization of  $A$ .

3: **d(\*) – double array**

**Note:** the dimension of the array **d** must be at least  $\max(1, \mathbf{n})$ .

Must contain the  $n$  diagonal elements of the upper triangular matrix  $U$  from the  $LU$  factorization of  $A$ .

4: **du(\*) – double array**

**Note:** the dimension of the array **du** must be at least  $\max(1, \mathbf{n} - 1)$ .

Must contain the  $(n - 1)$  elements of the first superdiagonal of  $U$ .

5: **du2(\*) – double array**

**Note:** the dimension of the array **du2** must be at least  $\max(1, \mathbf{n} - 2)$ .

Must contain the  $(n - 2)$  elements of the second superdiagonal of  $U$ .

6: **ipiv(\*) – int32 array**

**Note:** the dimension of the array **ipiv** must be at least  $\max(1, \mathbf{n})$ .

Must contain the  $n$  pivot indices that define the permutation matrix  $P$ . At the  $i$ th step, row  $i$  of the matrix was interchanged with row **ipiv**( $i$ ), and **ipiv**( $i$ ) must always be either  $i$  or  $(i + 1)$ , **ipiv**( $i$ ) =  $i$  indicating that a row interchange was not performed.

7: **anorm – double scalar**

If **norm\_p** = '1' or 'O', **anorm** must contain  $\|A\|_1$ .

If **norm\_p** = 'I', **anorm** must contain  $\|A\|_\infty$ .

**anorm** must be computed either before calling f07cd, or else from a copy of the original matrix  $A$ .

**5.2 Optional Input Parameters**1: **n – int32 scalar**

*Default:* The dimension of the array **d** The dimension of the array **ipiv**.  
 $n$ , the order of the matrix  $A$ .

*Constraint:*  $\mathbf{n} \geq 0$ .

**5.3 Input Parameters Omitted from the MATLAB Interface**

work, iwork

**5.4 Output Parameters**1: **rcond – double scalar**

Contains an estimate of the reciprocal condition number.

2: **info – int32 scalar**

**info** = 0 unless the function detects an error (see Section 6).

**6 Error Indicators and Warnings**

Errors or warnings detected by the function:

**info** =  $-i$

If **info** =  $-i$ , parameter  $i$  had an illegal value on entry. The parameters are numbered as follows:

1: **norm\_p**, 2: **n**, 3: **dl**, 4: **d**, 5: **du**, 6: **du2**, 7: **ipiv**, 8: **anorm**, 9: **rcond**, 10: **work**, 11: **iwork**, 12: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

## 7 Accuracy

In practice the condition number estimator is very reliable, but it can underestimate the true condition number; see Section 15.3 of Higham 2002 for further details.

## 8 Further Comments

The condition number estimation typically requires between four and five solves and never more than eleven solves, following the factorization. The total number of floating-point operations required to perform a solve is proportional to  $n$ .

The complex analogue of this function is f07cu.

## 9 Example

```
norm_p = '1-norm';
dl = [0.8823529411764706;
      0.01960784313725495;
      0.1400560224089636;
      -0.01479925303454714];
d = [3.4;
     3.6;
     7;
     -6;
     -1.015373482726424];
du = [2.3;
     -5;
     -0.9;
     7.1];
du2 = [-1;
      1.9;
      8];
ipiv = [int32(2);
       int32(3);
       int32(4);
       int32(5);
       int32(5)];
anorm = 15.1;
[rcond, info] = f07cg(norm_p, dl, d, du, du2, ipiv, anorm)

rcond =
      0.0108
info =
      0
```