

NAG Toolbox for MATLAB

f07fu

1 Purpose

f07fu estimates the condition number of a complex Hermitian positive-definite matrix A , where A has been factorized by f07fr.

2 Syntax

```
[rcond, info] = f07fu(uplo, a, anorm, 'n', n)
```

3 Description

f07fu estimates the condition number (in the 1-norm) of a complex Hermitian positive-definite matrix A :

$$\kappa_1(A) = \|A\|_1 \|A^{-1}\|_1.$$

Since A is Hermitian, $\kappa_1(A) = \kappa_\infty(A) = \|A\|_\infty \|A^{-1}\|_\infty$.

Because $\kappa_1(A)$ is infinite if A is singular, the function actually returns an estimate of the **reciprocal** of $\kappa_1(A)$.

4 References

Higham N J 1988 FORTRAN codes for estimating the one-norm of a real or complex matrix, with applications to condition estimation *ACM Trans. Math. Software* **14** 381–396

5 Parameters

5.1 Compulsory Input Parameters

1: **uplo** – **string**

Indicates how A has been factorized.

uplo = 'U'

$A = U^H U$, where U is upper triangular.

uplo = 'L'

$A = L L^H$, where L is lower triangular.

Constraint: **uplo** = 'U' or 'L'.

2: **a(lda,*)** – **complex array**

The first dimension of the array **a** must be at least $\max(1, \mathbf{n})$

The second dimension of the array must be at least $\max(1, \mathbf{n})$

The Cholesky factor of A , as returned by f07fr.

3: **anorm** – **double scalar**

The 1-norm of the **original** matrix A , which may be computed by calling Missing 'id'. **anorm** must be computed either **before** calling f07fu or else from a copy of the original matrix A .

Constraint: **anorm** ≥ 0.0 .

5.2 Optional Input Parameters

1: **n** – int32 scalar

Default: The second dimension of the array **a**.

n, the order of the matrix *A*.

Constraint: $n \geq 0$.

5.3 Input Parameters Omitted from the MATLAB Interface

lda, work, rwork

5.4 Output Parameters

1: **rcond** – double scalar

An estimate of the reciprocal of the condition number of *A*. **rcond** is set to zero if exact singularity is detected or the estimate underflows. If **rcond** is less than *machine precision*, *A* is singular to working precision.

2: **info** – int32 scalar

info = 0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

info = $-i$

If **info** = $-i$, parameter *i* had an illegal value on entry. The parameters are numbered as follows:

1: **uplo**, 2: **n**, 3: **a**, 4: **lda**, 5: **anorm**, 6: **rcond**, 7: **work**, 8: **rwork**, 9: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

7 Accuracy

The computed estimate **rcond** is never less than the true value ρ , and in practice is nearly always less than 10ρ , although examples can be constructed where **rcond** is much larger.

8 Further Comments

A call to f07fu involves solving a number of systems of linear equations of the form $Ax = b$; the number is usually 5 and never more than 11. Each solution involves approximately $8n^2$ real floating-point operations but takes considerably longer than a call to f07fs with one right-hand side, because extra care is taken to avoid overflow when *A* is approximately singular.

The real analogue of this function is f07fg.

9 Example

```
uplo = 'L';
a = [complex(3.23, 0), complex(1.51, -1.92), complex(1.9, 0.84),
     complex(0.42, 2.5);
     complex(1.51, 1.92), complex(3.58, 0), complex(-0.23, 1.11),
     complex(-1.18, 1.37)];
```

```
        complex(1.9, -0.84), complex(-0.23, -1.11), complex(4.09, +0),  
complex(2.33, -0.14);  
        complex(0.42, -2.5), complex(-1.18, -1.37), complex(2.33, +0.14),  
complex(4.29, +0)];  
anorm = norm(a, 1);  
[a, info] = f07fr(uplo, a);  
[rcond, info] = f07fu(uplo, a, anorm)
```

```
rcond =  
      0.0066  
info =  
      0
```
