

NAG Toolbox for MATLAB

g05lm

1 Purpose

g05lm generates a vector of pseudo-random numbers from a two parameter Weibull distribution with shape parameter a and scale parameter b .

2 Syntax

```
[x, iseed, ifail] = g05lm(a, b, n, igen, iseed)
```

3 Description

The distribution has PDF (probability density function)

$$f(x) = \frac{a}{b} x^{a-1} e^{-x^a/b} \quad \text{if } x > 0,$$

$$f(x) = 0 \quad \text{otherwise.}$$

g05lm returns the value $(-b \ln y)^{1/a}$, where y is a pseudo-random number from a uniform distribution over $(0, 1)$.

One of the initialization functions g05kb (for a repeatable sequence if computed sequentially) or g05kc (for a non-repeatable sequence) must be called prior to the first call to g05lm.

4 References

Kendall M G and Stuart A 1969 *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin

Knuth D E 1981 *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison–Wesley

5 Parameters

5.1 Compulsory Input Parameters

1: **a – double scalar**

a , the shape parameter of the distribution.

Constraint: $a > 0.0$.

2: **b – double scalar**

b , the scale parameter of the distribution.

Constraint: $b > 0.0$.

3: **n – int32 scalar**

n , the number of pseudo-random numbers to be generated.

Constraint: $n \geq 0$.

4: **igen – int32 scalar**

Must contain the identification number for the generator to be used to return a pseudo-random number and should remain unchanged following initialization by a prior call to g05kb or g05kc.

5: **iseed(4) – int32 array**

Contains values which define the current state of the selected generator.

5.2 Optional Input Parameters

None.

5.3 Input Parameters Omitted from the MATLAB Interface

None.

5.4 Output Parameters

1: **x(*) – double array**

Note: the dimension of the array **x** must be at least $\max(1, \mathbf{n})$.

The n pseudo-random numbers from the specified Weibull distribution.

2: **iseed(4) – int32 array**

Contains updated values defining the new state of the selected generator.

3: **ifail – int32 scalar**

0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

ifail = 1

On entry, $\mathbf{a} \leq 0.0$.

ifail = 2

On entry, $\mathbf{b} \leq 0.0$.

ifail = 3

On entry, $\mathbf{n} < 0$.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

```
a = 1;  
b = 2;  
n = int32(5);  
igen = int32(1);  
iseed = [int32(1762543);  
         int32(9324783);  
         int32(42344)];
```

```
int32(742355)];  
[x, iseedOut, ifail] = g05lm(a, b, n, igen, iseed)  
  
x =  
    4.8310  
    0.1006  
    1.8009  
    0.5936  
    0.1031  
iseedOut =  
    16516983  
    2826895  
    4504715  
    8850212  
ifail =  
        0
```
