

NAG Toolbox for MATLAB

f07gs

1 Purpose

f07gs solves a complex Hermitian positive-definite system of linear equations with multiple right-hand sides,

$$AX = B,$$

where A has been factorized by f07gr, using packed storage.

2 Syntax

```
[b, info] = f07gs(uplo, ap, b, 'n', n, 'nrhs_p', nrhs_p)
```

3 Description

f07gs is used to solve a complex Hermitian positive-definite system of linear equations $AX = B$, the function must be preceded by a call to f07gr which computes the Cholesky factorization of A , using packed storage. The solution X is computed by forward and backward substitution.

If **uplo** = 'U', $A = U^H U$, where U is upper triangular; the solution X is computed by solving $U^H Y = B$ and then $UX = Y$.

If **uplo** = 'L', $A = LL^H$, where L is lower triangular; the solution X is computed by solving $LY = B$ and then $L^H X = Y$.

4 References

Golub G H and Van Loan C F 1996 *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Parameters

5.1 Compulsory Input Parameters

1: **uplo** – string

Indicates how A has been factorized.

uplo = 'U'

$A = U^H U$, where U is upper triangular.

uplo = 'L'

$A = LL^H$, where L is lower triangular.

Constraint: **uplo** = 'U' or 'L'.

2: **ap**(*) – complex array

Note: the dimension of the array **ap** must be at least $\max(1, n \times (n + 1)/2)$.

The Cholesky factor of A stored in packed form, as returned by f07gr.

3: **b**(ldb,*) – complex array

The first dimension of the array **b** must be at least $\max(1, n)$

The second dimension of the array must be at least $\max(1, \text{nrhs_p})$

The n by r right-hand side matrix B .

5.2 Optional Input Parameters

1: **n** – **int32 scalar**

Default: The first dimension of the array **ap** and the second dimension of the array **ap**. (An error is raised if these dimensions are not equal.)

n , the order of the matrix A .

Constraint: $n \geq 0$.

2: **nrhs_p** – **int32 scalar**

Default: The second dimension of the array **b**.

r , the number of right-hand sides.

Constraint: **nrhs_p** ≥ 0 .

5.3 Input Parameters Omitted from the MATLAB Interface

ldb

5.4 Output Parameters

1: **b(ldb,*)** – **complex array**

The first dimension of the array **b** must be at least $\max(1, n)$

The second dimension of the array must be at least $\max(1, \text{nrhs_p})$

The n by r solution matrix X .

2: **info** – **int32 scalar**

info = 0 unless the function detects an error (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the function:

info = $-i$

If **info** = $-i$, parameter i had an illegal value on entry. The parameters are numbered as follows:

1: **uplo**, 2: **n**, 3: **nrhs_p**, 4: **ap**, 5: **b**, 6: **ldb**, 7: **info**.

It is possible that **info** refers to a parameter that is omitted from the MATLAB interface. This usually indicates that an error in one of the other input parameters has caused an incorrect value to be inferred.

7 Accuracy

For each right-hand side vector b , the computed solution x is the exact solution of a perturbed system of equations $(A + E)x = b$, where

if **uplo** = 'U', $|E| \leq c(n)\epsilon|U^H||U|$;

if **uplo** = 'L', $|E| \leq c(n)\epsilon|L||L^H|$,

$c(n)$ is a modest linear function of n , and ϵ is the *machine precision*.

If $\hat{x}$ is the true solution, then the computed solution x satisfies a forward error bound of the form

$$\frac{\|x - \hat{x}\|_{\infty}}{\|x\|_{\infty}} \leq c(n) \operatorname{cond}(A, x) \epsilon$$

where $\operatorname{cond}(A, x) = \| |A^{-1}| |A| |x| \|_{\infty} / \|x\|_{\infty} \leq \operatorname{cond}(A) = \| |A^{-1}| |A| \|_{\infty} \leq \kappa_{\infty}(A)$.

Note that $\operatorname{cond}(A, x)$ can be much smaller than $\operatorname{cond}(A)$.

Forward and backward error bounds can be computed by calling f07gv, and an estimate for $\kappa_{\infty}(A)$ ($= \kappa_1(A)$) can be obtained by calling f07gu.

8 Further Comments

The total number of real floating-point operations is approximately $8n^2r$.

This function may be followed by a call to f07gv to refine the solution and return an error estimate.

The real analogue of this function is f07ge.

9 Example

```

uplo = 'L';
ap = [complex(1.797220075561143, +0);
      complex(0.8401864749527325, +1.068316577423342);
      complex(1.057188279741849, -0.467388502622712);
      complex(0.233694251311356, -1.391037210186643);
      complex(1.316353439509685, +0);
      complex(-0.4701749470106329, +0.3130658155999466);
      complex(0.08335250923944192, +0.03676071443037458);
      complex(1.560392977137124, +0);
      complex(0.9359617337923402, +0.9899692192815736);
      complex(0.6603332973655893, +0)];
b = [complex(3.93, -6.14), complex(1.48, +6.58);
     complex(6.17, +9.42), complex(4.65, -4.75);
     complex(-7.17, -21.83), complex(-4.91, +2.29);
     complex(1.99, -14.38), complex(7.64, -10.79)];
[bOut, info] = f07gs(uplo, ap, b)

bOut =
    1.0000 - 1.0000i   -1.0000 + 2.0000i
    0.0000 + 3.0000i    3.0000 - 4.0000i
   -4.0000 - 5.0000i   -2.0000 + 3.0000i
    2.0000 + 1.0000i    4.0000 - 5.0000i
info =
      0

```